



HP ZCentral Software Licensing Guide

SUMMARY

This document describes licensing of HP ZCentral Remote Boost Software and HP ZCentral Connect Software. Remote Boost licensing applies to Remote Boost Sender only; Remote Boost Receiver can be used freely.

Legal information

© Copyright 2013–2015, 2017–2021 HP Development Company, L.P.

Linux® is the registered trademark of Linus Torvalds in the U.S. and other countries.

Windows is either a registered trademark or trademark of Microsoft Corporation in the United States and/or other countries.

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

Ninth Edition: December 2021

First Edition: February 2013

Document Part Number: M26122-003

Third-party software notice

Third-party source code and licenses are redistributed, if required, with HP ZCentral Software.

User input syntax key

Text that you must enter into a user interface is indicated by `fixed-width font`.

Table User input syntax key

Item	Description
<code>Text without brackets or braces</code>	Items you must type exactly as shown
<code><Text inside angle brackets></code>	A placeholder for a value you must provide; omit the brackets
<code>[Text inside square brackets]</code>	Optional items; omit the brackets
<code>{Text inside braces}</code>	A set of items from which you must choose only one; omit the braces
<code> </code>	A separator for items from which you must choose only one; omit the vertical bar
<code>...</code>	Items that can or must repeat; omit the ellipsis

Table of contents

1 ZCentral license types	1
Remote Boost license types	1
Connect license types	1
2 Remote Boost licensing overview	2
Remote Boost floating and CA+ licenses.....	2
Remote Boost version number	2
Remote Boost license version date	3
Remote Boost license policy.....	3
3 Installing a local license key file	5
Configuring Remote Boost Sender to access a local license key file on Windows.....	5
Configuration during Remote Boost Sender installation	5
Configuration after Remote Boost Sender Installation.....	5
Configuring Remote Boost Sender to access a local license key file on Linux.....	6
4 Installing and configuring the FLEXnet license server	7
Before you install the license server	7
License server port configuration	8
Installing the license server on Windows.....	8
Starting and stopping the license server on Windows.....	8
Using LMTTOOLS	9
Installing the license server on Linux.....	9
Accessing the Remote Boost floating license	11
Configuring Remote Boost Sender to access a floating license	11
Down, missing, or moved floating license servers.....	12
Hosting multiple license key files	12
5 Configuring Cloud Access Plus Licenses	13
Configuring Cloud License Server Licenses	13
Creating allowlists for network blocks for Cloud Licensing	13
Configuring local license server licenses.....	13
Using the Remote Boost License Tool	14
Register	15
Validate	15
List.....	16
Config	16
6 Connect licensing overview	18

Connect license types	18
Connect version number	18
Connect license version date	19
Connect license policy	19
Providing a hostname and quantity	20
Installing a ZCentral Connect license file	20
Adding additional connections to a license file	20
Appendix A Troubleshooting licensing	22
Troubleshooting Remote Boost Sender licensing	22
Troubleshooting the FLEXnet license server	22
Troubleshooting Cloud Access Plus licensing	22
Troubleshooting Connect licensing	23
Contacting HP for licensing support	23
Appendix B Cleaning registry references to the Flexnet license server	24
Appendix C Uninstalling the FLEXnet License Server on Windows	25
Appendix D Uninstalling the FLEXnet License Server on Linux	26
Index	27

1 ZCentral license types

The tables in this chapter outline the licenses available for ZCentral products.

For more information about purchasing a license, go to <http://www.hp.com/go/zcentral>.

Remote Boost license types

A Standard, Floating, Cloud Access Plus (CA+), or Trial license is required on each sender (remote) system or virtual machine (VM) except when you use an HP Z series desktop workstation or HP Zbook Mobile Workstation. HP Z workstations include Remote Boost licenses for no charge and are valid until 1 January 2023. After this date, you must obtain one of the previously listed licenses.

The Remote Boost Receiver does not require a license.

Table 1-1 Remote Boost license types

License type	Description	Product number
Standard license	Licenses Remote Boost for one system or VM.	9TS60AAE
Floating license	Licenses Remote Boost for multiple systems or VMs. Requires you to install a license server in your environment. You purchase the Floating license for a specific number of concurrent Remote Boost systems.	9TS61AAE
Trial license	Free, 60-day trial of the Standard license.	9TS60ABE
Cloud Access Plus (CA+)	Licenses Remote Boost for multiple systems or VMs. Requires cloud access or a license server installation in your environment. You purchase the CA+ license for a specific number of concurrent Remote Boost systems.	TCAP01YP

Connect license types

The table in this section describes ZCentral Connect license types that are available.

Table 1-2 Connect license types

License type	Description	Product number
License to use	Enables concurrent Connect sessions up to the quantity of licenses purchased.	9TS59AAE
Trial license	Free, 60-day trial license that supports up to 5 concurrent connections.	9TS59ABE

2 Remote Boost licensing overview

This section describes the licensing of HP ZCentral Remote Boost Software. Remote Boost licensing applies to the Remote Boost Sender only; you can use the Remote Boost Receiver freely.



NOTE: Remote Boost does not require a license on HP Z series desktop workstations or HP Zbook Mobile Workstations until 1 January 2023. After this date, HP Z workstations will require another valid license type.

For detailed Remote Boost information, see the latest version of the *HP ZCentral Remote Boost Software User Guide* that is bundled with HP ZCentral Remote Boost, available at <http://www.hp.com/go/zcentral>. This website might also contain a more recent version of this licensing guide.

You can download, install, and run Remote Boost Sender to verify a connection without a license. If you do not obtain a license, you can still view and interact with the remote desktop. A notification displays in your viewing window, which indicates that the Remote Boost Sender is unlicensed.

Remote Boost floating and CA+ licenses

When you purchase floating or CA+ licenses, you receive a pool of licenses. These licenses dynamically allocate on a first-come, first-served basis whenever Remote Boost Receiver attempts to connect to Remote Boost Sender. You automatically check out a floating or CA+ license when you establish a connection to Remote Boost Sender and check it in when the connection ends.

If multiple receivers connect to a single sender (for example, when conducting a collaboration session), Remote Boost Sender uses only one license. A license is checked out only when the first Remote Boost connection is established.

Floating or CA+ licenses allow a company to purchase, for example, 75 licenses but support a user community of perhaps hundreds of users, as long as no more than 75 users ever attempt to establish connections with separate Remote Boost Senders simultaneously.

Floating licenses require a license server, which you can install on one of the computers running Remote Boost Sender, or you can install the license server on a separate computer. Remote Boost includes an installer for the FLEXnet license server. For installation information, see [Installing and configuring the FLEXnet license server on page 7](#).

CA+ licenses require access to a cloud license server. If your deployment cannot use cloud licensing, either because the site is not connected to the public internet or local management of licenses is necessary, then you can use a local license server instead. For further information, see [Configuring local license server licenses on page 13](#).

Remote Boost version number

The Remote Boost version number contains the three components shown in this section.



NOTE: The version numbering changed between HP Remote Graphics Software (RGS) and HP ZCentral Remote Boost. The last version of RGS is 7.7.x and the first version of Remote Boost is 2020.0.

Figure 2-1 Remote Boost version number components





Table 2-1 Remote Boost version number components

Item	Description
1.	Primary release number —A primary release contains sufficient changes such that interoperability with the prior primary release is not guaranteed by HP. For example, a connection between different primary releases of HP ZCentral Remote Boost Sender and HP ZCentral Remote Boost Receiver might not function at an acceptable quality, or at all.
2.	Minor release number —When the number is not zero, it represents a minor release, which typically introduces new features or enhances existing functionality, as well as including changes from any previous patch releases. A connection between different minor releases (but the same primary release) of HP ZCentral Remote Boost Sender and HP ZCentral Remote Boost Receiver should function at an acceptable level of quality.
3.	Patch release number —When the number is not zero, it represents a patch release, which is typically only for fixing major security issues or defects. A connection between different patch releases (but the same primary release) of HP ZCentral Remote Boost Sender and HP ZCentral Remote Boost Receiver should function at an acceptable quality.


 **NOTE:** Each release of Remote Boost is a complete release of the entire product, regardless of which components have changed.

Remote Boost license version date

Each release of Remote Boost has a license version date that the Remote Boost licensing uses. For example, the Remote Boost 7 license version date is 1 November 2019, which is formatted **2019.1101** (YYYY.MMDD). Viewing the license version date might assist in troubleshooting any licensing issues. Follow the steps outlined here to view the license version date.

1. Right-click the Remote Boost Sender icon in the Windows notification area, and click **About**.
2. Locate the line **License Version Date** like in the following example:

```
License Version Date: 2019.1101
```


 **NOTE:** The license version date should not be confused with the build date. The build date is not used by the Remote Boost licensing mechanism.

Remote Boost license policy

You are only required to purchase a new license for Remote Boost when the version date changes, and the version date only changes for primary releases, such as RGS 7.0 and Remote Boost 2020.0. Therefore, when

you purchase a license for Remote Boost, you are entitled to free upgrades to all future minor and patch releases.

For example, if you purchased an RGS 7 license, you are entitled to free upgrades to versions 7.x.x. However, you would have to purchase a new license to upgrade to Remote Boost 2020.0.

 **NOTE:** Remote Boost licenses also work with older versions of RGS. For example, a Remote Boost 2020.0 license can be used with RGS 7.

The following table demonstrates example RGS and Remote Boost version numbers and license version dates.


 **IMPORTANT:** The values in this table might not match actual releases of Remote Boost or RGS.

Table 2-2 Remote Boost and RGS version number and license version date examples

Version number	Release type	License version date
2020.1	Minor release	2019.1101
2020.0.1	Patch release	2019.1101
2020.0	Primary release	2019.1101
7.1	Minor release	2014.0401
7.0.1	Patch release	2014.0401
7.0	Primary release	2014.0401

3 Installing a local license key file

This chapter describes how to install a local license key file. License key files are provided only for Standard and Floating licenses.

Configuring Remote Boost Sender to access a local license key file on Windows

Remote Boost Sender can be configured to access a local license key file either during installation or after installation.

Configuration during Remote Boost Sender installation

During Remote Boost Sender installation (as described in the *HP ZCentral Remote Boost User Guide*), you will be presented with a dialog box that asks you to install the Remote Boost Sender license. For local licenses, select **Install a license file on this system**, and click **Next**.

Browse to the location where you saved your license key file, select it, and select **Open**.

 **NOTE:** License key files must end with the .lic suffix.

The license key file will be copied from the location you specified to the Remote Boost Sender installation directory:

Default location:

```
C:\Program Files\HP\Remote Graphics Sender
```

Configuration after Remote Boost Sender Installation

If, during Remote Boost installation, you select **I do not yet have a license file**, you can specify the location of the license key file post-installation in one of two ways.

The first way to specify the location of the license key file post-installation is to copy the license file into the Remote Boost Sender installation directory:

Default location:

```
C:\Program Files\HP\Remote Graphics Sender
```

The second way to specify the location of the license key file post-installation is by using the `LM_LICENSE_FILE` environment variable. To set this environment variable:

1. In **Windows Search**, type `env`, and choose **Edit the system environment variables**.
2. Select **Environment Variables**.
3. Under **System variables**, click **New**. This opens the **New System Variable** dialog box.
4. Type `LM_LICENSE_FILE` as the variable name.

5. Enter the path to the local license key file as the variable value. You can enter multiple paths. Separate them by semicolons, such as:

```
C:\licenses;C:\backuplicenses
```

Remote Boost Sender will sequentially examine each folder from left to right until it finds a folder containing a valid local license key file.



NOTE: If a license key file is specified and found during Remote Boost Sender installation, it will be copied into the folder `C:\Program Files\HP\Remote Graphics Sender`. License key files found in folders specified by the `LM_LICENSE_FILE` environment variable are not copied; they are read in place.

If a license key file location is specified during Remote Boost Sender installation and is also specified by the `LM_LICENSE_FILE` variable, Remote Boost Sender will look in both locations for a valid local license key file at startup.

Configuring Remote Boost Sender to access a local license key file on Linux

For Remote Boost Sender on Linux to find the local license key file, it must be saved in this directory on the remote computer:

```
/etc/opt/hpremote/rgsender
```


4 Installing and configuring the FLEXnet license server

The FLEXnet license server is required only if you are using the HP Remote Boost floating license.


Before you install the license server


This section provides information to help you plan your installation of the FLEXnet license server.

- The 64-bit version of the FLEXnet license server is provided with Remote Boost.
- Remote Boost FLEXnet server version 11.17.2.0 is required beginning with Remote Boost 20.2. If you have a previous version installed, you must uninstall it first. Previous versions of RGS and Remote Boost can still check out licenses from the newer license server. You can use licenses from older license servers on newer servers.


 **NOTE:** You can run only the FLEXnet license server included with Remote Boost on Windows and Linux® operating systems.


- The license server is usually installed on a computer other than one of the computers running Remote Boost Sender. However, nothing prohibits installing the license server on an Remote Boost Sender computer.
- The following processes run when the license server is active on Windows:
 - HPQ.exe
 - lmgrd.exe (x2)

 **NOTE:** When two separate `lmgrd.exe` processes run, one runs as a service.

 **NOTE:** The FLEXnet license server for Linux has two associated processes, `lmgrd` and `HPQ`.

- The `HPQ.exe` vendor daemon interfaces with Remote Boost Sender and provides license server functions specific to HP, such as counting Remote Boost floating licenses.

 **NOTE:** Other products, such as HP OpenView, also have a vendor daemon named `HPQ.exe`. The different `HPQ.exe` executable files might not be interchangeable. Furthermore, only one `HPQ.exe` vendor daemon at a time can execute on the license server computer. Therefore, a single computer cannot run two FLEXnet license servers simultaneously.

 **NOTE:** Both processes, `lmgrd` and `HPQ`, might require port forwarding in firewalled environments. You can customize these ports in the license key file.

The Remote Boost license does not support FLEXnet's three-server redundancy capability, also known as *triad license servers*.

- During license server installation on Windows, the FLEXnet administration utility, LMTTOOLS, is installed. LMTTOOLS provides a graphical user interface that allows you to administer the license server. See [Using LMTTOOLS on page 9](#).

License server port configuration

For a Remote Boost Sender to connect to a license server that's behind a firewall, two ports need to be opened. One for the license server manager and one for the vendor daemon. These ports can be specified in the floating license key file.

For the license server manager port, if no TCP/IP port number is specified in the floating license key file, one of the default ports in the range of 27000 - 27009 is used.

For the vendor daemon port, if no TCP/IP port number is specified in the floating license key file, the port is chosen by the operating system at run-time. There is no set range.

To change the default ports, specify the ports in the floating license key file in this format:


```
SERVER MyLicenseServer.hp.com <manager port>
```

```
VENDOR HPQ PORT=<vendor port>
```

The following example will set the manager port to 27010 and the vendor port to 27020:

```
SERVER MyLicenseServer.hp.com 27010
```

```
VENDOR HPQ PORT=27020
```

 **IMPORTANT:** Only modify the ports in the floating license key file. Further modifications can invalidate the license key.

Installing the license server on Windows

To install the license server, perform the following steps.

1. Locate the FLEXnet installation executable file, `Setup.exe`, in the following location in the Remote Boost installation package:
`/flexlm/Setup.exe`
2. Move the `Setup.exe` file to your license server computer.
3. Double-click **Setup.exe** to begin installation of the license server. If an installation of an older version of the license server is detected, you will be prompted to uninstall it. If you uninstall the older server this way, you might be prompted to restart after the uninstallation finishes. If you select to restart, you must restart the installation of the new server when the system starts up again. You can change the default installation folder, `C:\Program Files\HP\ZCentral Remote Boost FlexLM`, to another folder. If the installation is successful, a notification indicating **InstallShield Wizard Complete** is displayed.

Starting and stopping the license server on Windows

You can start and stop the license server in two ways:

- Using Windows Services—Open the Windows **Control Panel**, select **Administrative Tools**, and then select **Services**, which brings up the **Services** dialog box. Next, open the properties dialog box for the Remote Graphics FlexLM License Server Service, and click **Start**. Because the license server is installed with a Startup type of Automatic, the license server will also start when the computer is restarted. To stop the license server, click **Stop**.
- Using the Service Control (SC) command—The SC command can be used in a Command Prompt window when run as an administrator to start and stop the license server.

```
sc start "Remote Graphics FlexLM License Server Service"
```

```
sc stop "Remote Graphics FlexLM License Server Service"
```

Using LMTOOLS

LMTOOLS can be executed from the Start menu as follows:

For Windows 7:

Start>All Programs>HP>Remote Graphics FlexLM>lmtools

For Windows 10:


Start >HP >lmtools

LMTOOLS can be used for tasks such as the following:

- Configuring the license server
- Adding licenses
- Re-reading the license file
- Viewing system information and the license server status
- Troubleshooting issues with the license server

 **NOTE:** Although LMTOOLS provides the **Start Server** and **Stop Server** buttons (under the **Start/Stop/Reread** tab), HP recommends that the license server be started and stopped using the methods described in [Starting and stopping the license server on Windows on page 8](#).

For detailed information about this license server and LMTOOLS, go to <http://www.reverera.com>.

 **NOTE:** LMTOOLS is available on Windows only.

Installing the license server on Linux

Follow the steps outlined here to install the license server on Linux.

 **NOTE:** The license server requires that `lsb` is installed. Be sure to meet this requirement before attempting to run the license server.

- Copy the FlexLM server package to a directory (for example, `/opt/hpremove/licensing`).
- Extract the tar archive with the command:

```
/usr/bin/tar xvf flexlm-server.tar.gz
```

- Change ownership of the directory and executable files to the user account that will run the daemon (FlexLM recommends using a non-root account).
- Copy the license file or files to a directory that is accessible by the owner of the license tools (For instance, `/opt/hpremove/licensing`).
- Create a script that launches `lmgrd` at boot time as described in the next steps.
- On UNIX, or any SysV system, edit the appropriate boot script, which might be `/etc/rc.boot`, `/etc/rc.local`, `/etc/rc2.d/Sxxx`, `/sbin/rc2.d/Sxxxx`. Include commands similar to the following example. See the notes section of the script for a full explanation.

```
/bin/su daniel -c 'echo starting lmgrd > /opt/hpremove/licensing/
boot.log'

/bin/nohup /bin/su daniel -c 'umask 022; \

/opt/hpremove/licensing/flexlm-server/64-bit/lmgrd -c \

/opt/hpremove/licensing/license.dat >> \

/opt/hpremove/licensing/boot.log'

/bin/su daniel -c 'echo exiting >> /opt/hpremove/licensing/boot.log'
```

- On any UNIX or Linux SystemD computer (RHEL or CENTOS 7.* and up), create a new service unit file at `/etc/systemd/system/flexlic.service` with the following content:

```
[Unit]

Description= HP RGS Flexnet License Start Service

After=network.target

[Service]


Type=simple

ExecStart=/opt/hpremove/licensing/start.sh TimeoutStartSec=0

[Install]

WantedBy=default.target
```

Run the commands `systemctl daemon-reload` and `systemctl enable flexlic.service` to allow service to start at next, and every, system boot.

 **NOTE:** An alternative method to creating a service enabled at boot is to set an `@reboot` cron job. However, the license server will depend on the cron service working properly.

- Create a boot script at `/opt/hpremove/licensing/start.sh` with commands like the following:

```
#!/bin/bash

/bin/su daniel -c 'echo starting lmgrd > /opt/hpremove/licensing/
boot.log'

/bin/su daniel -c 'umask 022; \

/opt/hpremove/licensing/flexlm-server/64-bit/lmgrd -c \
```


```
/opt/hpremove/licensing/license.dat >> \  
/opt/hpremove/licensing/boot.log'  
/bin/su daniel -c 'echo exiting >> /opt/hpremove/licensing/boot.log'
```

Note the following points about these scripts:

- All paths must be specified in full because paths cannot be assumed at boot time.
- The `su` command is used to run `lmgrd` as a non-root user `daniel`. HP recommends that `lmgrd` not run as root because it is a security risk to run any program as root that does not require root permissions. `lmgrd` does not require root permissions.
- Daniel has a `cs` login, so all commands executed as `daniel` must be in `cs` syntax. All commands not executed as `daniel` must be in `/bin/sh` syntax to match that used by the boot scripts.

Accessing the Remote Boost floating license

This section describes how to access the Remote Boost floating license. After you obtain your floating license key file, store it on the license server in accordance with the FLEXnet license server configuration requirements.

 **NOTE:** When you acquire an Remote Boost floating license key, you provide your license server hostname. The signature included in the license key file reflects the hostname that you provide; changing the hostname within the license key file to a different license server invalidates the license key. If you need to change your license server hostname, contact the appropriate HP Regional License Center.

Configuring Remote Boost Sender to access a floating license

Remote Boost Sender can be configured to access a floating license by setting the `LM_LICENSE_FILE` environment variable to point to the Remote Boost license server. Specify the location of the license server in this format:

```
<port>@<host>
```

 **NOTE:** This location should match the values from the `SERVER` line in the floating license file.

If a port number isn't specified, the default port 27000 is used. See the following examples:


```
@MyLicenseServer.hp.com
```

```
@15.2.21.129
```

```
27002@MyLicenseServer.hp.com
```

Multiple server locations can be entered, separated by colons, as in the following example:

```
27000@15.232.16.2:@MyLicenseServer.hp.com:27002@BackupServer.hp.com
```

 **NOTE:** Remote Boost Sender will sequentially examine each listed license server from left to right until it finds a license server containing a valid Remote Boost license.

Down, missing, or moved floating license servers

If a license server is down, missing, or has been moved, a Remote Boost connection might fail. Depending on where the license server is listed in LM_LICENSE_FILE, Remote Boost might wait until a network timeout occurs when trying to communicate with the license server.

If the timeout is greater than Remote Boost Receiver's **Dialog** timeout (defaulted to 15 seconds), then a connection will not be made because Remote Boost expects the connection to be made before the timeout is reached.


To correct this issue, increase the timeout to 60 seconds or remove the reference to moved or nonexistent license servers in the LM_LICENSE_FILE environment variable. If the license server is down, resolve that issue and then retry using Remote Boost.

If you still experience issues, you might need to clean the Windows registry. See [Cleaning registry references to the Flexnet license server on page 24](#) for more information.

Hosting multiple license key files


If you have multiple license key files, possibly due to purchasing a new Remote Boost version or even licenses from different vendors, they can be hosted in a few different ways.

- Multiple license servers, each hosting one license file. Configure the client computers to look to all servers that host licenses.
- One license server hosting multiple license files. Each license file and associated vendor application (HPQ.exe for Remote Boost) must be valid for the version of the license server. License files should be listed in a semicolon-delimited list when running lmgrd.

 **NOTE:** If you are running the license server as a service on Windows, you can edit the service parameters in LMTOOLS under **Config Services**. Select the **Service Name** to edit, and modify the **Path to the license file** to point to the directory where the license files are located. Select **Save Service** to save the changes. You must restart the service for changes to take effect.

The service does not allow a semicolon-delimited list of license file names. Instead, all licenses found in the specified path will be used.

- One license server hosting a combined license file. To be able to combine licenses, they must have been originally created with the same server information. This means that the SERVER lines must be the same in all the license files. If the licenses meet these conditions, then you can create a single file by copying the contents of all the files to a single file. Delete any redundant SERVER or VENDOR lines. Be sure that you don't edit the content or it will invalidate the license signature.

 **NOTE:** To use multiple licenses of the same product, the license key file might have to be regenerated. This means that the FEATURE and INCREMENT lines in the license key file describe the license mode for a product. Only the first FEATURE line for a feature name is processed by the vendor daemon. If you want to have additional copies of the same feature, then you must get the license key file re-generated with multiple INCREMENT lines instead.

For further information about license server configurations, go to <http://www.reverera.com>.

5 Configuring Cloud Access Plus Licenses

This chapter applies only when using Cloud Access Plus (CA+) licenses.

Configuring Cloud License Server Licenses

To use the Cloud Licensing Service on a Remote Boost deployment, you must register each Remote Boost Sender. You receive a registration code when you purchase licenses from Teradici. You can use this registration code multiple times.

Example of registration codes: **ABCDEFGH12@AB12-C345-D67E-89FG**. After you install the Remote Boost Sender, you receive a tool to register the device with the Cloud License Server. You can use the Remote Boost licensing tool for the following tasks:

1. Register your device with the cloud server, using the register action.
2. Validate that you have the correct license entitlements on the server using the validate action.
3. List all available license entitlements using the list action.
4. Configure the sender to use a proxy service using the config action.

See [Using the Remote Boost License Tool on page 14](#) to learn how to use the Remote Boost License Tool.

Creating allowlists for network blocks for Cloud Licensing

If you use Cloud Licensing, you must include the following locations in the allowlist.

- teradici.flexnetoperations.com
- teradici.compliance.flexnetoperations.com

Alternatively, you can also include the following network blocks in the allowlist:

- Production: 64.14.29.0/24
- Disaster Recovery: 64.27.162.0/24

The following network blocks are not currently in use, but might also be used in the future:

- Production: 162.244.220.0/24
- Disaster Recovery: 162.244.222.0/24


Configuring local license server licenses

In deployments where Remote Boost Senders cannot access the internet, or where cloud-based licensing is not permitted or wanted, you can use a local license server instead. You must install and configure a Teradici-specific license server called the PCoIP License Server. This PCoIP License Server manages Cloud Access Plus licenses in your private environment.

In this case, you must ask the Teradici support team to convert your licenses. You can find these instructions in the email that you received with your registration code. For detailed instructions about installing, configuring, and managing a local license server, see the following guides. At the time of publishing, the latest version of the following two documents is located at:

Teradici License Server (Offline Environments) 20.10: https://www.teradici.com/web-help/pcoip_license_server/20.10/offline/

Teradici License Server (Online Environments) 20.10: https://www.teradici.com/web-help/pcoip_license_server/20.10/online/

 **IMPORTANT:** After you install your local license server, you must configure your Remote Boost Sender to point to this server. You can use the Remote Boost Licensing Tool to:

1. Configure your device to point to your local license server using the config action and passing the `--license-server-url` parameter.
2. Confirm that you have the correct license entitlements on the server using the validate action and passing the `--license-server-url` parameter.
3. List all available license entitlements using the list action and passing the `--license-server-url` parameter.
4. Configure the sender to use a proxy service if applicable using the config action.

See [Using the Remote Boost License Tool on page 14](#), for instructions about using the `config` command to set this URL.

Using the Remote Boost License Tool

The Remote Boost License Tool provides the administrator with four actions.

- `register`: Registers your device with the cloud and configures the Remote Boost Sender settings to point to the cloud license service.
- `validate`: Verifies the system's licensing configuration. A successful response indicates that a valid license is found on the server.
- `list`: Lists your license entitlements from a Cloud License Server or a local license server.
- `config`: Allows you to configure a variety of Remote Boost Sender licensing settings.


You can find the `rb-license-tool` in the Remote Boost Sender installation directory.


Windows default location:


```
C:\Program Files\HP\Remote Graphics Sender\rb-license-tool.exe
```

Linux default location:

```
/opt/hpremove/rgsender/rb-license-tool
```


 **IMPORTANT:** Run the `rb-license-tool` with administrative privileges.


 **NOTE:** Running this tool generates a log file `rb-license-tool.log`, which is also found in this directory.

 **NOTE:** For a full list of command options, run `rb-license-tool -h`.

Register

Use the `register` command to register your device with the cloud and configure the Remote Boost Sender settings to point to the cloud license service.


 **NOTE:** You do not need to register the Remote Boost Sender if using a local license server.

 **NOTE:** Stop the `Rgsender` service before issuing this command, and restart it after the command is complete for the changes to take effect.


- Navigate to the Remote Boost Sender installation directory.
- Run the tool, and pass the following command:

```
rb-license-tool register --proxy-server x.x.x.x --proxyport xxxx --
registration-code xxxxxxxxxxxx@xxxx-xxxx-xxxx-xxxx --no-vm-uuid --no-
write-properties --prioritize-cloud-checkout -vv
```

- `--proxy-server` and `--proxy-port` are optional. These properties are required if you are running behind a proxy server.
- `--registration-code` is required.
- `--no-vm-uuid` is optional. By default, VM UUID is used as host ID to register the Remote Boost Sender to the Cloud License Server. If `no-vm-uuid` is included, the MAC address is used as host ID to register the Remote Boost Sender.

 **NOTE:** This applies only to a VM, not bare metal.

- `-v` is optional. This flag stands for verbose and provides more information into the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.
- `-vv` is optional. This flag stands for extra verbose and even more information is output to the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.
- `--no-write-properties` is optional. Passing this property skips the step to write new properties to the `rgsenderconfig` file.
- `--prioritize-cloud-checkout` is optional. Passing this property configures the Remote Boost Sender to check out from the cloud server first.

 **NOTE:** This property can save time at checkout if you prefer a cloud license checkout.

Validate

Use the `validate` command to verify the system's licensing configuration.

- Navigate to the Remote Boost Sender installation directory.
- Run the tool, and pass the following command:

```
rb-license-tool validate --proxy-server x.x.x.x --proxy-port xxxx --
license-server-url https://xxx.xxx.com:xxxx/request -vv
```

- `--proxy-server` and `--proxy-port` are optional. Required if you are running the command behind a proxy server.
- `-l` or `--license-server-url` is optional. You can specify the extra local license server in the command line for the license tool to validate the licenses against. If included, `validate` first looks for the Cloud License Server for validation and then looks for a local license server. If both are successful, both return a success.
- `-v` is optional. This flag stands for verbose and provides more information into the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.
- `-vv` is optional. This flag stands for extra verbose and even more information is output to the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.

List

Use the `list` command to list your license entitlements from a Cloud License Server or a local license server.

- Navigate to the Remote Boost Sender installation directory.
- Run the tool, and pass the following command:

```
rb-license-tool list --proxy-server x.x.x.x --proxy-port xxxx --
license-server-url https://xxx.xxxx.com:xxxx/request -vv --detailed
```

- `--proxy-server` and `--proxy-port` are optional. These properties are required if you are running behind a proxy server.
- `-l` or `--license-server-url` is optional. You can specify the extra local license server in the command line for license tool to list the license information against. If included, the `list` command first looks for Cloud License Server to list licenses against and then looks for a local license server. If both are successful, both return successfully.
- `-v` is optional. This flag stands for verbose and provides more information into the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.
- `-vv` is optional. This flag stands for extra verbose and even more information is output to the log file by changing the default of ERROR to INFO. This property can be helpful when troubleshooting.
- `-d` or `--detailed` is optional. If included, the output has more details and is not well formatted.

Config

You can use several commands to configure license settings.



NOTE: Stop the Rgsender service before issuing this command, and restart it after the command is complete for the changes to take effect.



NOTE: Only the parameters that pass are configured; the rest remain unchanged.

- Navigate to the Remote Boost Sender installation directory.
- Run the tool, and pass the following command:

```
rb-license-tool config --proxy-server x.x.x.x --proxyport xxxx --no-vm-uuid --license-server-url https://xxx.xxxx.com:xxxx/request --no-write-properties --prioritize-cloud-checkout
```

- `--proxy-server` and `--proxy-port` configures the proxy server settings. These settings are required if you are running behind a proxy server.
- `--no-vm-uuid` configures the Remote Boost Sender to use a MAC address, not a VM UUID.



NOTE: This property applies only to a VM, not bare metal.

- `-l` or `--license-server-url` configures the extra license server URL information for the sender to use. Configure this parameter to point to a local license server.
- `--no-write-properties` is optional. Passing this property skips the step to write the property values to the `rgsenderconfig` file.
- `--prioritize-cloud-checkout` configures the Remote Boost Sender to check out from the cloud server first.



NOTE: This property can save time at checkout if you prefer a cloud license checkout.

6 Connect licensing overview

This section describes licensing of HP ZCentral Connect Software. ZCentral Connect licensing applies to the Manager software only. Complimentary software, ZCentral Connect Agent and ZCentral Connect Client can be installed and used without an additional license.

ZCentral Connect licensing is based on a license key file that is obtained from HP after you purchase a LTU (License to Use) license. The license file is checked by the Manager software each time a user starts a new session with a host. New sessions will be denied once the licensed maximum is reached. This number is defined in the license file, denoted as "Qty=N".

For detailed ZCentral Connect information, see the latest version of the *HP ZCentral Connect User Guide* bundled with HP ZCentral Connect, available at <http://www.hp.com/go/zcentral>. You can go visit this website for information on how to download a free 60 day trial license supporting up to five connections, or for information about purchasing and renewing a license.



NOTE: You can download, install, and run ZCentral Connect without a license. However, you cannot establish any new sessions between a user and host without a valid license file.

Connect license types

ZCentral Connect uses a local license file to license the software and does not support configuring a license server.

The following ZCentral Connect license types are available:

- **License to Use**—You can purchase this license type from HP to support the number of concurrent connections needed for your deployment.
- **Trial license**—HP offers a free, 60-day trial license for ZCentral Connect which supports up to 5 concurrent connections.

For more information about downloading ZCentral Connect and purchasing a license, go to <http://www.hp.com/go/zcentral>.



NOTE: Except for 60-day trial license, ZCentral Connect licenses never expire. However, a new license purchase is required to upgrade to a newer primary version of ZCentral Connect. For more information, see [Connect license policy on page 19](#).

Connect version number

The ZCentral Connect version number contains the four components show in the following example.

Figure 6-1 ZCentral Connect version number components






Table 6-1 ZCentral Connect version number components


Item	Description
1.	Primary release number —A primary release typically contains upgrades and changes significant enough that interoperability with previous primary releases is not guaranteed by HP.
2.	Minor release number —When the number is not zero, it represents a minor release, which typically introduces new features or enhances existing functionality, as well as including changes from any previous patch releases.
3.	Build number —This number represents a build within a release. It is an incremental value that helps HP identify the specific build of a release.
4.	Patch release number —When the number is not zero, it represents a patch release, which is typically only fixing major security issues or defects.

 **NOTE:** Each release of ZCentral Connect is a complete release of the entire product, regardless of which components have changed.

 **NOTE:** Connect and Remote Boost are part of the same software solution called ZCentral. While the best user experience requires customers to have the most up-to-date versions of ZCentral software, ZCentral Connect supports older versions of Remote Boost, formerly known as HP RGS. Using ZCentral Connect with an older Remote Boost version will limit some of its management and brokering functionality.

Connect license version date

The license version date in your license file can be located on the first FEATURE line. It is formatted as YYYY.MMDD and typically corresponds to the date your license was generated. This version date is used by the ZCentral Connect licensing mechanism to determine which primary release your license file supports.

 **NOTE:** The license version date should not be confused with the build date. The build date is not used by the ZCentral Connect licensing mechanism.

Connect license policy

You are only required to purchase a new license for ZCentral Connect when a new primary version of the software is released, such as ZCentral Connect 20.0. Therefore, when you purchase a license for ZCentral Connect you are entitled to free upgrades to all future minor and patch releases.


For example, if you purchased an ZCentral Connect 20.0 license, you are entitled to free upgrades to versions 20.x.x.x. However, you would have to purchase a new license to upgrade to the next primary release of ZCentral Connect.

 **NOTE:** You can view the version of your ZCentral Connect software by logging on to the Administrator Portal of the ZCentral Connect Manager and viewing the About section.

Providing a hostname and quantity

When you acquire a ZCentral Connect Manager license file, you will need to provide the server hostname where you intend to install and run the Manager on. To find the hostname of the server, type 'hostname' into a Windows Command Prompt.

You will also need to provide a quantity which represents the number of concurrent sessions you wish to support. The typical use case is to redeem the entire quantity purchased, however it is possible to redeem partial quantities to provide licensing for sessions in multiple ZCentral Connect Managers.

 **NOTE:** The signature included in the license file reflects the hostname and quantity that you provided. Changing either field within the license file will invalidate the license key. If you need to change your Manager server hostname, or if you wish to increase your number of connections, contact the appropriate HP Regional License Center: <https://myhplicensing.hp.com/cwp-ui/static/contactus>


Installing a ZCentral Connect license file


Follow the steps outlined here to install a ZCentral Connect license file.

- Copy the license file to the ZCentral Connect Manager data directory:

```
%PROGRAMDATA%\HP\ZCentralConnectManager
```
- As administrator, use the Services.msc app to restart the HP ZCentral Connect Manager service.

 **NOTE:** The ZCentral Connect Agent and ZCentral Connect Client do not require a license file.

 **NOTE:** License files must end with the .lic suffix.

 **NOTE:** ZCentral Connect licensing mechanism is limited to checking out a single license file at a time. After upgrading your license, it is recommended that you keep only the latest license in the data directory.

Adding additional connections to a license file

To add additional connections to an existing license, purchase the additional quantity for the same major version that your current license supports. Then generate a new license key file containing the combined quantity of new and existing connections.

1. To generate the combined license key, you must first redeem the newly purchased license file. Use the same host name as your original license.
2. After you redeem the license file, send a request for a combined license key to e-sw-ops-support@hp.com. In the request, include one of the following proofs of purchase for the license files that you are combining:
 - EON (Entitlement Order Number)
 - Entitlement Certificate, a pdf file that you receive after you redeem a license


- A copy of the EDR (electronic delivery receipt)
3. After you receive the new license key containing the combined quantity of licenses, remove the original license key file from the %PROGRAMDATA% file, and replace the original file with the new file.
 4. Follow the steps in [Installing a ZCentral Connect license file on page 20](#) to install the new license file.

A Troubleshooting licensing

In this section, you learn how to troubleshoot licensing issues.

Troubleshooting Remote Boost Sender licensing

To help debug licensing problems, Remote Boost Sender records licensing failures in a log file.

 **TIP:** The default log file is `rg.log`, but it might vary if you did custom logging configuration. See the *HP ZCentral Remote Boost User Guide* for more information about Remote Boost Sender logging.

If licensing fails, the string **FlexLM** will be added to the log file. The remainder of the entry will indicate where Remote Boost Sender is searching for the license key file.

- For local licenses, the location will be the path you specified either during or after installation (see [Installing a local license key file on page 5](#)).
- For floating licenses, the location will be the hostname and port number used to contact the license server (see [Accessing the Remote Boost floating license on page 11](#)).

However, in both cases, the log entry does not identify the specific cause of a licensing failure. For local licenses, failure to locate the Remote Boost license key file is not differentiated from an Remote Boost license key file that is found but contains an invalid license. Likewise, for floating licenses, failure to contact the license server is not differentiated from a license server that is contacted but has an invalid Remote Boost license.

Troubleshooting the FLEXnet license server


To help debug licensing problems, check the license server log file.

 **NOTE:** The log file name and location can vary based on installation.

- For Windows license servers, you can use LMTTOOLS to view the log file and server status. You can query the current status of the license server under **Server Status**. For license servers running as a service, you can view the service logs under **Config Services**.
- For Linux license servers, the log file is specified in the script that launches `lmgrd`.

Troubleshooting Cloud Access Plus licensing

To help debug licensing problems, Remote Boost Sender records licensing failures in a log file.

 **TIP:** The default log file is `rg.log`, but the name might vary if you made a custom logging configuration. See the *HP ZCentral Remote Boost User Guide* for more information about Remote Boost Sender logging.

If licensing for Cloud Access Plus fails, see the log file for detailed error messages.

To debug environments that are configured to use Cloud Access Plus licenses, use the license tool provided to gain insight to license rights and other license issues. See the [Using the Remote Boost License Tool on page 14](#) for more details on usage.

To debug a local license server deployment, see [Troubleshooting licensing on page 22](#).

Teradici License Server (Offline Environments) 20.10: https://www.teradici.com/web-help/pcoip_license_server/20.10/offline/

Teradici License Server (Online Environments) 20.10: https://www.teradici.com/web-help/pcoip_license_server/20.10/online/

Troubleshooting Connect licensing

There are several reasons licensing can fail for the service account:


1. The license file is not located in the correct directory. Verify that the license file is located in:

```
%PROGRAMDATA%\HP\ZCentralConnectManager
```

2. The license file is expired. Check your license file for its expiration date found on the first line, in the format DD-MMM-YYYY.

 **NOTE:** This only applies to a trial license type.


3. The current software version is not supported by the license file. See [Connect license version date on page 19](#) for details.
4. The license file has been edited. If any of the text in the license file has been edited, the signature becomes invalid.
5. The license file has a hostname other than the server where you are running the Manager. Verify that the server where you installed the Manager has the same hostname that you provided during the license redemption process. See [Providing a hostname and quantity on page 20](#) for details.

 **NOTE:** A trial license does not require a hostname.

To help debug licensing problems, ZCentral Connect Manager records licensing checkout failure warnings in a log file. The log file, Manager.log, is located in:

```
%PROGRAMDATA%\HP\ZCentralConnectManager
```

If a licensing checkout fails, an entry containing the string “License Checkout warning for feature:” will be added to the log file. The remainder of the entry will indicate which checkout error occurred.

 **NOTE:** These warnings are intended to provide insight. It is sometimes expected to have a license warning written to the log. The system can write a warning about failure to check out an LTU license, but successfully check out a Trial license for example. This is the intended behavior.


Contacting HP for licensing support

If you have questions or need assistance with Remote Boost licensing, go to the following:

<https://myhplicensing.hp.com/cwp-ui/static/contactus>

B Cleaning registry references to the Flexnet license server

This appendix provides supplemental information about removing FlexLM references from the Windows registry. The registry keys listed in this appendix are not removed during uninstallation of Remote Boost and might need to be removed manually if you are experiencing issues using a Flexnet server.


 **CAUTION:** Back up the registry prior to making any changes. See Windows documentation for more information.

When a FlexLM license server is used with RGS, the FlexLM libraries will add the license server information to the following registry keys:

- HKLM\SOFTWARE\FLEXlm License Manager\HPQ_LICENSE_FILE
- HKLM\SYSTEM\ControlSet001\Control\Session Manager\Environment\LM_LICENSE_FILE
- HKLM\SYSTEM\ControlSet001\Control\Session Manager\Environment\HPQ_LICENSE_FILE
- HKLM\SYSTEM\ControlSet002\Control\Session Manager\Environment\LM_LICENSE_FILE
- HKLM\SYSTEM\ControlSet002\Control\Session Manager\Environment\HPQ_LICENSE_FILE
- HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\LM_LICENSE_FILE
- HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\HPQ_LICENSE_FILE
- HKEY_USERS\.DEFAULT\Software\FLEXlm License Manager\LM_LICENSE_FILE

 **NOTE:** Some keys might not be present in your registry.

In some cases, FlexLM might use other registry entries. To find them, search the registry for keys named either LM_LICENSE_FILE or HPQ_LICENSE_FILE. The value of these keys will be the license server paths, as specified by the environment variables. See [Configuring Remote Boost Sender to access a floating license on page 11](#) for details on these values and how they are set.

 **CAUTION:** Any registry keys named LM_LICENSE_FILE can be used by any application that accesses a Flexnet license server on the system. If other applications besides Remote Boost are using a Flexnet license server, they might be adversely impacted by any changes made to the LM_LICENSE_FILE registry entries. Any registry keys named "HPQ_LICENSE_FILE" can be used by any HP application that accesses a FlexLM license server. If other HP applications besides Remote Boost are using a Flexnet license server, they could be adversely affected by any changes made to the HPQ_LICENSE_FILE registry entries.

C Uninstalling the FLEXnet License Server on Windows

Follow the step here to uninstall the FLEXnet License Server on Windows.

- ▲ Open the **Programs and Features** item in **Control Panel**, and uninstall the entry corresponding to HP Remote Graphics FlexLM.

D Uninstalling the FLEXnet License Server on Linux

Follow the step here to uninstall the FLEXnet License Server on Linux.

- ▲ Remove the lmgrd, lmutil, and hpq files that were provided in the FlexLM server package. Other cleanup steps might be required, depending on how the license server was installed (see [Installing the license server on Linux on page 9](#)).

Index

F

FlexLM license server 9
FLEXnet license server 7

L

LMTTOOLS 9
local license key file
 configuring RGS Sender on
 Linux 6
 configuring RGS Sender on
 Windows 5
installing 5