

# User's Manual

---



## R-Studio



© R-Tools Technology Inc 2024.  
All rights reserved.  
[www.r-tt.com](http://www.r-tt.com)

© R-tools Technology Inc 2024.  
All rights reserved.

No part of this User's Manual may be copied, altered, or transferred to, any other media without written, explicit consent from R-tools Technology Inc..

All brand or product names appearing herein are trademarks or registered trademarks of their respective holders.

R-tools Technology Inc. has developed this User's Manual to the best of its knowledge, but does not guarantee that the program will fulfill all the desires of the user.

No warranty is made in regard to specifications or features.

R-tools Technology Inc. retains the right to make alterations to the content of this Manual without the obligation to inform third parties.

# Table of Contents

<b>I Introduction to R-Studio</b>	<b>1</b>
1 R-Studio Features .....	1
2 System Requirements .....	4
3 Contact Information and Technical Support .....	4
4 R-Studio Registration and Activation .....	5
5 R-Studio Main Panel .....	6
6 R-Studio Settings .....	12
<b>II Data Recovery Using R-Studio</b>	<b>18</b>
1 Basic File Recovery .....	20
Opening several disks/partitions in one tab .....	30
Searching for a File .....	31
Finding Previous File Versions .....	34
Previewing Files .....	34
File Masks .....	41
Regular Expressions .....	42
Event Log .....	42
2 Advanced Data Recovery .....	43
Drive Scan .....	43
Fast Search for Lost Partitions .....	59
Customizing File Types .....	60
Customizing File Types-I .....	62
Customizing File Types-II .....	65
Regions .....	70
Exclusive Regions .....	71
Images .....	73
Wiping Objects .....	80
3 Mass File Recovery .....	81
Find and Mark Multiple Files .....	82
Recover Multiple Files .....	83
Recovery Lists .....	85
4 Volume Sets and RAIDs .....	90
Volume Sets, Stripe Sets, and Mirrors .....	92
Basic RAID 4 and RAID 5 Operations .....	96
Working with RAID6 (Double Xor) Presets .....	98
Working with RAID 6 Presets .....	100
Working with RAIDs with Parity Delays .....	103
Working with Advanced RAID Layouts .....	106
Nested and Non-Standard RAID Levels .....	116
RAID10 (1+0).....	116
RAID1E .....	118
RAID5E .....	120
RAID5EE .....	122
RAID6E .....	124
Finding RAID Parameters .....	127
Checking RAID Consistency .....	129

Syntax of a Description File for RAID Configurations .....	129
Description Files for RAID Configurations .....	134
<b>Various Disk and Volume Managers .....</b>	<b>140</b>
BitLocker Drive Encryption .....	140
Windows Dynamic Disks .....	144
Windows Storage Spaces .....	146
Apple RAIDs .....	149
Apple CoreStorage/FileVault/Fusion Drive Volumes .....	152
Linux mdadm RAIDs .....	159
Linux LVM/LVM2 .....	161
<b>Mounting Virtual Objects in the System as Virtual Drives .....</b>	<b>163</b>
<b>5 Data Recovery over Network .....</b>	<b>165</b>
<b>R-Studio Agent .....</b>	<b>165</b>
R-Studio Agent for Windows .....	166
R-Studio Agent for Mac .....	167
R-Studio Agent for Linux .....	169
<b>Data Recovery over Network .....</b>	<b>170</b>
<b>Connecting over the Internet .....</b>	<b>172</b>
<b>III R-Studio Technician/T80+ .....</b>	<b>175</b>
<b>1 Portable version .....</b>	<b>177</b>
<b>2 Multitasking .....</b>	<b>179</b>
<b>3 Additional Recovery Options .....</b>	<b>182</b>
<b>4 Hidden Devices .....</b>	<b>183</b>
<b>5 File Information .....</b>	<b>185</b>
<b>6 Symbolic Link Processing .....</b>	<b>186</b>
<b>7 Custom Recovery Lists .....</b>	<b>188</b>
<b>8 Drive Copy Wizard .....</b>	<b>213</b>
<b>9 File Maps .....</b>	<b>219</b>
<b>10 I/O Monitor and Sector Map Files .....</b>	<b>220</b>
<b>11 Runtime Imaging .....</b>	<b>221</b>
<b>12 Multi-pass Imaging .....</b>	<b>226</b>
<b>13 Reverse RAIDs .....</b>	<b>230</b>
Reverse RAID of an Object .....	231
Reverse RAID of a RAID .....	232
<b>14 Working with the Third-Party Hardware .....</b>	<b>234</b>
DeepSpar Disk Imager™ .....	234
DeepSpar USB Stabilizer .....	238
DeepSpar RapidSpar™ .....	243
PC-3000 UDMA hardware .....	246
<b>15 Forensic Mode .....</b>	<b>246</b>
<b>IV Text/hexadecimal Editor .....</b>	<b>297</b>
<b>1 Viewing and Editing Objects .....</b>	<b>298</b>
<b>2 Navigating through an Object .....</b>	<b>304</b>
<b>3 Data Copy .....</b>	<b>307</b>



4	Files and Sectors .....	307
5	Creating Custom Patterns .....	308
6	Pattern Example I .....	311
7	Pattern Example II .....	315
<b>V</b>	<b>Technical Information and Troubleshooting</b>	<b>319</b>
1	IntelligentScan Technology .....	319
2	Data Recovery Issues .....	320
3	Extended Information Recovery .....	323
4	Data Formats and Multipliers .....	323
5	Data Recovery on HFS/HFS+ File System .....	324
6	Supported Virtual Disk and Disk Image Formats .....	325
7	Bad Sectors .....	326
8	Memory Usage .....	327
9	R-Studio Switches .....	327
10	Properties Tab .....	328
<b>VI</b>	<b>R-Studio Emergency</b>	<b>335</b>
1	Contact Informaiton and Technical Support .....	335
2	Creating Startup Disks .....	335
	Installing R-Studio Emergency Startup Media Creator .....	336
	Creating Startup Disks Using R-Studio Emergency Startup Media Creator .....	337
	Creating Startup Disks on Mac and Linux Computers .....	343
3	R-Studio Emergency Operation .....	343
	Starting a Computer with the R-Studio Emergency Startup Disks .....	344
	File Recovery .....	346
	Searching for a File .....	347
	Disk Scan .....	348
	Disk Images .....	349
4	Using R-Studio Emergency as an Emergency Agent .....	350
5	R-Studio Emergency Technical Information .....	354
	Properties and Text/Hexadecimal Viewer .....	354
	Network Drives .....	355
	Log .....	356
	Devices to Store Recovered Files .....	356
6	R-Studio Emergency Hardware Compatibility List .....	358
<b>VII</b>	<b>R-Studio Agent Emergency</b>	<b>363</b>
1	Contact Information and Technical Support .....	363
2	Installing R-Studio Agent Emergency Startup Media Creator .....	363
3	Creating Startup Disks .....	363
4	Starting a Computer with the R-Studio Agent Emergency Startup Disk .....	369
5	R-Studio Agent Emergency Hardware Compatibility List .....	372
	Disk Controllers .....	372

Network Cards ..... 382

**Index** ..... **394**

# I Introduction to R-Studio

**R-Studio** is a family of powerful and cost-effective undelete and data recovery software. Empowered by new unique data recovery technologies, it is the most comprehensive data recovery solution for recovering files from [FAT/exFAT](#), NTFS, NTFS5, ReFS/ReFS2+ (Windows), HFS/HFS+ and APFS (Macintosh), Little and Big Endian variants of [UFS1/UFS2](#) (FreeBSD/OpenBSD/NetBSD/Solaris), [Ext2/3/4FS](#) and [XFS](#) (Linux) [partitions](#). It functions on local and network disks, even if such partitions are [formatted](#), damaged or deleted. Flexible parameter settings give you absolute control over the data recovery.

## [R-Studio Features](#)

## [System Requirements](#)

## [Contact Information and Technical Support](#)

## [R-Studio Registration and Activation](#)

## [Data Recovery Using R-Studio](#)

## [Basic File Recovery](#)

## [Advanced Data Recovery](#)

## [Mass File Recovery](#)

## [Volume Sets and RAIDs](#)

## [Data Recovery over Network](#)

## [R-Studio Technician/T80+](#)

## [Text/Hexadecimal editor](#)

## [Technical Information and Troubleshooting](#)

## [R-Studio Emergency](#)

## [R-Studio Agent Emergency](#)

Windows 9x/ME/NT4.0/Windows 2000, XP, Vista, 7,8/8.1, 10, 11, Windows Server 2003, 2008, 2012, 2016, 2019, 2022 are registered trademarks of Microsoft Corporation.

Mac OS X, OS X, and macOS are registered trademarks of Apple Inc.

All other trademarks are the property of their respective owners.

## 1.1 R-Studio Features

**R-Studio** is a family of file restoring utilities. It recovers files both on local drives and on drives on remote computers over network, even if their [partition](#) structures are damaged. A unique **IntelligentScan** technology and flexible parameter settings give you real control over the fastest data recovery ever seen.

### **R-Studio features:**

- Standard "Windows Explorer" - style interface.
- Host OS: An Intel-compatible platform running Windows 11 /10 /8.1/8 /7 /Vista /XP /2000 Windows Server 2019 /2016 /2012 /2008 /2003.
- Automatic check for updates.
- Remotely recovers data over network. Data can be recovered on network computers running Windows, MacOS X, Linux, and some other UNIX OS.
- Supported [file systems](#):  
**Windows:** FAT12/16/32, [exFAT](#), NTFS, NTFS5, ReFS/ReFS2+ file (Resilient File System); ReFS for Windows Server 2019 (including deduplication).  
**macOS:** HFS, HFS+, HFSX, APFS, [FAT](#)/exFAT;

**Linux and UNIX:** [Ext2/3/4FS](#) and [XFS](#) (created by Linux or other OS), and [UFS1](#), [UFS2](#), [UFS BigEndian](#) (used by the FreeBSD, OpenBSD, and NetBSD operating systems);

**CD/DVD/Images:** ISO9660;

**Magnetic tape devices:** UStar/Tar/CPIO/Pax (**R-Studio Technician/T80+**).

Please note, that when a file is being deleted on the HFS, HFS+, HFSX file systems, the computer completely removes all system information on it, and there is no way to recover the deleted file except by using the [Extra Search for Known File Types](#) option. Nevertheless, **R-Studio** is able to read existing files from HFS, HFS+, and HFSX disks.

- Support for [known file types](#). **R-Studio** searches for files with known typical features of their structures allowing the user to search for files on devices with unknown files systems, including an HD, CD, DVD, floppy disk, Compact Flash Card, USB drive, ZIP drive, Memory Sticks, and other removable media.
- [Scan process](#) visualization. While scanning an object, **R-Studio** graphically shows items that have been found, including files of known types, FAT and NTFS MFT records, boot records, etc.
- Mass file recovery support.
- Support for estimation of chances for successful recovery.
- Support for file recovery lists - lists of files that can be exported from **R-Studio**, manually edited, and then loaded back. Files from such lists will be automatically marked for recovery.
- APM, Basic and GPT support. **R-Studio** supports all three partition schemes used to define the low-level organization of data on drives [formatted](#) for use with Macintosh computers.
- [Dynamic disk](#) support.
- Support for [BitLocker Drive Encryption](#) encryption, both for the ToGo and System Drive Encryption methods.
- Software RAID, volume set, and stripe set support. Support for RAID 6, RAID 5, and RAID 4 layouts. Support for custom RAID layouts. Parameters like block size and order, offsets, and even the number of stripe blocks can be explicitly specified. Custom RAID configurations can be saved.
- Support for [Windows Storage Spaces](#), created by Windows 8/8.1 and Windows 10/Threshold 2/? Anniversary/Fall Creators updates.
- Support for [Apple software RAIDs](#)
- Support for [Apple CoreStorage/FileVault/Fusion Drive Volumes](#)
- Support for [Linux mdadm Volumes](#)
- Support for [Linux LVM/LVM2](#)
- Support for Intel Software RAID.
- Hardware RAID, volume set, and stripe set support.
- RAID consistency check (check for valid data parity values).
- Automatic RAID parameter recognition.
- Creates [image](#) files for an entire drive, [logical](#) disk, or its part. Such image files can be processed like regular drives. In addition to simple exact object copies (Plain images) and [R-Drive Image](#) compatible images, it can create other disk image and virtual disk formats, together with opening several file formats "read-only". You may read more about those formats and their properties on the [Supported Virtual Disk and Disk Image Formats](#) page. Images may be saved either on the local or remote computer. Image creation can be stopped and then resumed. **R-Studio** can scan objects while creating their images. **R-Studio Technician/T80+** supports [multi-pass](#) and [runtime](#) imaging. Images can be mounted in the operating system as devices which makes their content accessible to any program including any other data recovery software.
- Recovers files on damaged or deleted partitions.

- Recovers compressed files (NTFS, NTFS5).
- Recovers encrypted files (NTFS5).
- Recovers [alternative data streams](#) (NTFS, NTFS5).
- Support for NTFS deduplication, including Windows Server 2022.
- Support for file system journal on the HFS+ and Ext3/4fs file systems.
- Support for soft updates journal on the UFS file system.
- Support for extended attributes on the HFS+, Ext3/4fs, XFS, and UFS file systems.
- Support for compressed files on the HFS+ file system.
- Recognizes localized names.
- Recovered files can be saved on any (including network) drives visible to the host operating system.
- A hexadecimal disk and file viewer/editor supporting NTFS file non-resident attribute editing. Data alteration is available on the **Technician/T80+** and **Corporate** versions only.
- Patterns (or templates) in the hexadecimal editor allowing for parsing the data according to specific data structure. Such patterns may be custom-created.
- File preview. Most of the file types can be previewed to estimate recovery chances.
- Enhanced remote host scanning procedure. In the **R-Studio** network versions, data is analyzed on the remote host rather than on the home host, thereby the speed of recovery procedure greatly increases. The scan information may be saved either on the local or remote computer.
- Recovered files may be saved on a drive on a connected remote computer rather than be transferred over network to the local one. Saving recovered files on a remote computer may be useful when the remote computer has a healthy drive because you do not have to transfer files over network. It may be an external USB drive, for example.
- Support for [S.M.A.R.T.](#) (Self-Monitoring, Analysis and Reporting Technology) attribute monitoring.
- **R-Studio Emergency\***. The **R-Studio Emergency** version starts from a floppy or compact disc when it is necessary to recover data on a computer, on which Windows cannot start up because its system files are corrupted or deleted.

\*The **R-Studio Emergency** is a part of the **R-Studio** software package. When you buy an **R-Studio** single license you may run the **R-Studio Emergency** or/and install the **R-Studio** Windows version on one PC only and you may not transfer the licensed software to another PC.

#### ***R-Studio features available in the Technician/T80+ versions:***

- Magnetic tape devices file system: **UStar/Tar/CPIO/Pax**.
- [Portable version](#)
- [Multitasking](#). Several data recovery tasks can be run simultaneously.
- [Additional Recovery Options](#)
- [Hidden Devices](#). Some unnecessary device can be hidden in the Main panel.
- [Extended file information](#)
- [Symbolic link recovery options](#)
- [Drive Copy Wizard](#) to copy any object in the Drives panel to any other object. In addition to byte to byte copy of any object visible in the Drives panel, smart copy of partitions and drives is available.
- [Mounting Virtual Objects to the System as Virtual Drives](#)
- [I/O Monitor and Sector Map files](#).
- [Multi-pass](#) and [Runtime](#) imaging

- [Reverse RAIDs](#): A technique that decomposes real drive objects into virtual RAIDs. Then those components of reverse RAID scan can be processed like real objects. They can be viewed, edited, imaged, copied to physical devices.
- Support for [third-party hardware](#).
- [Forensic mode](#).
- [File recovery over Internet](#).

#### **R-Studio recovers files:**

- That have been removed without the **Recycle Bin**, or when the **Recycle Bin** has been emptied;
- Removed by virus attack or power failure;
- After the partition with the files was reformatted, even for a different file system;
- When the partition structure on a drive was changed or damaged. In this case, **R-Studio** can scan the drive trying to find previously existed partitions and recover files from found partitions.
- From drives with [bad sectors](#). In this case, **R-Studio** can first copy the entire drives or its part into an image file and then process such image file.

**R-Studio** can create image files for an entire drive, logical disk, or its part. Such image files can be processed like regular drives. Images are very useful if there is a risk of total data loss due to hardware malfunction. If bad blocks are constantly appearing on a drive, the only way to save the data is to immediately create an image of that drive. All data search, scan and recovery can be done from this image.

To learn more about the *IntelligentScan* technology, go to the [IntelligentScan](#) topic .

## **1.2 System Requirements**

- An Intel-compatible platform running Windows 11, 10 /8.1/8 /7 /Vista /XP /2000 Windows Server 2022, 2019 /2016 /2012 /2008 /2003
- At least 256 MB of RAM, a mouse, and enough disk space for recovered files, image files, etc.
- The administrative privileges are required to install and run R-Studio utilities.
- A network connection for data recovering over network.

## **1.3 Contact Information and Technical Support**

To obtain the latest version of **R-Studio**, go to:

Product Site: <http://www.r-tt.com>

Sales Department: [sales@r-tt.com](mailto:sales@r-tt.com)

**R-Studio** Technical Support Team is available 24 hours a day, seven days a week, and has an average response time less than 4 hours.

Tech. Support: [support@r-tt.com](mailto:support@r-tt.com)

Send your support request to: <http://www.r-tt.com/SupportRequest.shtml>

File Recovery FAQ: [http://www.r-tt.com/File\\_Recovery\\_FAQ.shtml](http://www.r-tt.com/File_Recovery_FAQ.shtml)

R-tt Forum: <http://forum.r-tt.com>


## 1.4 R-Studio Registration and Activation

**R-Studio Standalone**, **Corporation**, and **T80+** requires on-line activation via the Internet. **R-Studio Standalone** and **Corporation** require activation one time upon their installation. **R-Studio T80+** requires activation every time a new data recovery session starts.

If you don't have an Internet connection on the computer where **R-Studio** to be installed, you'll need to complete activation manually.

- 1 Upon receiving the email with the Registration key, open the attachment, then select and copy the key.
- 2 Start R-Studio. The Please Register R-Studio Demo dialog box will appear.
- 3 Enter your registration information and then paste the Registration key. Do not try to type it manually.

Please Register dialog box




- 3 Click the OK button and wait for the Registration successful message.

***If you don't have an Internet connection.***

You need to manually obtain an activation code to complete the registration.

The Online Activation dialog window will appear next time you'll start **R-Studio**.

R-Studio Online Activation dialog box



You may copy the url with the activation information and go to it on another computer connected to the Internet, obtain the activation code, and enter it into the respective field on the dialog box.

You may also use your smartphone to activate **R-Studio**. Scan the QR-code and go to the specified URL, obtain the activation code, and finish program activation.

## 1.5 R-Studio Main Panel

When **R-Studio** starts, its main panel appears on the Windows desktop.

**R-Studio Main panel**

The screenshot shows the R-Studio main panel with the following components:

- Menu:** Drive, Create, Tools, View, Help
- Toolbar:** Refresh, Show Files, Scan, Partition Search, Create Image, Open Image, Create Region, RAID's, Connect To Remote, Remove
- Device view:** A table listing devices and disks with columns for Device/Disk, Label, /Interfa, Start, and Size. The selected item is Hitachi HTS545016B9SA00.
- Properties Panel:** A table showing details for the selected drive, including Drive Type, Name, OS Object, R-Studio Driver, Size, Logical Sector Size, Physical Sector Size, Partition Size, I/O Retries, Drive Control (Maximum Transfer, I/O Block Size, Buffer Alignment), and Physical Drive Geometry (Cylinders, Tracks Per Cylinder).
- Log:** A table showing system events with columns for Type, Date, Time, and Text.

Device/Disk	Label	/Interfa	Start	Size
Local Computer				
KINGSTON SA400S37120...	50026B77843A...	#0 SATA2, SSD		111.79 GB
TOSHIBA DT01ACA100 ...	44H5ATLKS	#1 SATA2, HDD		931.51 GB
Hitachi HTS545016B9SA...	100713PBPB08...	#2 SATA2, HDD		149.05 GB
I:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
G:	FAT-TEST	FAT16	54.96 GB	2.01 GB
E:	EXFAT	FAT32	56.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
Reformatted1		NTFS	0 Bytes	33.86 GB
ST1000LM024 HN-M101...	S314J90DA25783	#3 USB, HDD		931.51 GB
H:	VirtMach	exFAT	17 KB	931.51 GB
SanDisk Ultra Fit 1.00	4C5300011103...	#4 USB		114.56 GB
J:	exFAT-media	exFAT	16 KB	114.56 GB

Name	Value
Drive Type	Physical Drive, Disk
Name	Hitachi HTS545016B9SA00 PBBOC64G
OS Object	\\.\PhysicalDrive2
R-Studio Driver	WinNT\Handle\Physical
Size	149.05 GB (312581808 Sectors)
Logical Sector Size	512 Bytes
Physical Sector Size	512 Bytes
Partition Size	149.05 GB (312581808 Sectors)
I/O Retries	Default
<b>Drive Control</b>	
Maximum Transfer	128 KB
I/O Block Size	512 Bytes
Buffer Alignment	4 Bytes
<b>Physical Drive Geometry</b>	
Cylinders	19457
Tracks Per Cylinder	255


Type	Date	Time	Text
System	2/21/2024	9:23:35 AM	Successfully loaded user's file types definitions from "C:\Program Files (x86)\R-Studio Technician\Presets\UserKnownFile..."
System	2/21/2024	9:23:35 AM	Successfully loaded user's RAID layouts from "C:\Program Files (x86)\R-Studio Technician\Presets\RAID6RS.xml"

Drives panel:

You can select an object by clicking it.

Device/Disk	Label	FS/Interface	Start	Size
Local Computer				
KINGSTON SA400S37120G 03090005	50026B77843A5618	#0 SATA2, SSD		111.79 GB
Efi system partition		FAT32	1 MB	100 MB
Microsoft reserved partition			101 MB	16 MB
C:	System	NTFS	117 MB	111.18 GB
Windows Recovery Partition		NTFS	111.29 GB	508 MB
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2, HDD		931.51 GB
D:	Data	NTFS	1 MB	931.51 GB
Hitachi HTS545016B9SA00 PBBOC64G	100713PBPB08CE4X50F	#2 SATA2, HDD		149.05 GB
I:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
G:	FAT-TEST	FAT16	54.96 GB	2.01 GB
E:	EXFAT	FAT32	56.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
Reformatted1		NTFS	0 Bytes	33.86 GB
ST1000LM024 HN-M101MBB 2BA30001	S314J90DA25783	#3 USB, HDD		931.51 GB
H:	VirtMach	exFAT	17 KB	931.51 GB
SanDisk Ultra Fit 1.00	4C530001110316108204	#4 USB		114.56 GB
J:	exFAT-media	exFAT	16 KB	114.56 GB

A logical disk may be represented by its name or its partition.





### Properties tab:

This tab shows the properties of an object selected in the Drives panel.

Name	Value
Drive Type	Physical Drive, Disk
Name	Hitachi HTS545016B9SA00 PBB0C64G
OS Object	\\.\PhysicalDrive0
R-Studio Driver	WinNT!Handle!Physical
Size	149.05 GB (312581808 Sectors)
Logical Sector Size	512 Bytes
Physical Sector Size	512 Bytes
Partition Size	149.05 GB (312581808 Sectors)
I/O Retries	Default
<b>Drive Control</b>	
Maximum Transfer	128 KB
I/O Block Size	512 Bytes
Buffer Alignment	4 Bytes
<b>Physical Drive Geometry</b>	
Cylinders	19457
Tracks Per Cylinder	255
Sectors Per Track	63
Sector Size	512 Bytes
Partition Layout Sector Size	512 Bytes
<b>Device Identification</b>	
Vendor	Hitachi
Product	HTS545016B9SA00
Firmware	PBB0C64G
Serial Number	100713PBPB08ECE4X50F
<b>IDE Properties</b>	
Size	149GB (312581808 LBA)
Sector Size	512
Device Type	HDD 2.5" 5400 RPM
Interface	SATA 2.6, 1.5 Gb/s
Standard	ATA8-ACS
Features	S.M.A.R.T., APM, AAM, LBA48, NCQ
<b>SCSI Address</b>	
Port Number	2
Path Id	1
Target Id	0
Lun	0
Bus Type	SerialATA-II

Depending on the selected object, information on this Properties tab may vary.

The Properties tab names and values are described in detail on the [Properties tab](#) topic.

### Log panel


Type	Date	Time	Text
System	2/21/2024	9:23:35 AM	Successfully loaded user's file types definitions from "C:\Program Files (x86)\R-Studio Technician\Presets\UserKnownFile...
System	2/21/2024	9:23:35 AM	Successfully loaded user's RAID layouts from "C:\Program Files (x86)\R-Studio Technician\Presets\RAID6RS.mli"

### **S.M.A.R.T. Info for a Drive**

R-Studio shows drive [S.M.A.R.T.](#) states using their icons. You may copy all S.M.A.R.T. attributes and paste them into a text editor.

☐ **Drive S.M.A.R.T. states and icons**

Normal: This state indicates that the drive is in good conditions.



Health Status: **GOOD** Temperature: 34 °C

Power on Hours: 14827 hour Power on Count: 5711 count

Rotation Rate: 5400 RPM

Standard: ATAB-ACS | ATAB-ACS version 6


Features: S.M.A.R.T., APM, AAM, 48bit LBA, NCQ

S.M.A.R.T.

ID	Attribute Name	Current	Worst	Threshold	Raw Values
01	Read Error Rate	100	100	62	000000000000
02	Throughput Performance	100	100	40	000000000000
03	Spin-Up Time	204	204	33	000F00000001
04	Start/Stop Count	97	97	0	000000001695
05	Reallocated Sectors Count	100	100	5	000000000000
07	Seek Error Rate	100	100	67	000000000000
08	Seek Time Performance	100	100	40	000000000000
09	Power-On Hours	67	67	0	0000000039EB
0A	Spin Retry Count	100	100	60	000000000000
0C	Power Cycle Count	97	97	0	00000000164F
0E	G-Sense Error Rate	100	100	0	000000000000
C0	Power-off Retract Count	100	100	0	00000000007D
C1	Load/Unload Cycle Count	89	89	0	0000000018D43
C2	Temperature	161	161	0	002B00060022
C4	Reallocation Event Count	100	100	0	000000000000
C5	Current Pending Sector Count	100	100	0	000000000000
C6	Uncorrectable Sector Count	100	100	0	000000000000
C7	UltraDMA CRC Error Count	200	200	0	0000000000DD
DF	Load/Unload Retry Count	100	100	0	000000000000

Refresh Copy All

Warning: This state indicates that some small problems with the drive are possible in the future, you may work with it but with cautions and regular check of these parameters. [Drive imaging](#) is strongly recommended.



Health Status: **CAUTION** Temperature: 29 °C

Power on Hours: 4882 hour Power on Count: 2740 count

Rotation Rate: 5400 RPM

Standard: ATAB-ACS | ---


Features: S.M.A.R.T., APM, AAM, 48bit LBA, NCQ

S.M.A.R.T.

ID	Attribute Name	Current	Worst	Threshold	Raw Values
01	Read Error Rate	198	198	51	000000005AFD
03	Spin-Up Time	158	156	21	000000000422
04	Start/Stop Count	96	96	0	00000000102D
05	Reallocated Sectors Count	199	29	140	000000000008
07	Seek Error Rate	200	200	0	000000000000
09	Power-On Hours	94	94	0	000000001312
0A	Spin Retry Count	100	99	51	000000000000
0B	Recalibration Retries	100	100	0	000000000000
0C	Power Cycle Count	98	98	0	000000000A84
C0	Power-off Retract Count	200	200	0	000000000140
C1	Load/Unload Cycle Count	158	158	0	000000001F202
C2	Temperature	114	81	0	00000000001D
C4	Reallocation Event Count	192	159	0	000000000008
C5	Current Pending Sector Count	196	196	0	000000000052
C6	Uncorrectable Sector Count	100	253	0	000000000000
C7	UltraDMA CRC Error Count	200	200	0	00000000001E
C8	Write Error Rate	100	253	51	000000000000

Refresh Copy All

**Critical:** This state indicates that the drive conditions are critical and chances of hardware failure are great. The best recommendation for this case is to stop working with the drive and bring it to professional data recovery specialists. You may though continue to work with the drive at your own risk, but [drive imaging](#) is very strongly recommended.



ID	Attribute Name	Current	Worst	Threshold	Raw Values
01	Read Error Rate	190	190	51	00000012629
03	Spin-Up Time	142	129	21	00000000742
04	Start/Stop Count	62	62	0	00000009523
05	Reallocated Sectors Count	129	129	140	00000000231
07	Seek Error Rate	200	200	0	00000000000
09	Power-On Hours	92	92	0	000000001747
0A	Spin Retry Count	100	100	0	00000000000
0B	Recalibration Retries	100	100	0	00000000000
0C	Power Cycle Count	95	95	0	000000015E3
C0	Power-off Retract Count	197	197	0	00000000B0F
C1	Load/Unload Cycle Count	53	53	0	00000006C5A
C2	Temperature	115	88	0	0000000001C
C4	Reallocation Event Count	168	168	0	00000000020
C5	Current Pending Sector Count	200	200	0	00000000012
C6	Uncorrectable Sector Count	100	253	0	00000000000
C7	UltraDMA CRC Error Count	200	200	0	00000000000
C8	Write Error Rate	100	253	0	00000000000

When a drive is selected in the **R-Studio** main panel, an additional S.M.A.R.T. tab will appear. You may view the detailed **S.M.A.R.T.** data of the drive.

**S.M.A.R.T.** (Self-Monitoring, Analysis and Reporting Technology) is a technology widely-used in drives and solid-state devices that monitors their reliability conditions to predict possible hardware failures.

### Changing the program language

You may select the language of **R-Studio** main panel and its help. To do so, select an available language on **Change Language** on the **Help** menu.

### Panel view options

You may set which panels and bars to enable/disable.

#### To enable/disable:


Toolbar	Select/clear <b>Toolbar</b> on the <b>View</b> menu
Status bar	Select/clear <b>Status bar</b> on the <b>View</b> menu
Drive pane	Select/clear <b>Device View</b> on the <b>View</b> menu
Properties pane	Select/clear <b>Properties View</b> on the <b>View</b> menu
Log panel	Select/clear <b>Event Log</b> on the <b>View</b> menu
If you have several tabs in the right pane, you may easily switch to any of the tab by selecting on the <b>View</b> menu	
<b>Properties Tab</b>	to view the Properties tab
<b>Scan Information Tab</b>	to view the Scan Information Tab tab
<b>Parents Tab</b>	to view the Parents tab
<b>Properties</b>	Select data types in which the data will be represented

**Connect**

Click this button to connect to a remote computer on a network.

**Refresh**

Click this button to refresh the panels.

**Scan**

Click this button to start scanning a selected object.

**Partition Search**

Click this button to start [fast searching for lost and deleted partitions](#).

**Show Files**

Click this button to start enumerating files on a selected object.

**Open Image**

Click this button to open a previously created image.

**Create Image**

Click this button to create an image of a selected area.

**Create Region**

Click this button to create a region on a selected disk.

**RAIDs**

Click this button to create a virtual volume set or RAID.

Select an appropriate type from the menu.

**Remove**

Click this button to remove a selected object in the main panel.

The button may change its appearance and title depending on the context.

Sometimes, there may be a lot of similar objects in the Drives panel. Those may be components of a RAID, for example. You may turn numerical indexes for such objects to distinguish them better. Those indexes will appear before the object names in the Drives panel.

To turn the numerical indexes on/off, go to the **Device** item on the **View** menu, and select/clear:

**Show Physical Drives Indexes** to display the indexes only for drives

**Show All Objects Indexes** to display the indexes for all objects in the Drives panel

Device/Disk	Label	FS/Interface	Start	Size
[0] Local Computer				
[4] KINGSTON SA400S37120G 03090005	50026877943A5618	#0 SATA2, SSD		111.79 GB
[23] EFI system partition		FAT32	1 MB	100 MB
[24] Microsoft reserved partition			101 MB	16 MB
[25] C:	System	NTFS	117 MB	111.18 GB
[26] Windows Recovery Partition		NTFS	111.29 GB	508 MB
[5] TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2, HDD		931.51 GB
[27] D:	Data	NTFS	1 MB	931.51 GB
[6] Hitachi HT545016B9SA00 PBB0C64G	100713PBP808CE4XS0F	#2 SATA2, HDD		149.05 GB
[28] I:	NTFS-Test	NTFS	512 KB	28.69 GB
[29] F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
[30] G:	FAT-TEST	FAT16	54.96 GB	2.01 GB
[31] E:	EXFAT	FAT32	56.97 GB	11.72 GB
[32] Partition5	HFS	HFSX	68.69 GB	21.48 GB
[33] Partition6	EXTFS	Ex4	90.17 GB	25.02 GB
[34] Partition7	XFS	XFS	115.19 GB	33.86 GB
[37] Reformatted1		NTFS	0 Bytes	33.86 GB
[7] ST1000LMD024 HN-M101MBB 2BA30001	S314J90DA25783	#3 USB, HDD		931.51 GB
[35] H:	VirtMach	exFAT	17 KB	931.51 GB
[8] SanDisk Ultra Fit 1.00	4C530001110316108204	#4 USB		114.56 GB
[36] J:	exFAT-media	exFAT	16 KB	114.56 GB

You may select the units in which object's start and size are displayed

## To select the units

- 1 Select Devices on the View menu
- 2 Select the units in which you want to see object sizes.

You may select

Show as Bytes

Show as Sectors

Show as Bytes and Sectors

Depending on the task **R-Studio** performs, its panel may vary. Those panels are described in appropriate topics. The Properties tab names and values are described in detail on the [Properties tab](#) topic.

The general settings can be set on the [Settings](#) dialog box.

You may also copy the object's information displayed in the Drives panel. Right-click the object on the necessary column and select **Copy Device/disk**, **Copy Label**, and so on.

## R-Studio has two operation modes:

**File search** on a [partition](#) (including recently found during [drive scan](#)).

In this mode, **R-Studio** analyzes MFTs on NTFS partitions, FATs on [FAT](#) partitions, and SuperBlocks on Ext2/3/4FS partitions. Then it displays all files which records have been found in the analyzed tables. Then recently deleted files, which records still remain, can be recovered. If files have not been found, that means that their records have been deleted. In this case, the drive must be scanned.

File search supports [file masks](#) and [regular expressions](#). Multiple files in different folders can be found and recovered in one recover session.

**R-Studio** supports [mass file recovery](#). There is no limit in the number of files that may be recovered during one session.

File content may be [previewed](#) before recovery.

File or drive binary data can be viewed and edited in the [Text/Hexadecimal editor](#). Also can be viewed and changed all attributes for NTFS files.

**Drive scan**, searching for partitions.

In this mode, **R-Studio** scans the entire drive or its part. Using a number of statistic and deterministic criteria known as *IntelligentScan* technology, it determines existing or existed partitions on the drive, and their [file systems](#). It is also possible to add new partitions, by setting manually all required parameters.

A drive can be scanned through several successive scans, each with its own parameters. **R-Studio** accumulates the information from successive scans and keeps track of changes in the information obtained from


different scans. The information obtained from the disc scan can be stored in a file. It may be loaded and processed later at any convenient time.

## 1.6 R-Studio Settings

You may specify some global setting for **R-Studio** on the Settings dialog box. You may reach it by selecting **Settings** on the **Tools** menu.

Main

Main dialog box




### Main settings

System Options	
Auto-refresh Drive Tree	If this box is selected, <b>R-Studio</b> automatically refreshes the list of connected drives. You may disable it if <b>R-Studio</b> experiences problems with connected devices.
Debug Mode	If this check box is selected, <b>R-Studio</b> displays an additional command <b>Create FS Snapshot</b> on the shortcut menu for an object with a <a href="#">file system</a> . An FS Snapshot contains system data for the file system only (file descriptions without file contents). If a problem appears, this snapshot can be sent to <b>R-Studio</b> technical support to identify the problem. This option greatly slows <b>R-Studio</b> .
Enable forensic mode (demo)	If this check box is selected, <b>R-Studio</b> turns on the <a href="#">Forensic mode</a> in demo mode.
Check for update	If this box is selected, <b>R-Studio</b> will automatically check for updates.
Use dark mode	If this box is selected, <b>R-Studio</b> will change to its dark mode.
Edit options	
Enable Write	If this check box is selected, <b>R-Studio Technician/T80+</b> enables you to write any changes made in the <a href="#">Text/Hexadecimal editor</a> . It enables <a href="#">wiping objects</a> in R-Studio and R-Studio Corporate.
Max changes buffer size	Maximum amount of data stored for the <b>Undo</b> command in the <a href="#">Text/hexadecimal editor</a> . <b>R-Studio Technician(T80+)</b>
User paths	

File types	Specifies a file name and path to the file where the descriptions of user's <a href="#">known file types</a> are stored. You need to re-start <b>R-Studio</b> or click the Reload User's File Types button on the Known File Types tab for the new file to take effect.
RAID layout presets	Specifies a file name and path to the file where the descriptions of user's <a href="#">RAID layouts</a> are stored
Text/hexadecimal editor templates	Specifies the path for <a href="#">pattern description files</a> for <a href="#">Text/hexadecimal editor</a> .
Mask presets	Specifies a file name and path to the file with <a href="#">file mask</a> presets.
Reset all hidden notifications	This button enables all previously disabled notification and warning messages.

## File Systems

### File Systems dialog box



### File Systems

Default encoding for HFS volumes	
Encoding	Select the national encoding for the HFS <a href="#">partitions</a> .
Default encoding for <a href="#">Ext2/Ext3/?</a> <a href="#">Ext4/UFS</a> volumes	
Encoding	Select the national encoding for the Ext2, Ext3, Ext4, and UFS partitions.
File system sorting	
Disable any sorting	Select this option if the number of files on the drive is so large that <b>R-Studio</b> sorts files in selected folders for too long time.
Advanced file system interpretation	
Minimize drive access	Select this option if a lot of <a href="#">bad sectors</a> are on the drive. <b>R-Studio</b> will reduce access to internal files in the file system to speed up the interpretation of file system data.

Show deleted empty folders


Select this option if you want to view empty deleted folders.

## Symbolic Links

**All settings are available in the Technician/T80+ version only!**

**Symbolic links** (of symlinks for short) are object that contains references to other files or folders directory in the form of absolute or relative paths and that affect pathname resolution. For example, if a symlink `C:\ProgramData\Documents` points to `D:\Recovered Files\Root\Users\Public\Documents`, entering it will result in entering `D:\Recovered Files\Root\Users\Public\Documents`.

### Symbolic Links dialog box




### Symbolic Links

Link conversion (Default)	
Both an object and its symbolic link are selected for recovery:	If both an object and its symbolic link are selected for recovery, both the object and its symbolic link will be recovered. The file path in that symbolic link will be converted from absolute to relative. Example: If the object <code>C:\ProgramData\Documents</code> is a symbolic link to <code>C:\Users\Public\Documents</code> , it will be converted to a symbolic link to <code>..\Users\Public\Documents</code> . Therefore, the symbolic link will point to its object regardless of the place to which the object has been recovered.
Only an object is selected for recovery:	Only the selected object will be recovered.
Only a symbolic link is selected for recovery:	The selected symbolic link will be recovered as a real object.



## Log

## Log dialog box




## Log options

Logging	
Maximum messages in the Event Log	Specifies the maximum number of messages <b>R-Studio</b> will keep in the event log
Save log to file	If this check box is selected, <b>R-Studio</b> writes its log into a log file specified in the File name field.
File name	Specifies the file name in which the log will be saved.
Type	
File	If this check box is selected, <b>R-Studio</b> logs all events with recovered files.
File System	If this check box is selected, <b>R-Studio</b> logs all events with the file system.
Partition	If this check box selected, <b>R-Studio</b> logs all events with partitions.
Recover	If this check box is selected, <b>R-Studio</b> logs all events with the recovering processes.
Drive	If this check box is selected, <b>R-Studio</b> logs all events with drives.
Network	If this check box is selected, <b>R-Studio</b> logs all events with network operation.
Severity	
Error	If this check box is selected, <b>R-Studio</b> adds error messages into its log.
Warning	If this check box is selected, <b>R-Studio</b> adds warning messages into its log.
Information	If this check box is selected, <b>R-Studio</b> adds information messages into its log.
Success	If this check box is selected, <b>R-Studio</b> adds success messages into its log.
<b>NEVER WRITE A LOG FILE ON THE DISK FROM WHICH YOU RECOVER DATA!!! Or you may obtain unpredictable results and lose all your data.</b>	
<b>Note:</b> If in the <a href="#">Recover</a> dialog box the Condense successful restoration events check box is selected, the Log will display only Error, Warning, and Information event messages.	

## Known File Types

### Known File Types dialog box




You may specify which [Known File Types](#) will be enabled/disabled by default. You may also specify know file types to search for during a specific [scan session](#) on the [Scan](#) dialog box.

#### **Known File Types**

Reset	Click this button to reset the settings to the previous state. Active until the <b>Apply</b> button is clicked.
Select All	Click this button to select all file types in the list.
Clear All	Click this button to clear all file types in the list except some predefined ones.
Reload User's File Types	Click this button to apply new file types after the user's file types file has been changes from the Main tab.
Edit User's File Types	Click this button to add a new customer's Known File Type, or to edit already existing ones. See the <a href="#">Customizing File Types</a> help page for more details.
Reset to Recommended	Click this button to reset the settings to the default (Recommended) file set.


#### **You may search for required file types if necessary**

## Search for the doc pattern



## Bad Sectors

### Bad Sectors dialog box



### Bad Sectors settings

Default read retries count

Specifies a default value for I/O Tries, or how many times **R-Studio** will try to read a bad sector. You may specify this parameter for each drive separately on the [Properties](#) tab.

**R-Studio** treats bad sectors in the following way:


It reads a certain part of drive (predefined by Windows) and

- If Default read attempts is set to 0, the entire part with bad sectors will be filled with the specified pattern.
- If Default read attempts is set to a non-zero value, **R-Studio** reads again that part sector by sector, repeating the attempts the specified number of times. If **R-Studio** still cannot read a bad sector, it fills the sectors with the specified pattern. In this case only the bad sectors will be filled with the pattern, but that extremely slows the drive read process.

	For example, if you set Default read retries count to 1, a bad sector will be read 2 times.
Set default read retries count for all drives	Click this button to reset Default read retries count for all drives to the default value.
Pattern to fill bad blocks	Specifies a default pattern <b>R-Studio</b> will use to fill bad sectors in files to recover, in <a href="#">images</a> , or when showing data in the <a href="#">Text/Hexadecimal viewer/editor</a> . You may specify the pattern either in the ANSI or Hex data format. <b>Note:</b> <b>R-Studio</b> will never ever try to write anything on the drive from which data is to recover or an image is to create.

## Memory Usage

### Memory Usage dialog box



These settings control how much memory **R-Studio** uses for its work. They help preventing **R-Studio** from locking when trying to perform very memory-consuming tasks like scanning large drives or processing file systems with a lot of files.

#### ☐ Memory Usage settings

Disable memory control	If this option is selected, the memory control is disabled.
Limit usage of the process memory by	If this option is selected, <b>R-Studio</b> will automatically stop performing the task when the amount of used virtual memory reaches the specified value.
Limit usage of the process memory by	If this option is selected, <b>R-Studio</b> will automatically stop performing the task when the amount of used physical memory reaches the specified value.

You may see how much memory **R-Studio** actually uses on the [Memory Usage](#) dialog box.

## II Data Recovery Using R-Studio

**Many specific data recovery cases are discussed in the R-TT's [Data Recovery Guide](#).**

Depending on the situation, data recovery may vary:

### 1. Recovery of deleted files that have resided on an existing logical disk










This can be done using [Basic File Recovery](#).

### 2. Recovery of files that have resided on a data disk with a damaged file system, or on a previously deleted or re-formatted partition

If the file system on such [logical disk](#) is damaged, the operating system sees that logical disk as a [partition](#) without a valid [file system](#). Such partition should be previously [scanned](#). Also, it should be scanned if you want to recover data on a previously deleted or [reformatted](#) partition.

You may use [Fast Search for Lost](#) partitions if you want only to find partitions previously existed on the drive. It's much faster.

When the partition is scanned, a number of recognized partitions will appear. **R-Studio** shows them in different colors depending on which elements of the partition have been found.

 F:	An existing logical disk or partition
 F: (Recognized12)	An existing logical disk or partition after drive scan
 Recognized18	A recognized partition. Both boot records and file entries are found for this partition
 Recognized22	A recognized partition. Only file entries are found for this partition
 Recognized16	A recognized partition. Only boot records are found for this partition
 Recognized8	A fast found partition
 Empty Space21	Empty space on the object
 DeletedPart1	A deleted partition
 Raw Files	Files that have been found using <a href="#">scan for known file types</a> (raw file search).

Although such recognized partitions are virtual objects, files can be searched for and recovered from recognized partitions as from real logical disks using [Basic File Recovery](#).

To successfully recover files from a recognized partition, it is necessary to find a right one which corresponds to the real logical disk on which the files resided. No strict rules can be applied to that, but the following considerations should be taken into account:

- If you are going to recover files from a **drive with a damaged file system**, most likely the right recognized partition will be a green one.
- If you are going to recover files from a **previously deleted or re-formatted partition**, most likely the right recognized partition will be a yellow one.

Also always check the recognized partition's file system, start point, and size. They should be the same for the recognized partition and real logical disk/partition. When in doubt, try to [preview](#) a couple of files from the recognized partition. If the files are seen correctly, this is the right partition.

### 3. Data recovery from a damaged [system disk](#). The computer does not start up.

- If this computer is on a network, create an [R-Studio Agent Emergency](#) startup disk for the computer, install **R-Studio** on another computer on the network, and recover data [over network](#).
- If this computer is stand-alone, create an [R-Studio Emergency](#) startup disk and use it to start up the computer and recover data. You may use external USB drives to store recovered files.

[R-Studio Features](#)

[Contact Information and Technical Support](#)

[Basic File Recovery](#)

[Advanced Data Recovery](#)

[Mass File Recovery](#)

[Volume Sets and RAIDs](#)

[Data Recovery over Network](#)

[Text/Hexadecimal editor](#)

[Technical Information and Troubleshooting](#)

[R-Studio Emergency](#)

[R-Studio Agent Emergency](#)

## 2.1 Basic File Recovery

**NEVER TRY TO SAVE RECOVERED FILES/FOLDERS TO THE SAME LOGICAL DISK WHERE THEY RESIDE!!!**

**Or you may obtain unpredictable results and lose all of your data.**

See the [Data Recovery Issues](#) topic for details.

Basic file recovery can be made for deleted files that has resided on an existing [logical disk](#) visible to the operating system. In all other cases, [Advanced Data Recovery](#) is required.

**To recover deleted files from a logical disk (recognized partition),**

**1 Double-click a logical disk in the R-Studio's Drives panel to enumerate files on the disk**

**Other ways to enumerate files**

- Select the disk and click the **Open Drive Files** button,  
or
- Right-click the selected disk and select **Open Drive Files** on the shortcut menu,  
or
- Select the disk and press the **F5** key.  
or
- Select **Open Drive Files** on the **Drive** menu

If you try to enumerate files on a drive or another object without a valid file system on it, a Double-click a logical disk... message will appear. Select a logical disk on the object or [scan](#) the object.

**> R-Studio will change its panel showing the disk's folders/files structure**

**R-Studio** analyzes data on the object and displays all files for which records have been found in the analyzed tables. If files have not been found, that means that their records have been deleted. To find such files, [Advanced Data Recovery](#) is required.

Please note that **R-Studio** shows only those files/folders that match a specified [file mask](#).

### R-Studio Main panel

The screenshot shows the R-Studio File view interface. The main panel displays a file list with the following columns: Name, Recovery chances, d sectr, Size, Bytes, and Created. The file list includes files like ?est2.arc, ?est4.arc, ?est5.arc, ?est6.arc, ?est7.arc, IMG\_6001.JPG, IMG\_6002.JPG, IMG\_6003.JPG, Outlook\_recovered\_by\_R\_Mail.pst, test1.arc, test3.arc, Wipe Test 1.doc, Wipe Test 2.doc, and Wipe Test 3.doc. A Find Results panel is also visible at the bottom, showing search results for files with extensions .doc and .arc.

Name	Recovery chances	d sectr	Size, Bytes	Created
?est2.arc [F:\Root\SRECYCLE.BIN\?IPP5DVN]	Undetermined (Unfragmented)	No	102,760,448	2/21/202...
?est4.arc [F:\Root\SRECYCLE.BIN\?R1PXC2.]	Above Average (Fragmented)	No	102,760,448	2/21/202...
?est5.arc [F:\Root\SRECYCLE.BIN\?R1MLPSB.]	Above Average (Fragmented)	No	102,760,448	2/21/202...
?est6.arc [F:\Root\SRECYCLE.BIN\?RICZIZ8.a]	Above Average (Fragmented)	No	102,760,448	2/21/202...
?est7.arc [F:\Root\SRECYCLE.BIN\?RBFQSL5.]	Above Average (Fragmented)	No	102,760,448	2/21/202...
IMG_6001.JPG	Good (Existing file)	No	656,192	2/21/202...
IMG_6002.JPG	Good (Existing file)	No	937,070	2/21/202...
IMG_6003.JPG	Good (Existing file)	No	1,180,895	2/21/202...
Outlook_recovered_by_R_Mail.pst	Good (Existing file)	No	163,840	2/21/202...
test1.arc	Good (Existing file)	No	102,760,448	2/21/202...
test3.arc	Good (Existing file)	No	102,760,448	2/21/202...
Wipe Test 1.doc	Good (Existing file)	No	22,528	2/21/202...
Wipe Test 2.doc	Good (Existing file)	No	22,528	2/21/202...
Wipe Test 3.doc	Good (Existing file)	No	22,528	2/21/202...

Sorted by: Real

Find Results

Find All "File Extensions: doc", "Files to Recover"

- Root\Files to Recover\Wipe Test 1.doc
- Root\Files to Recover\Wipe Test 2.doc
- Root\Files to Recover\Wipe Test 3.doc
- Root\Files to Recover\Wipe Test 4.doc
- Root\Files to Recover\Wipe Test 5.doc
- Root\Files to Recover\Wipe Test 6.doc

=== Matching files: 6 Total files searched: 17 ===

Log Find Results

Ready Marked: 10 file and 4 folder. Total size: 490.27 MB Total 13.19 GB in 399 files in 56 folders

### Panel view options

You may set which panels and bars to enable/disable. To enable/disable


The <b>Toolbar</b>	Select/lear <b>Toolbar</b> on the <b>View</b> menu
The <b>Status</b> bar	Select/lear <b>Status bar</b> on the <b>View</b> menu
The <b>Folders</b> panel	Select/lear <b>Folders View</b> on the <b>View</b> menu
The <b>Files</b> panel	Select/lear <b>Contents View</b> on the <b>View</b> menu
The <b>Log</b> panel	Select/lear <b>Event Log</b> on the <b>View</b> menu
The <b>Find Results</b> panel	Select/lear <b>Find Results</b> on the <b>View</b> menu

You may also arrange the data as required. On the **View** menu, select **Arrange** and then a required arrangement.

You may specify which columns will be visible in the Files panel. On the **View** menu, select **Contents Columns**, and select the columns you want to see.

Files can be shown as a list or as icons/files of different sizes.

#### Files shown as icons/files




## Recovery chances

**R-Studio** shows its estimates of chances for successful file recovery in the **Rec** column.

### Recovery chances

	Undefined
	Good
	Above average
	Average
	Below average
	Bad

When **R-Studio** has enumerated files, those estimates may not be accurate and aren't available for most files. You may improved them by right-clicking the root folder on the left pane, selecting **Recheck Recovery Chances** on the shortcut menu, and specifying required parameters.




The best estimations are though after scanning the disk/partition.

## File Information

You may view some information about a file. Right-click the file and select **Get Info** on the context menu.

### File Information



**R-Studio Technician/T80+** shows much more information about a file. See the [Information about a File](#) topic for more details.



Folders panel

Deleted\_Files

Deleted folder

Files to Delete

Marked folder (all child objects in this folder are marked)

Files to Recover

Partially marked folder (some child objects in this folder are marked)

Users

[Target of a symlinked folder](#)

Documents and Settings

[Symlink](#) to a folder

Movie


[Cross-linked](#) folder (A FAT folder containing data which also belongs to other FAT folders.)

?MP

[Questionable cross-linked](#) deleted folder (A FAT folder found by **R-Studio**, but with apparently invalid content.)

My Photos [\\Files\Photos]

[Symbolic link](#)



Files panel:

Deleted file

Deleted file:

Marked deleted file

Marked deleted file

Selected deleted file

Selected deleted file


[Target of a hard link](#)

[Target of a hard link](#)

[Hard link to a file](#)

[Hard link to a file](#)


Name	Recovery chances	Bad sectors	Size, Bytes	Created	Modified	Accessed	Fileid	ParentId
<input checked="" type="checkbox"/> Test2.arc [F:\Root\SRECYCLE\BIN\71PP5DVN]	● Undetermined (Unfragmented)	No	102,760,448	2/21/2022...	3/21/2005 10:22:26 PM	2/21/2024 12:00:00 AM	64000000000001a	644000000...
<input checked="" type="checkbox"/> Test4.arc [F:\Root\SRECYCLE\BIN\781PXCP2.arc]	● Above Average (Fragmented)	No	102,760,448	2/21/2022...	3/21/2005 10:22:26 PM	2/21/2024 12:00:00 AM	64000000000001b	644000000...
<input checked="" type="checkbox"/> Test5.arc [F:\Root\SRECYCLE\BIN\781M1PSR.arc]	● Above Average (Fragmented)	No	102,760,448	2/21/2022...	3/21/2005 10:22:26 PM	2/21/2024 12:00:00 AM	64000000000001c	644000000...
<input checked="" type="checkbox"/> Test6.arc [F:\Root\SRECYCLE\BIN\781C7Z28.arc]	● Above Average (Fragmented)	No	102,760,448	2/21/2022...	3/21/2005 10:22:26 PM	2/21/2024 12:00:00 AM	64000000000001d	644000000...
<input checked="" type="checkbox"/> Test7.arc [F:\Root\SRECYCLE\BIN\78BFQSL5.arc]	● Above Average (Fragmented)	No	102,760,448	2/21/2022...	3/21/2005 10:22:26 PM	2/21/2024 12:00:00 AM	64000000000001e	644000000...
<input type="checkbox"/> IMG_6001.JPG	● Good (Existing file)	No	656,192	2/21/2022...	5/17/2010 05:17:56 PM	2/21/2024 12:00:00 AM	640000000000012	644000000...
<input type="checkbox"/> IMG_6002.JPG	● Good (Existing file)	No	937,070	2/21/2022...	5/17/2010 05:18:14 PM	2/21/2024 12:00:00 AM	640000000000013	644000000...
<input type="checkbox"/> IMG_6003.JPG	● Good (Existing file)	No	1,180,895	2/21/2022...	5/17/2010 05:18:36 PM	2/21/2024 12:00:00 AM	640000000000014	644000000...
<input type="checkbox"/> Outlook_recovered_by_R_Mail.pst	● Good (Existing file)	No	163,840	2/21/2022...	5/14/2006 04:25:50 PM	2/21/2024 12:00:00 AM	640000000000022	644000000...
<input type="checkbox"/> test1.arc	● Good (Existing file)	No	102,760,448	2/21/2022...	3/21/2005 10:22:42 PM	2/21/2024 12:00:00 AM	640000000000015	644000000...
<input type="checkbox"/> test3.arc	● Good (Existing file)	No	102,760,448	2/21/2022...	3/21/2005 10:23:42 PM	2/21/2024 12:00:00 AM	640000000000016	644000000...
<input type="checkbox"/> Wipe Test 1.doc	● Good (Existing file)	No	22,528	2/21/2022...	11/16/2003 11:13:20 PM	2/21/2024 12:00:00 AM	640000000000017	644000000...
<input type="checkbox"/> Wipe Test 2.doc	● Good (Existing file)	No	22,528	2/21/2022...	11/16/2003 11:13:20 PM	2/21/2024 12:00:00 AM	640000000000018	644000000...
<input type="checkbox"/> Wipe Test 3.doc	● Good (Existing file)	No	22,528	2/21/2022...	11/16/2003 11:13:20 PM	2/21/2024 12:00:00 AM	640000000000019	644000000...
<input checked="" type="checkbox"/> Wipe Test 4.doc [F:\Root\SRECYCLE\BIN\78A71CE0.doc]	● Above Average (Fragmented)	No	22,528	2/21/2022...	11/16/2003 11:13:20 PM	2/21/2024 12:00:00 AM	640000000000020	644000000...
<input checked="" type="checkbox"/> Wipe Test 5.doc [F:\Root\SRECYCLE\BIN\78B0Q14E.doc]	● Above Average (Fragmented)	No	22,528	2/21/2022...	11/16/2003 11:13:20 PM	2/21/2024 12:00:00 AM	640000000000021	644000000...
<input checked="" type="checkbox"/> Wipe Test 6.doc [F:\Root\SRECYCLE\BIN\787M584D.doc]	● Above Average (Fragmented)	No	23,040	2/21/2022...	11/16/2003 11:14:08 PM	2/21/2024 12:00:00 AM	640000000000019	644000000...



### Sorted by:

You may also arrange the data as required: by their extensions, creation/modification time, or as a real file structure. See [Find and Mark Multiple Files](#) for more details.

### Find Results panel



### Select Drive

Click this button to return to the **R-Studio** main panel to select another drive.



### Reopen Drive Files

Click this button to list files again.



### Recover

Click this button to recover selected folders/files.




### Recover Marked

Click this button to recover marked folders/files.



### Find

Click this button to find or/and mark a particular file/folder.



### Find Next

Click this button to find the next object specified in the **Find/Mark** dialog box.



### Find Previous

Click this button to find the previous object specified in the **Find/Mark** dialog box.



### File Mask

Click this button to specify a file mask.




The **Unmask** button appears when a mask is applied.

Click this button to remove the applied mask.



#### Up

Click this button to move highlighting one folder up.



#### Details

A button selecting how the files will be shown: Details, Small, Medium, Large Icons



#### Preview

Click this button to [preview](#) the selected file.



#### Options

Click this button to change Recovery Options.

The Log panel will show how many files and folders are on the object, and their size. You may specify which events will be shown in the log pane by setting a [log filter](#).

**Note:** Metafiles are the file system's internal files invisible to any user, or file system data, which **R-Studio** represents as files. These files do not contain user data directly. Unless you want to scrutinize a disk file system, do not restore them.

If the Too many files... message appears, you may temporarily stop file listing and browse through found files. Then you can resume file listing. You also may skip this file topic and continue. **R-Studio** will keep information about the entire file structure.

### You may also copy the information about folders and files.

#### ▣ For the folder (the Folders pane):

Click <b>Copy Folder</b> :	To copy the folder's name
Click <b>Copy Path</b> :	To copy the path to the folder

#### ▣ For the file (the Contents pane):

Click <b>Copy (Column Name)</b> :	To copy the file's <b>Name</b> , <b>Size</b> , <b>Created</b> , etc., depending on which column is selected
Click <b>Copy Path</b> :	To copy the file path.
Click <b>Copy Selected Text</b> :	To copy all the columns of the selected file.

### Symbolic Link processing

**R-Studio** recognizes [symlinks](#) and processes them as specified in the [R-Studio Settings](#) panel. Go to the [Data Recovery Issues](#) topic for details.

You may open several disks/[partitions](#) in one tab. Read the [Opening several disks/partitions in one tab](#) help page for more details.

## 2 Select a file/folder to recover

You may select several files/folders in the same parent folder by pressing the **Shift** button and clicking the objects simultaneously.

### **Marking multiple files/folders from different parent folders manually:**

Mark a file/folder to recover by clicking the box left to the object, or select **Mark** on the shortcut menu. You may mark several files/folders in different parent folders. You may mark all objects in the folder by selecting **Mark All** on the **Tools** or shortcut menu. To unmark an object, click the box left to the object once more or select **Unmark** on the shortcut menu. You may unmark all objects in the folder by selecting **Unmark All** on the **Tools** or shortcut menu.

The Log panel will show how many files and folders you have marked, and their total size.

**R-Studio** can search for a particular file. Go to the [Searching for a File](#) topic for details. If you need to find and mark many files, go to the [Find and Mark Multiple Files](#) topic for details.

File content may be previewed before recovery. Go to the [Previewing Files](#) topic for details.

### **If you do not find files that you want to recover:**

Sometimes **R-Studio** can find the files but not the entire file paths to them. It puts such files into the **Extra Found Files** folder. Try to search for the files there. If that does not help, try to find them by using file search globally on the entire drive. Go to the [Searching for a File](#) topic for details.

If you still cannot find files that you want to recover but are sure they have existed on the logical disk, you need to use [Advanced Data Recovery](#) to find them.


## 3 Click the Recover or Recover Marked button

### **Other ways to recover selected files**


- Right-click the selected file/folder and select **Recover** or **Recover Marked** on the shortcut menu,
- or
- Select **Recover** or **Recover Marked** on the **File** menu
- or
- Press the **F2** button.

## 4 Specify recover options and output folder on the Recover dialog box and click the OK button

### Recover dialog box



## Recover (Advanced) dialog box



If you have another computer connected to **R-Studio** over network, the Recover dialog box will be slightly different. See [Data recovery over network](#) for details.

### [-] Recover options

Recover all marked files	All files, regardless of the applied mask, will be recovered.
Recovered only masked marked files	Only files matching the applied mask will be recovered.
Condense successful restoration events	If this check box is selected, <b>R-Studio</b> will display only error and warning messages in its Log
Restore folder structure	If this check box is selected, <b>R-Studio</b> recovers the entire path to the selected object.
Restore from root	If this check box is selected, <b>R-Studio</b> recovers the entire path to the selected object starting from the root folder of the disk.
Recover metafiles	If this check box is selected, <b>R-Studio</b> recovers disk metafiles. Metafiles are the file system's internal files invisible to any user, or file system data, which <b>R-Studio</b> represents as files. These files do not contain user data directly. Unless you want to scrutinize a disk file system, do not restore them.
Recover alternative data streams	If this check box is selected, <b>R-Studio</b> recovers <a href="#">alternative data streams</a> for file systems that support them. Has no effect on <a href="#">FAT</a> files. See <a href="#">Extended Information Recovery</a> for the NTFS file system, and <a href="#">Data Recovery on HFS/HFS+ File System</a> for the Mac computers.
Recover security	If this check box is selected, <b>R-Studio</b> recovers security attributes for NTFS files. Has no effect on FAT files. See <a href="#">Extended Information Recovery</a> for details.
Recover extended attributes	If this check box is selected, <b>R-Studio</b> recovers extended file attributes in the file system.
Recover real folders structure	Enabled when the files are sorted by their extensions or date. See <a href="#">Find and Mark Multiple Files</a> for details. If this check box is selected, <b>R-Studio</b> recovers the real folders/files structure on the disk rather than that of sorted files.

Skip files with <a href="#">bad sectors</a>	If this check box is selected, <b>R-Studio</b> skips files with bad sectors and displays their list on the Files with bad sectors dialog box when the recovery has been completed. You may separately decide later what to do with those files. See <a href="#">Bad sectors</a> for details. If this check box is cleared, <b>R-Studio</b> tries to read those sectors several times (specified on the <a href="#">Settings/Bad Sectors</a> dialog box), and, if fails, fills bad sectors in the recovered file with the pattern specified on the same box. Information about such files will appear in the <a href="#">Log</a> .
Do not recover duplicate files from Extra Found Files	If this check box is selected, <b>R-Studio</b> does not recover files from Extra Found Files (raw files) that are duplicates of the files found in file system (Root).
Ignore file mask	If this check box is selected, <b>R-Studio</b> recovers all content of a selected folder, ignoring a specified <a href="#">File Mask</a> .
Open local folder (folders) when done	If this check box is selected, the folder with recovered files will be opened upon recovery completion.
Advanced	Specifies options for <a href="#">mass file recovery</a>


If you want to recover multiple files at once, go to the [Recover Multiple Files](#) for more information.

### **R-Studio Technician/T80+**

It has [additional Recovery options](#).

If a file to be recovered appears to have an invalid name, a Broken File Name dialog box will appear. You may correct the name and resume file recovery.

#### Broken File Name dialog box




#### **Broken File Name properties**

File name	Shows the current incorrect file name.
New name	Field for a new file name.
Edit broken symbols only	If this check box is selected, only invalid symbols may be corrected
Change all invalid symbols to	If this check box is selected, all invalid symbols will be changed to the specified symbol
Buttons	
Rename	Click to resume file recovery
Rename All	Click to resume file recovery. All other files will be renamed according to the specified rule.
Skip	Click to skip this file
Skip All	Click to skip all files and stop file recovery

If there is no space available for the recovered files, the There is not enough space on the disk dialog box will appear. You may either select other place to store the files, skip that particular file or abort the recovery process.


There is not enough space on the disk **dialog box**



- > **R-Studio will recover the selected/arked files/folders to the specified folder and show the results in the Log pane**


The Recovery progress indicator will show the log and progress of recovery process.

Recovery progress indicator




You may see [I/O Monitor](#) (**R-Studio Technician** only) to inspect the process of drive input/output operations in real time, and change some options during the process of file recovery.

You may change some options during the process of file recovery



**Only in the Technician version**



**Note:** **R-Studio** recovers files from Ext2/3/4FS partitions, but writes it to FAT or NTFS local disks. Or you may write such files to network drives. **R-Studio** successfully recovers files from Ext2/3/4FS partitions except its security attributes. **R-Studio** recovers [symlinks](#) as files containing the path to files which *symlinks* point to.

See [Data Recovery on HFS/HFS+ file system](#) for details on recovering data from disks with the HFS/HFS+ file system

### [Opening several disk/partitions in one tab](#)

#### [Searching for a File](#)

#### [Finding Previous File Versions](#)

#### [Previewing Files](#)

#### [File Masks](#)

#### [Regular Expressions](#)

#### [Event Log](#)


### 2.1.1 Opening several disks/partitions in one tab

You may open several [disks/partitions](#) in one tab. Then you may search for files and recover them from several disks/partitions at once. This is especially useful if files are to be recovered from several recognized partitions found on one real disk/partition or a drive.

To open several disks/partitions in one tab,

- 1 Open one partition in a usual way (double-click a logical disk, for example).
- 2 Right-click the next partition, select **Show Files In Tab**, and select the tab you want the partition appear in, or drag the disk/partition from the Device view to the required tab.


#### Several partitions in one tab





## > R-Studio will show files from several partitions in one tab

### Several partitions in one tab




Now files may be searched for, marked for recovery, and recovered.

## To remove a disk/partition from the tab,

- 1 Right-click the required disk/partition in the tab and select Close drive in the shortcut menu.

### Several partitions in one tab



## > R-Studio will remove the selected disk/partition from the tab

### 2.1.2 Searching for a File

R-Studio can find a particular file, if it is difficult to find it manually in the Folders or Files panel. You can also automatically mark/unmark all found files.

#### To search for a file,

- 1 Click the Find button

#### Other ways to search for the file

- Right-click a folder and select **Find** on the shortcut menu,


OR

- Select a folder and select **Find** on the **Tools** menu

## 2 Specify a file to be found and its options on the Find dialog box, and click the OK button

Note that a [File Mask](#) may be applied.







### Find/Mark (Main) dialog box



### Find/Mark options

You may specify how to treat specified strings. Please note that **R-Studio** stores previously entered search strings.

All Files and Folders	If this option is selected, <b>R-Studio</b> applies Advanced Options to all files.
File Extensions	If this option is selected, <b>R-Studio</b> treats specified strings as file extensions
Files and Folders	If this option is selected, <b>R-Studio</b> treats specified strings as file names. Use ? for one unspecified character and * for an unlimited number of them to specify file masks.
Regular Expressions	If this option is selected, <b>R-Studio</b> treats specified strings as regular expressions
File Id	Specifies File Id that <b>R-Studio</b> assigns to a file.
Match case	If this check box is selected, <b>R-Studio</b> makes a case-sensitive search
Look at	
Files	If this check box is selected, <b>R-Studio</b> includes files into a search.
Folders	If this check box is selected, <b>R-Studio</b> includes folders into a search. Disables when the Mark/Unmark All option is selected.
Deleted files	If this check box is selected, <b>R-Studio</b> makes a search among deleted files/folders.
Existing files	If this check box is selected, <b>R-Studio</b> makes a search among existing files/folders.
Look in	Specifies where <b>R-Studio</b> searches for, and marks, files. It can look for them on the Entire partition, or in/from a certain folder. If several <a href="#">partitions</a> are opened in one tab, the places will be: All opened partitions, Selected partition, or in/from a certain folder. You may specify the starting folder for the search.

	 <ul style="list-style-type: none"> <li> identifies current opened folder.</li> <li> identifies current starting folder for the search.</li> <li> sets starting folder to the current opened folder.</li> <li> sets back current starting folder.</li> </ul>
Advanced options	If this check box is selected, <b>R-Studio</b> will use the advanced options.
Size from/up to	Specifies file size limits. See the <a href="#">Data Formats and Multipliers</a> topic for more details on data formats.
<a href="#">Bad sectors</a>	Specifies whether there are bad sectors in the files. Not known: it's unclear if there are bad sectors in the files.
Runtime image	Specifies whether the files have already been included into the runtime <a href="#">image</a> .
Recovery Chances	Specifies files with certain recovery chances.
Date	Specifies file date boundaries. Dates for Modified, Created, and Last Accessed timestamps may be set separately.
	The <b>Set for all</b> button sets the specified data for all fields.
Find/Mark options	<p>Specify what <b>R-Studio</b> does with the found files.</p> <p>The Find first/previous/next/last options. <b>R-Studio</b> stops at the first/previous/next/last file that matches the specified search criteria.</p> <p>Find all files. <b>R-Studio</b> searches for all files that matches the specified search criteria..</p> <p>The search results appear in the Find Results panel.</p> <p>Mark/Unmark All. <b>R-Studio</b> marks/unmarks all files that match the search criteria. When these options are selected, <b>R-Studio</b> marks/unmarks files only, not folders, regardless of what Look at: Folders specifies.</p> <p>Please note, that when performing a new find and mark/unmark task, <b>R-Studio</b> does not takes into consideration the previous marked/unmarked state of files. For example, if you first mark all doc files, and then all txt files, all doc files remain marked, too. To unmark them, you should specify doc once again and select Unmark files.</p>
Find/mark objects only in real paths, ignore links to folders	If this check box is selected, <a href="#">links to folders</a> will be treated as real folders: they will appear among search results or marked objects.

> **R-Studio will show/mark the found file(s)**

If you need to find and mark many files, go to the [Find and Mark Multiple Files](#) topic for details.

## To repeat the search,

- \* Click the **Find Next** or **Find Previous** buttons

### Other ways to repeat the search

- Right-click a folder and select **Find Next** or **Find Previous** on the shortcut menu  
or
- Select a folder and select **Find Next** or **Find Previous** on the **Tools** menu

## To find all files and show them in the Find Results panel,

- \* Select **Find all** on the on the Find dialog box,

or

select **Find all** on the **Tools** menu

- > **R-Studio** will show the found files in the Find Results panel

You may do the following actions on the found files:

### Recover, Mark, Preview

by right-clicking the found file and selecting the appropriate item in the shortcut menu.

## 2.1.3 Finding Previous File Versions

**R-Studio** can find previous versions of files. It searches for them in the file's current folder and in **Extra Found Files**.

File versions are searched for using file size. If the size of a files is within 10% of the original filesize, the following conditions are checked:


Conditions	Legend
File name	N
File extension	E
Recognized file type	T

## To search for previous file versions,

- 1 Right-click the file and select **Find Previous Versions of the File** on the shortcut menu

- \* **R-Studio** will show the files in the list:

### File versions



This technique can be used to find deleted original files after attacks of file encrypting viruses.

## 2.1.4 Previewing Files

**R-Studio** has a built-in file previewer that allows you to preview both existing and deleted files. You may use this feature to estimate chances for successful file recovery or to find a file to recover.

While previewing a file in the external viewer, you may recover it or mark the file for recovery using Previewer buttons.

## Previewer buttons



Mark for recovery, Previous file, Next file, Recover

## To preview a file

### 1 Right-click a file to preview in the Files panel and select Preview on the shortcut menu

#### Other ways to preview the file

- Select the file in the Files panel and click the **Preview** button,
- OR
- Select the file in the Files panel and select **Preview** on the **File** menu

### > R-Studio will show the content of the file

If you have several files open in the previewer, you may instantly close all of them by selecting **Close All Previews** on the **File** menu.


## File Previewer for Pictures:

Pictures can be previewed either as tiles within the main window of **R-Studio** or in an external previewer.

### Within the main window as tiles:

Tile size can be changed..

## Pictures as tiles



### In the external viewer:

Picture files can be zoomed in/out and rotated.


### Picture file previewer



### File Previewer for Video and Audio files:

Video and audio files can be played even without their respective application installed.


### Video file previewer



### File Previewer for Microsoft/Open/Libre Office Documents:

Documents can be shown (including embedded pictures) even without their respective applications installed. They can be zoomed in/out for better viewing.

### Microsoft/Open/Libre Office document previewer






### File Previewer for Adobe Acrobat PDF Files:

Files can be shown even without Adobe Acrobat installed.

The previewer allows the users to jump to a required page, zoom the document, and search for a required text.

Adobe Acrobat pdf document previewer



### Supported File Types:

#### Documents:

**MS Office and Open/Libre Office** files, even without the programs installed:

- Word/Writer documents: docx;
- Excel/Calc spreadsheets: xlsx;
- PowerPoint presentation: pptx.

**Office 97-2003**, without the program installed:

- Word documents: doc;
- Excel spreadsheets xls;
- PowerPoint presentation ppt.

**Adobe Acrobat** document: pdf.

#### Multimedia Files

##### Video formats:

AIFF, ASF, AVI, BFI, CAF, FLV, GIF, GXF, HLS, QuickTime, 3GP, MP4, Matroska, Maxis XA, MPEG-DASH, MPEG program stream, MPEG transport stream (including AVCHD), MXF, Material eXchange Format, SMPTE, MSN Webcam stream, NUT, Ogg, OMA, RL2, TXD, WTV.

##### Audio formats:

8SVX, AAC, AAC+, AC-3, ADPCM, AMR-NB, AMR-WB, Amazing Studio PAF Audio, Apple lossless audio, QuickTime, ATRAC, CELT, DCA (DTS Coherent Acoustics), DPCM, DSD (Direct Stream Digital), DSP Group TrueSpeech, DST (Direct Stream Transfer), DV audio, FLAC (Free Lossless Audio Codec), G.723.1, G.729, GSM, IAC (Indeo Audio Coder), iLBC (Internet Low Bitrate Codec), IMC (Intel Music Coder), Interplay ACM, MACE (Macintosh Audio Compression/Expansion), MACE (Macintosh Audio Compression/Expansion), MLP (Meridian Lossless Packing), Monkey's Audio, MP1

(MPEG audio layer 1), MP2 (MPEG audio layer 2), MP3 (MPEG audio layer 3), MPEG-4 Audio Lossless Coding (ALS), Musepack SV7/SV8, Nellymoser Asao, AVC (Audio for Video Codec), PCM A-law/µ-law, QCELP/PureVoice, QDesign Music Codec, RealAudio, Vorbis, Voxware MetaSound, WavPack, Westwood Audio, Windows Media Audio, Xbox Media Audio

#### ▣ **Graphic files (with file extensions)**

3DS Max thumbnail (max), AAA logo (bpr), ACE texture (ace), ADEX (img, rle), AIM Grey Scale (ima, im), AIPD image (aipd), ARF (arf), AT&T Group 4 (att), AT&T multigen (icn), AVHRR Image (sst), AVT RAW (raw), AWD (awd), Ability Photopaint Image (apx), Access (g4, acc), Aces200 (ace), Acorn Sprite (acorn), AdTech perfectfax (adt), Adobe Illustrator (ai), Adobe PhotoParade(images) (php), Adobe Photoshop (psd), Advanced Art Studio (ocp, art, pic), AirNav (anv), Album bébé (frm), Alias Image File (pix, als, alias), Alpha Microsystems BMP (bmp), Amapi (2d), Amica Paint (ami, [b]), Amiga IFF (iff, blk), Amiga icon (info), Amstrad Cpc Screen (cpc), Analyze (avw), Analyze-7 (img), Andrew Toolkit raster object (atk), Apollo HDRU (hdru, hdr, gn), ArcInfo Binary (hdr), Art Director (art), Artisan (art), Artist 64 (a64), Artrage (ptg), Artweaver Document (awd), Astronomical Research Network (arn), Atari grafik (pcp), Aurora (sim), Auto F/X (afx), AutoCAD DWG (dwg, dwt), AutoCAD DXF (dxf), Autocad CAD-Camera (img), Autodesk Animator (fli, flc), Autodesk QuickCAD thumbnail (cad), Autodesk SKETCH thumbnail (skf), Autodesk SketchUp component (skp, skb), Autologic (gm, gm2, gm4), Award Bios Logo (epa), Axialis Screensaver(images) (ssp), B3D(images) (b3d), BFLI (bfl, bfli, fli, flp, afl), BIAS FringeProcessor (msk, img, raw, flt), BLP textures (blp), BMF (bmf), BSB/KAP (kap), BYU SIR (sir), Bert's Coloring (bmg, ibg), Bfx Bitware (bfx), Bio-Rad confocal (pic), Blazing Paddles (pi), Bob Raytracer (bob), Brender (pix), Brooktrout 301 (brk, 301, brt), Brother Fax (uni), Buttonz & Tilez texture (til), CALS Raster (cal, cals, gp4, mil), CDU Paint (cdu), CGM (cgm), CImage (dsi), CMU Window Manager (cmu), CP8 256 Gray Scale (cp8), CSV (csv), Calamus (cpi, crg), Camera RAW (raw), Canon EOS-1D Mark II RAW (cr2), Canon Navigator Fax (can), Canon PowerShot (crw), Cartes Michelin (big), Casio QV-10/100 Camera (cam), Casio RAW (bay, raw), Chinon ES-1000 digital camera (cmt), Cisco IP Phone (cip), Cloe Ray-Tracer (clo, cloe), ColoRIX (rix, sci, sex, sc?), CompW (wlm), CompuServe GIF (gif, giff), Computer Eyes, Digital Vision (ce), ComputerEyes Raw (ce1, ce2), Contax RAW (bay, raw), Core IDC (idc), Corel Draw Bitmap(preview) (cdr), Corel Draw Pattern(preview) (pat), Corel Flow(preview) (bmf), Corel Metafile Exchange(preview) (cmx), Corel PhotoPaint 6.0 (cpt), CoverDesigner(images) (ncd), CoverDesigner Template(images) (nct), Crayola (art), Creative PC-CAM RAW (bay, raw), DBW Render (), DIV Game Studio Map (map), DIV Game Studio Multi Map (fpg), DKB Ray-Tracer (dis), DNG (dng), DPX (dpx), Dali Raw (sd0, sd1, sd2), Datacopy (img), Degas & Degas Elite (pil, pc1, pi2, pc2, pi3, pc3, pi4, pi5, pi6), Deluxe Paint, Electronic Arts (lbm, ilbm), Dicom (dcm, acr, dic, dicom, dc3), Digital F/X (tdim), Digital Research(GEM Paint) (img, gem), Direct Draw Surface (dds), Discorp CMP Image (cmp), DjVu (djvu, djv, iw4), DolphinEd (dol), Doodle Atari (doo), Doodle C64 (dd), Doodle C64(Compressed) (jj), Dr Halo (cut), Draz Paint (drz), EA Sports FSH (fish), EPS Interchange Format (epi, ept), ERI-chan(Entis Rasterized Image) (eri), ESM Software Pix (pix), Ecchi (ecc), Eclipse (tile), Edmics (c4), Egg Paint (trp), Electric Image (ei, eidi), Embroidery (bmc), Encapsulated Postscript (ps, eps), Encapsulated Postscript (Preview) (eps), Enhance Simplex (esm), Enhanced Compressed Wavelet (ecw), Epson RAW (erf), Eroïca (eif), Everex Everfax (efx, ef3), Explore(TDI) & Maya (iff, tdi), FIF(Iterated System) (fif), FIT (fit), Face Painter (fpt), Fast Piecewise-constant (pwc), Fax Group 3 (g3, fax), Fax man (fmf), Faxable PCX (fcx), Faxable TIFF (ftf), Fenix Map (map), Fenix Multi Map (fpg), FileMagic (mag), Flash Image (fi), FlashCam Frame (ncy), FlashPix Format (fpx), Flexible



Image Transport System (fts, fits, fit), Foculus RAW (bay, raw), Fantasy Grafik (bsg), Fremont Fax96 (f96), Fugawi Map (fx3), Fuji S2 RAW (raf), Fun Painter II (fp2, fun), Fun Photor (fpr), Fuzzy bitmap (fbm, cbm), GRS16 (g16), Gamma Fax (gmf), GeoPaint (geo), Gfa Raytrace (sul), GigaPaint Hi-res (gih), GigaPaint Multi (gig), Gimp Bitmap (xcf), Gimp Brush (gbr), Gimp Icon (ico), Gimp Pattern (pat), GoDot (4bt, 4bit, clp), GunPaint (gun, ifl), HD Photo (wdp, hdp), HDRI (hdr, hdri), HF (hf), HP-48/49 GROB (gro, grb), HP-49 OpenFire (gro2, gro4), HPGL-2 (hp, hpg, hgl, plt, hpgl, hpgl2, gl2, prm, prt, spl), HRU (hru), HSI Raw (raw), Half-Life Model (mdl), Hasselblad RAW (3fr), Hayes JTFax (jtf), Hemera Photo Image (hpi), Hemera Thumbs (hta), Heretic II MipMap (m8), Hi-Eddi (hed), Hires C64 (hir, hbm), Homeworld Texture (lif), IBM Kips (kps), IBM Printer Page Segment (pse), IM5(Visilog) (im5), IMNET Image (imt), IOCA (ica, ioca, mod), IPLab (ipl), iPod thumb (ithmb), ISS (iss), IcoFX (ifx), Icon Library (icl), Imacon/Hasselblad RAW (fff), Image Capture Board (icb), Image Magick file (mif, miff), Image Speeder (ish), Image System(Hires) (ish), Image System(Multicolor) (ism), Image Systems RLC2 Graphic (rlc), ImageLab (b&w, b\_w), ImagePro Sequence (seq), Imaging Fax (g3n), Imaging Technology (img), Img Software Set (img), Inshape (iim), InterPaint(Hires) (iph), InterPaint(Multicolor) (ipt), Intergraph Format (itg, cit, rle), Interleaf (iimg), Iris CT (ct), Iris Graphics (iris), J Wavelet Image Codec (wic), JBIG (jbg, bie, jbig), JBIG-2 (jb2), JFIF based file (jb2), JPEG/JFIF (jpg, jpeg, jif, jfif, J, jpe), JPEG 8BIM header(Mac) (jpg, jpeg, jif, jfif, J, jpe), JPEG XR (jxr), JPEG-2000 Code Stream (jpc), JPEG-2000 JP2 File Format (jp2, j2k, jpx, jpf), JPEG-LS (jls), Jeff's Image Format (jif), Jigsaw (jig), Jovian VI (vi), Jpeg Network Graphics (jng), JustButtons animated bitmap (btn), KONTRON (img), Khoros Visualization Image file (vif, viff, xv), KinuPix Skin (thb), Kiss Cel (cel), Koala Paint (koa, kla), Koala Paint(Compressed) (gg), Kodak Cineon (cin), Kodak DC120 Digital Camera (kdc), Kodak DC25 Camera (k25), Kodak Photo CD (pcd), Kodak Pro Digital RAW (dcr), Kofax Group 4 (kfx), Kolor Raw Format (kro), Konica Camera File (kqp), LSS16 (lss, 16), LView Pro (lvp), LaserData (lda), Leaf RAW (mos), Leica RAW (bay, raw), Light Work Image (lwi), LucasFilm Format (lff), Lumena CEL (cel), LuraDocument Format (ldf), LuraDocument.jpM Format (jpm), LuraWave Format (lwf), LuraWave JPEG-2000 Code Stream (jpc), LuraWave JPEG-2000 Format (jp2, j2k, jpx, jpf), MAKIchan Graphics (mag), MGI Photosuite Project(images) (pzp), MGR bitmap (mgr), MRC(Medical Research Council) (mrc), MTV Ray-Tracer (mtv), Mac Paint (mac, mpnt, macp, pntg, pnt, paint), Mac icon (icns), Macintosh Quickdraw/Pict (pic, pict, pict2, pct), Mac OSX Resource (rsc, rsrc), Maggi Hairstyles & Cosmetics (fff), Male MRI (pd, t1, t2), Male Normal CT (fre), Mamiya RAW (mef), Marks Russel File (mrf), Mavica (411), Maw-Ware Textures (mtx), Mayura Draw (pdx), MegaPaint (bld), Megalux Frame (frm), Micro Dynamics MARS (pbt), Micro Illustrator Uncompressed (mil), Micrografx Picture Publisher 4.0 (pp4), Micrografx Picture Publisher 5.0 (pp5), Micron RAW (bay, raw), Microsoft Image Composer (mic), Microsoft Paint (msp), Microtek Eyestar (img), Mindjongg Format (ipg), Minolta DiIMAGE RAW (mrw), Mobile FAX (rfa), MonkeyCard (pdb), MonkeyLogo (pdb), MonkeyPhoto (mph), MrSid (sid), Msx 2 Screen (sc2), Multiple Network Graphics (mng), NCR Image (ncr), NIST ihdr (pct), National Imagery Transmission F. (ntf, nitf), NeoBook Cartoon (car), Neochrome(ST & TT) (neo), Neopaint Mask (npm), Neopaint Stamp (stw), NewsRoom (nsr, ph, bn), Nifti (img), Nikon RAW (nef), Nokia Group Graphics (ngg), Nokia Logo File (nlm), Nokia OTA bitmap (otb), Nokia Operator Logo (nol), OAZ Fax (oaz, xfx), OS/2 Bitmap (bmp, bga), Olicom Fax (ofx), Olympus RAW (orf), Open Image Library Format (oil), OpenEXR (exr), Optigraphics (ctf), Optigraphics Tiled (ttf), Optocat (abs), Oric Hires (hir), Oric TAP (tap), OS/2 Warp (bga), PABX background (pix), PAX (pax), PC Paint/Pictor Page (pic, clp), PCO (b16), PM (pm), Page Control Language (pcl), Paint Magic (pmg), PaintShopPro Browser Cache File (jbf), PaintShopPro Brush (psbrush), PaintShopPro Brush (jbr), PaintShopPro Frame (pfr, pspframe), PaintShopPro Image (psp, pspimage), PaintShopPro Mask (pspmask), PaintShopPro Mask (msk),

PaintShopPro Pattern (pat), PaintShopPro Picture Tube (tub, psptube), PaintShopPro Texture (tex), Palm Pilot (pdb), Panasonic DMC-LC1 RAW (srf), Panasonic LX3 RAW (rw2), Panasonic RAW (bay, raw), Pegs (pxs, pxa), Pentax \*ist D (pef), Pfs Art Publisher (art), Photo Deluxe (pdd, pdb), Photo Filtre Studio (pfi), PhotoFantasy Image (fsy), PhotoFrame (frm), PhotoStudio File (psf), PhotoStudio Stamp (stm), Photomatrix (cat), Pic2 (p2), Picasso 64 (p64), Picture Gear Pocket (prc), Picture It! (mix), Pixar picture file (pic, pxr, picio, pixar), Pixel Power Collage (ib7, il7, il8, if9), Pixia (pxa), Pixibox (pxb), Planetary Data System (pds, img), Playback Bitmap Sequence (bms), Pocket PC Bitmap (2bp), Pocket PC Themes(images) (tsk), Polychrome Recursive Format (prf), Portable Bitmap (pbm, rpbm, ppma), Portable Document Format (pdf), Portable Greyscale (pgm, rpgm), Portable Image (pnm, rpnm, pbm, rpbm, pgm, rpgm, ppm, rppm), Portable Network Graphics (png, apng), Portable Pixmap (ppm, rppm), Portfolio Graphics (pgf), Portfolio Graphics Compressed (pgc), Portrait (cvp), Poser Bump (bum), Postscript (ps, ps1, ps2, ps3, eps, prn), PowerCard maker (crd), PowerPoint(images) (pps), PowerPoint Presentation(images) (ppt), Print Master (pm), Print Shop (psa, psb), Printfox/Pagefox (bs, pg, gb), Prism (cpa), Prisms (pri), Psion Series 3 Bitmap (pic), Psion Series 5 Bitmap (mbm), Punk Productions Picture (ppp), Puzzle (pzl), Q0 (q0, rgb), Qdv(Random Dot Software) (qdv), Qrt Ray-Tracer (qrt), Quake Texture (wal), Quantel VPB (vpb), QuickTime Image Format (qtif, qti), RAW DVR (raw), RIPTerm Image (icn), Radiance (rad, img, pic), Rainbow Painter (rp), Raw (raw, gry, grey), Rawzor (rwz), Rayshade (pic), Red Storm File Format (rsb), Ricoh Digital Camera (j6i), Ricoh Fax (001, ric), Ricoh IS30 (pig), Rm2K XYZ (xyz), Rollei RAW (rdc, ia), RoverShot RAW (bay, raw), RunPaint(Multicolor) (rpm), Saracen Paint (sar), SBIG CCD camera ST-4 (st4), SBIG CCD camera ST-X (stx, st4, st5, st6, st7, st8), SciFax (sci), SciTex Continuous Tone (sct, ct, ch), Seattle Film Works (sfw), Seattle Film Works multi-image (pwp, sfw), SecretPhotos puzzle (xp0), Sega SJ-1 DIGIO (sj1), Sharp GPB (img), Siemens Mobile (bmx), SIF MICHEL-Soft (sif), Sigma RAW (x3f), Silicon Graphics RGB (rgb, rgba, bw, iris, sgi, int, inta), Sinar RAW (cs1, sti), Skantek (skn), Slow Scan Television (hrz), SmartDraw 6 template (sdt), SmartFax (1), SmoothMove Pan Viewer (pan), Softimage (pic, si), Solitaire Image Recorder (sir), Sony DSC-F1 Cyber-shot (pmp), Sony DSC-F828 RAW (srf), Sony PS2 TIM (tm2), Sony Playstation TIM (tim), Sony RAW (sr2, arw), Spectrum 512 (spu), Spectrum 512(Compressed) (spc), Spectrum 512(Smooshed) (sps), SPOT (dat), SriSun (ssi), Stad (pic, pac, seq), Star Office Gallery (sdg), Starbase (img), Stardent AVS X (x, avs, mbfs, mbfavs), Starlight Xpress SX (RAW), Stereo Image (jps), ST Micro RAW (bay, raw), Structured Fax Format (sff), Sun Icon/Cursor (icon, cursor, ico, pr), Sun Rasterfile (ras, rast, sun, sr, scr, rs), Sun TAAC file (iff, vff, suniff, taac), Syberia texture (syj), Synthetic Universe (syn, synu), SVG (svg), TG4 (tg4), TI Bitmap (92i, 73i, 82i, 83i, 85i, 86i, 89i), TIFF Revision 6 (tif, tim, tiff), TMSat image (imi), TRS 80 (hr), TealPaint (pdb), Teli Fax (mh), Thumbnail (tnl), TilePic (tjp), Tiny (tny, tn1, tn2, tn3), TopDesign Thumbnail (b3d, b2d), Total Annihilation (gaf), Truevision Targa (tga, targa, pix, bpx, ivb), Ulead Pattern (pst), Ulead PhotoImpact (upi), Ulead Texture(images) (pe4), Usenix FaceServer (fac, face), Utah raster image (rle, urt), VIPS Image (v), VITec (vit), VRML2 (wrl), Venta Fax (vfx), Verity (vif), Vicar (vic, vicar, img), Vidcom 64 (vid), Video Display Adapter (vda), Vista (vst), Vivid Ray-Tracer (img), Vort (pix), Vue d'esprit (vob), WAD(Half life) (wad), WSQ (wsq), WaveL (iwc), Wavefront Raster file (rla, rlb, rpf), WebShots(images) (wb1, wbc, wbp, wbz), Weekly Puzzle (jig), WebP (webp, wep), Whypic (ypc), WinFAX (fxs, fxo, wfx, fxr, fxd, fxm), WinMIPS (pic), Windows & Aldus Metafile (wmf), Windows Animated Cursor (ani), Windows Bitmap (bmp, rle, vga, r14, r18, sys), Windows Clipboard (clp), Windows Comp. Enhanced Metafile (emz), Windows Compressed Metafile (wmz), Windows Cursor (cur), Windows DIB (dib), Windows Enhanced Metafile (emf), Windows Icon (ico), Winzle Puzzle (wzl), Wireless Bitmap(level 0) (wbmp, wbm, wap), Word Perfect Graphics(images) (wpg), Worldport Fax (wfx), X Windows System dump (xwd, x11), X11 Bitmap (xbm, bm), X11 Pixmap (xpm, pm), XV Visual

Schnauzer (p7), Xara(images) (xar), Xerox DIFF (xif), Ximage (xim), Xionics SMP (smp), YUV 16Bits (yuv, qtl, uyvy), YUV 16Bits Interleaved (yuv, qtl, uyvy), YUV 4:1:1 (yuv, qtl), YUV 4:2:2 (yuv, qtl), YUV 4:4:4 (yuv, qtl), ZX Spectrum Hobetta (\$s, \$c, !s), ZX Spectrum Snapshot(sna), ZX Spectrum standard (screen scr), ZZ Rough (rgh), Zeiss BIVAS (dta), Zeiss LSM (lsm), Zoner Callisto Metafile(zmf), Zoner Zebra Metafile (zbr), Zsoft Multi-page Paintbrush (dcx), Zsoft Publisher's Paintbrush (pcx, pcc, dcx), byLight (bif)

### 2.1.5 File Masks

**R-Studio** shows only those files/folders that match the specified file mask. File mask affects files/folders that are processed by the **Recover** and **Find** commands.

**To specify a file mask,**


#### 1 Click the File Mask button

##### Other ways to specify the file mask

- Right-click a folder and select **File Mask** on the shortcut menu
- OR
- Select the folder and select **File Mask** on the **Tools** menu


#### 2 Specify the file mask on the File mask dialog box and click the OK button

Mask dialog box



##### File mask options

You may specify options for All Files, File Extensions, Files, and Regular Expressions	
Match case	If this check box is selected, <b>R-Studio</b> makes a case-sensitive search.
Show empty folders	If this check box is selected, <b>R-Studio</b> will show folders with no files in them.
Deleted files	If this check box is selected, <b>R-Studio</b> makes a search among deleted files/folders.
Existing files	If this check box is selected, <b>R-Studio</b> makes a search among existing files/folders.
Hide symbolic links	If this check box is selected, <b>R-Studio</b> hides all <a href="#">symbolic links</a> . It may be selected by default if the Don't show symbolic links by default option is selected on the <a href="#">Settings</a> dialog box.
Use advanced options	If this check box is selected, <b>R-Studio</b> will use the advanced options, even when they are hidden.
<a href="#">Advanced Options</a>	
Size from/up to	Specifies file size limits. See the <a href="#">Data Formats and Multipliers</a> topic for more details on data formats.

<a href="#">Bad sectors</a>	Specifies whether there are bad sectors in the files. Not known: it's unclear if there are bad sectors in the files.
Runtime image	Specifies whether the files have already been included into the runtime image.
Date	Specifies file date boundaries. Dates for Modified, Created, and Last Accessed timestamps may be set separately.
	The <b>Set for all</b> button sets the specified data for all fields.

> **R-Studio will show only those files that match the specified file masks**

Click the **Unmask** button to remove the applied mask.

### Mask presets

You may set various presets with different file masks. Just click on the Plus button to add the data from the dialog box to the presets. You may also give presets names, delete them, and store them permanently.

#### 2.1.6 Regular Expressions

Regular expression is a notation for patterns of text, as opposed to exact strings of characters. The notation uses literal characters and metacharacters. Every character which does not have special meaning in the regular-expression syntax is a literal character and matches an occurrence of that character. For example, letters and numbers are literal characters. A metacharacter is a symbol with special meaning (an operator or delimiter) in the regular-expression syntax.

.	Wildcard: any character
*	Repeat: zero or more occurrences of previous character or class
^	Line position: beginning of line
\$	Line position: end of line
[class]	Character class: any character in the set
[^class]	Inverse class: any character not in the set
[x-y]	Range: any characters within the specified range
\x	Escape: literal use of metacharacter x
\<xyz	Word position: beginning of the word
xyz\>	Word position: end of the word

For example, the following regular expression `.*` matches any string of characters, `^a` matches any string beginning with character a.

#### 2.1.7 Event Log

**R-Studio** logs and displays events in the Log panel. You may set a **Log filter** to display only needed information and to write it to a log file. You may specify the log settings on the [Settings](#) dialog box.

You may clear or save the log

##### To clear the log,

- \* Right-click the **Log** panel and select **Clear Log** on the shortcut menu.

##### To save the log to a file,

- \* Right-click the **Log** panel and select **Save Log to File** on the shortcut menu.

You may copy data from separate messages:

Click **Copy (Column Name)**: To copy the record's Type, Date, Time, Text, depending on which column is selected

Click **Copy Selected Text**: To copy all the columns of the selected record.

## 2.2 Advanced Data Recovery

This chapter explains how to perform advanced data recovery operations.

- [Drive Scan](#)
- [Fast-Search-for-Lost-Partition](#)
- [Customizing File Types](#)
- [Customizing File Types-I](#)
- [Customizing File Types-II](#)
- [Regions](#)
- [Exclusive Regions](#)
- [Images](#)
- [Wiping Objects](#)

### 2.2.1 Drive Scan

In order to completely analyze data structure on an object, it must be scanned. Any object in the Drives panel can be [scanned](#). In addition, you may create a **region** to scan only a part of an object. The [Regions](#) topic explains how to create and work with **regions**. Scan is also greatly improves estimations for chances of successful file recovery.

You may select scan area and some other scan parameters. Scan information may be saved to a file and later this file may be opened.

You may save scan information on the remote computer if necessary.

**Note:** You may use [Fast Search for Lost partitions](#) if you want only to find partitions previously existed on the drive. It's much faster.

**Attention: Scanning large areas may be a very lengthy process!**

**NEVER TRY TO SAVE SCAN INFORMATION TO THE OBJECT BEING SCANNED!!!**

**Or you may obtain unpredictable results and lose all of your data.**

**To scan an object**


- 1 **Select an object in the R-Studio's Drives panel**
- 2 **Click the Scan button**

**Other ways to start scan**

- Right-click the selected drive and select **Scan** on the shortcut menu,  
or
- Select **Scan** on the **Drive** menu

### 3 Specify the required parameters on the Scan dialog box and click the Scan button

#### Scan dialog box




#### Scan options

Drive Size:	Shows the size of the object to be scanned
Start:	Sets the start point of the area to be scanned.
Size:	Sets the size of the area to be scanned.
Numbers in these fields can be in bytes or sectors. See the <a href="#">Data Formats and Multipliers</a> topic for more details on data formats.	
File Systems:	Specifies the file systems which objects are to be searched for. Current version supports: <a href="#">FAT</a> , NTFS, <a href="#">exFAT</a> , ReFS, <a href="#">Ext2/3/4FS</a> , <a href="#">XFS</a> , HFS, APFS, and <a href="#">UFS</a> file systems. The Technician version supports also the ISO9660 file system. Please note that if you need to scan an HFS, HFS+, or HFSX disk, always enable the Extra search for <a href="#">Known File Types</a> option. This is very important because when files are being deleted on the HFS, HFS+, HFSX file systems, the computer completely removes all system information on them, and there is no way to recover the deleted files except by using the Extra Search for Known File Types option. See <a href="#">Data Recovery on HFS/HFS+ file system</a> for details.
Extra search for Known File Types	Enables search for Known File Types.
Save scan Info to File:	If this checkbox is selected, <b>R-Studio</b> will save scan information to a specified file. Later this file may be opened. Please note, that this option does not save actual drive data, only information on drive data structure gathered during drive scan. If
Simple view	If this option is selected, <b>R-Studio</b> will show only scan progress.
Detailed view	If this option is selected, <b>R-Studio</b> will show graphic representation on objects found during scan.
None	If this option is selected, <b>R-Studio</b> will not show the Scan Information tab during scan.
Buttons	
Scan	Starts scanning
Advanced	Activates advanced scan options
Known File Types...	Selects file types that <b>R-Studio</b> will recognize during the drive scan.


Cancel	Closes the dialog box
--------	-----------------------

<b>NEVER TRY TO SAVE SCAN INFORMATION TO THE OBJECT BEING SCANNED!!! Or you may obtain unpredictable results and lose all of your data.</b>
---

If a remote computer is connected for [Data Recovery over Network](#), the Scan dialog box will have a different look




and the Save Scan Information File dialog box will appear when you select a place to store scan info. You may save it to the local or remote computer.



**Known File Types (raw file search):** While scanning, **R-Studio** can recognize the data's particular file type. Using such information, **R-Studio** can obtain more information about data/file structure on the object being scanned. By default, **R-Studio** tries to recognize the default list of supported file types specified on the Known File Types tab of the [Settings](#) panel, greatly increasing time required for the scan. You may reduce it by selecting only those file types that you need. Click the **Known File Types...** button and select the required file types on the File Types dialog box. These selections will be applied to that scan session only.

**R-Studio** places such found files in the Raw Files section in the the Drives panel.

### File Types dialog box



### Known File Types

Set as Default	Click this button to set the current list of selected file types as default values.
Revert to Default	Click this button to revert the default settings specified on the Known File Types tab of the <a href="#">Settings</a> panel.
Reset to Recommended	Click this button to revert to factory-preset default settings.
Select All	Click this button to select all file types in the list.

Clear All

Click this button to clear all file types in the list except some predefined ones.

▣ **List of known file types**

<b>Document</b>			
AbiWord Document: .abw	Adobe InDesign File: .indd	Adobe PDF document: .pdf	Apple iWork Keynote document: .key
Apple iWork Pages document: .pages	Apple iWork document	Capella document: .cap	Final Draft Document: .fdr
FrameMaker Document: .fm	GNU Info Document: .info	Garmin MapSource data: .mps	Lotus AMI Pro Document: .sam
Lotus Organizer: .or5	Lotus Word Pro Document: .lwp	Microsoft Office Open XML Document	Microsoft OneNote section file: .one
Microsoft Pocket Streets Map File: .mps	Microsoft PowerPoint 2007 XML Document: .pptx	Microsoft PowerPoint Document: .ppt	Microsoft Visio document: .vsd
Microsoft Word 2007 XML Document: .docx	Microsoft Word Document: .doc	Word for Macintosh Document: .mcw	Microsoft Word2 Document: .doc
Microsoft Works document: .wps	OLE Storage	OpenOffice Writer document: .odt	OpenOffice document: .ods
PageMaker Document: .p65	PostScript document: .ps	QuarkXPress file: .qxd	QuarkXpress project: .qxp
Rich Text Document: .rtf	TEX document: .tex	Text document: .txt	Unicode document: .txt
WordPerfect Document: .doc			
<b>Document: E-book</b>			
Chaoxing SSReader eBook: .pdg	EPUB eBook: .epub	FB2 eBook: .fb2	MOBI eBook: .mobi Microsoft Money Data: .mny
Microsoft Reader eBook: .lit	Microsoft Reader eBook annotations: .ebo		
<b>Document: Spreadsheet</b>			
Apple iWork Numbers document: .numbers	Lotus 1-2-3 v1 worksheet: .wk3	Lotus 1-2-3 v2 workshee: .wk1, .fmt	Lotus 1-2-3 v3 worksheet: .wk3, .fm 3
Lotus 1-2-3 v4 worksheet: .wk4	Lotus 1-2-3 workbook: .123	Microsoft Excel 2/3/4 worksheet: .xls	Microsoft Excel 2007 XML Document: .xlsx
Microsoft Excel 4 Spreadsheet: .xls	Microsoft Excel Spreadsheet: .xls	Quattro Pro Spreadsheet: .wq1	



<b>Document: Database</b>			
Cathy database: .caf	Data Interchange Format file: .dif	GDSII database: .gds	Microsoft Access 2007 XML Document: .accdt
Microsoft Access 2007 Database: .accdb	Microsoft Access Database: .mdb	Microsoft SQL Log: .ldf	Microsoft SQL Database: .mdf
MySQL Database Dictionary: .frm	MySQL database: .myi	Omnis Studio Library: .lbs	Omnis Studio Database: .df1
OpenOffice Base document: .odb	dBase III Database: .dbf		
<b>Document: Financial</b>			
Microsoft Money Data: .mny	QuickBooks Backup File: .qbb	QuickBooks Primary Data File: .qbw	Quicken Data: .qdf
TurboTax return file: .tax			
<b>Internet-related files</b>			
Compiled HTML file: .chm	Internet shortcut: .url	Microsoft Outlook Personal Folder: .pst	Microsoft Outlook/? Inbox offline folder: .ost
Mozilla Firefox browser extension: .xpi	Mozilla Mail Summary file: .msf	Outlook Express Messages: .dbx	The Bat! Address book: .abd
The Bat! Message Base: .tbb	The Bat! Message Index: .tbi	Windows Address Book: .wab	XML document (Unicode): .xml
<b>Email</b>			
E-Mail Message: .eml	Microsoft Outlook Personal Folder: .pst	Microsoft Outlook Inbox offline folder: .ost	Mozilla Mail Summary file: .msf
Outlook Express Messages: .dbx	The Bat! Address book: .abd	The Bat! Message Base: .tbb	The Bat! Message Index: .tbi
Windows Address Book: .wab			
<b>Font</b>			
Adobe PostScript Font: .pfb	Adobe Printer Font: .pfm	BDF Unix font: .bdf	BGI font: .chr
CPI DOS font: .cpi	OpenType font: .otf	TrueType Font: .ttf	Windows System Font: .fon
<b>Graphics/Picture</b>			
AVHRR Satellite image: .sst	Adobe Lightroom preview: .lrprev	Adobe Photoshop image: .psd	Agfa/Matrix Scodl Image: .scd
Alias Wavefront Raster Image: .rla	Amiga icon: .info	ArcView Shape: .shp	AutoCAD Binary Image: .dxf

AutoCAD Drawing: .dwg	AutoCAD Image: .dxf	Autodesk Animator Pro color palette: .col	Autodesk Animator Pro Image: .pic
Autodesk Animator Image: .pic	Autologic Image: .gm	BMF image: .bmf	Bentley MicroStation CAD Drawing: .dgn
Canon (CR2) RAW graphics file: .cr2	Canon (CRW) RAW graphics file: .crw	ColorIX Image: .rix	Computer Graphics Metafile image: .cg
ComputerEyes Raw Image: .cel, .cel	Continous Edge Graphic Image: .ceg	Corel Texture Image: .tex	CorelDraw CMX Image: .cmx
CorelDraw Image: .cdr	Cubcomp Picture Maker Image .r8, .g8, .b8	DICOM medical image: .dcm	Digital Negative image: .dbg
Dr. Halo palette: .pal	Enhanced MetaFile Image: .emf	Epson RAW image: .erf	Epson Stylus Image: .prn
Erdas LAN/GIS Image: .lan, .gis	Fractal Image Format: .fif	Freehand (MX) Database: .fh10	Fuji RAW image: .raf
GEM Raster Image: .img	GEM VDI Image: .gdi	CompuServe GIF Image: .gif	Garmin Mapsource image: .img
Graphics Workshop for Windows Thumbnail: .thn	Gridded Binary Image: .grb	HP Command Language Image: .pcl	HP Raster Image: .rtl
HSI JPEG Image: .hsi	Hemera Photo-Object Image: .hpi	Hitachi Raster Image: .hrf	Hotspot Image: .shg
IBM Picture Maker Image: .pic	JPEG 2000: .jp2	JPEG Digital Camera: .jpg	JPEG Image: .jpg
Jovian Logic Image: .vi	Kodak PhotoCD Image: .pcd	Kodak RAW image: .dng	LBM/IFF Image: .lbm
Leica RAW image: .dng	Lightwave Object: .lwo	Lotus PIC Image: .pic	Macintosh PICT Image: .pct, .pic
Macintosh Paint Image: .mac	Mamiya RAW image: .mef	McIDAS Satellite Image: .goe	Microsoft Paint Image: .msp
Minolta RAW image: .mrw	Nikon RAW image: .nef	OS/2 Icon: .ico	Olympus RAW image: .orf
PBM Image: .pbm	PGM Image: .pgm	PIX Image: .pix	PM Image: .pm
PNG Image: .png	PPM Image: .ppm	PaintShop Pro Image: .psp	Panasonic RAW image: .rw2
PaperPort Image: .max	Pentax RAW image: .pef	Pictor PC Paint Image: .pic	Print Shop Image: .pds
Quick Link II fax Image: .qfx	QuickDraw 3D Metafile: .3dmf	RAW Digital Camera image: .dng	RenderMan Image: .rib
Ricoh RAW image: .dng	SGI Image: .sgi	STAD Image: .pac	Samsung RAW image: .dng

Seattle FilmWorks/? PhotoWorks image: .pwm	Sigma RAW image: .x3f	Sketch Image: .sk	SmartDraw file: .sdr
Sony RAW image: .arw	Sun Raster Image: .sun	SymbianOS Image: .mbm	TI Image: .92i
Tagged Image Format File: .tif	TargetExpress image: .mte	Utah Raster Toolkit Image: .rle	VITec Image: .vit
Webshots Image: .wb1	Weresc CADE drawing: .drc	Windows Animated cursor: .ani	Windows Bitmap Image: .bmp
Windows Color Palette: .pal	Windows Fax Cover Image: .cpe	Windows MetaFile Image: .wmf	Windows cursor: .cur
Windows icon: .ico	WordPerfect Graphics Image: .wpg	X PixMap Image: .xpm	X Window Dump Image: .xwd
Xara Drawing: .xar	ZSoft PCX Image: .pcx	iPhoto Image: .attr	
<b>Multimedia: Audio Files</b>			
AIFF Sound: .aif	AVR Sound: .avr	AY Chip music: .ay	AdLib Tracker 2 module: .a2m
Advanced Streaming Format file: .asf	Audacity audio: .au	AudioCD file: .cda	Battery 3 sample: .nov
CMF music: .cmf	Common Loudspeaker Binary: .cfl	Creative voice file: .voc	DiamondWare sound: .dwd
Digital Speech File: .dss	Digital voice file: .dvf	EA ASF/MUS audio file: .asf	Extended M3U playlist: .m3u
FLAC audio file: .fla, .flac	KaraBox sound: .mkf	La Lossless audio file: .la	Liquid Audio File: .la1
MIDI Instrument definition: .idf	MIDI music: .mid	MIDI stream: .mds	MPEG Layer I audio file: .mpg
MPEG Layer II audio file: .mp2	MPEG Layer III audio file: .mp3	MUS music: .mus	Monkeys audio file: .ape
Musepack audio file: .mpc	Next/Sun uLaw sound: .au	Nitro Composer sound: .minincs	Nord Modular G2 Patch: .pch2
Ogg Vorbis audio file: .ogg	OptimFROG audio file: .ofr	Portable Sound Format: .psf	RIFF MIDI music: .rmi
RK Audio sound: .rka	Sierra AUD sound: .aud	Sony OpenMG audio file: .oma	Super NES audio file: .spc
TTA audio file: .tta	VQF sound: .vqf	WavPack audio file: .wv	Westwood AUD sound: .aud
Windows Media Audio File: .wma	Windows WAVE sound: .wav	X-MIDI music: .xmi	ZyXEL sound: .zyx
aPac audio file: .apc			
<b>Multimedia: Video Files</b>			

3GPP multimedia audio/? video: .3gp	3GPP2 multimedia audio/video: .3g2	4X Movie Video: .4xm	Adobe Filmstrip Animation: .fsf
AMV Video: .amv	ARMovie video: .rpl	Adobe Filmstrip animation: .fsf	Autodesk Animator: .fli
BINK Video: .bik	BluffTitrer video: .bt	DVM video: .dvm	DeluxePaint animation: .anm
Director video: .dcr	DriveCam video: .dce	Eyemail video: .eye	Flash Video: .flv
Intel DVI Video: .dvi	Intel Indeo Video File: .ivf	Interplay MVE Video: .mve	LZA animation: .lza
LZA Animation: .lza	Lotus ScreenCam video: .scm	MPEG Transport Stream video: .mts	MPEG video: .mpg
MPEG-2 Transport Stream video: .m2ts	Matroska video: .mkv	MythTV video: .nuv	NEOchrome animation: .ani
Nancy Codec video: .noa	Nullsoft Video: .nsv	QV-10 video: .cam	QuickTime video: .mov
SGI movie format: .mv	SMJPEG Video: .mjpg	Sega FILM/CPK video: .cpk	Shockwave video: .swf
Smacker video: .smk	Sony Movie Player video: .mqv	VOB video files: .vob	VP6 encoded Video: .vp6
VideoCD video: .vcd	Vivo streaming video: .viv	Windows AVI Video: .avi	Windows Media Video: .wmv
<b>Multimedia Files</b>			
MP4 file: .mp4	Material Exchange File: .mxf	RIFF Multimedia File	Real Networks audio/? video: .rm
<b>Archive Files</b>			
7-Zip archive: .7z	ACE archive: .ace	AIN archive: .ain	ARJ archive: .arj
ARX archive: .arx	Android Package: .apk	BAG archive: .bag	BIX archive: .bix
BOA archive: .b58, .boa	BZip2 archive: .bz2	BlackHole archive: .bh	Blink archive: .bli
CPIO archive: .cpio	ChArc archive: .chz	Compress archive: .z	Crush archive: .cru
DEB archive: .deb	FOXSQZ archive: .sqz	GZip archive: .gz	HA archive: .ha
HAP archive: .hap	HPack archive: .hpk	Hyper archive: .hyp	InstallShield CAB archive: .cab
InstallShield Z archive: .z	InstallShield compressed file	JAR archive: .jar	JRC archive: .jrc
LHA/LZARK archive: .lzh	LZA archive: .lza, .lzz	LZOParchive: .lzo, . lzop	LZX archive: .lzx
LIMIT archive: .lim	Microsoft Cabinet archive: .cab	Microsoft Compress compressed file	PAKLEO archive: .p11


QFC archive: .qfc	Quantum archive: .q, .pak	Quark archive: .ark	RAR archive: .rar
RPM archive: .rpm	ReSOF archive: .sof	SAR archive: .sar	SBC archive: .sbc
SQZ archive: .sqz	SZip archive	StuffIt archive: .sit	TAR archive: .tar
UFA archive: .ufa	UHArc archive: .uha	UltraCompressor 2 archive: .uc2	WRaptor archive: .wra
WinImp archive: .imp	Windows Installer Merge Module: .msm	Windows Installer Package: .msi	indows Installer Patch: .msp
Windows Installer Patch Creation File: .pcp	Windows Installer Validation Module: .cub	YAC archive: .yc	YBS archive: .ybs
ZIP archive: .zip	ZOO archive: .zoo	ZZip archive: .zz	iOS Package: .ipa
xz archive: .xz			
<b>Executable/Library/DLL</b>			
DOS Style Executable: .exe	ELF Executable (UNIX)	ELF Library (UNIX)	ELF Module (UNIX)
Java Bytecode: .class	KolibriOS Executable	NetWare Loadable Module: .nlm	Shell Script
UEFI Executable .efi	Windows DLL: .dll	Windows Executable: .exe	Windows 9x Device Driver: .vxd
Windows Device Driver: .sys	Windows OCX File: .ocx		
<b>Development files</b>			
ACUCOBOL object	Borland Delphi Compiled Unit: .dcu	Borland Turbo Pascal compiled Unit: .tpu	C/C++ Source Code: .c
COM Type Library: .tlb	GUI Design Studio project: .gui	LUA Script: .lua	Library: .lib
Microsoft .NET XML Resource template: .resx	Microsoft ClassWizard file: .clw	Microsoft Linker database .ilk	Microsoft Precompiled header: .pch
Microsoft Program database: .pdb	Microsoft Visual C++ project: .mdp	Microsoft Visual Studio Solution: .sln	Microsoft Visual Studio project: .dsp
Microsoft Visual Studio workspace: .dsw	OMF Object library: .lib	PolySpace results: .chk	RDOFF Object File: .rdf
Resource Compiler Script File: .rc	Visual Studio Solution User Options: .suo	Visual Studio Widget File: .wid	Visual Studio Workspace Options file: .opt
VisualBasic Project: .vbproj	WinDev Window: .wdw	Windows Compiled resource (32bit) : .res	XPCOM Type Library: .xpt
Xcode Project: .pbxproj			

<b>Disk images</b>			
Hyper-V virtual disk: .vhdx	JAM compressed disk: .jam	Norton Ghost disk image: .ghs	QEMU virtual disk: .qcow2
R-Drive Image disk image: .rdr	VMware virtual disk: .vmdk	Virtual PC virtual disk: .vhd	VirtualBox virtual disk: .vdi
<b>Other file types</b>			
ABBYY Lingvo dictionary: .lsd	AIX Backup File: .bff	ArtMoney Table file: .amt	CrystalMaker Data File: .cmdf, .cmmf
Dwarf Fortress save data: .dat	EasyCrypto file: .encrypted	Fallout 3 save game: .fos	Java Applet cache index: .idx
Kaspersky Anti-Virus data base: .avc	Kaspersky Anti-Virus report: .rpt	Kaspersky Anti-Virus signature bas: .kdc	Magic 3D Easy View object: .x
Microsoft Security Catalog: .cat	NHTSA UDS-1992 crash test result: .uds	NOD32 Antivirus Update file: .nup	ORTIMZeit project: .ozv
OziExplorer Map data: .map	PRO100 project: .sto	PlayStation 3 Theme: .p3t	RegEdit file: .reg
RegEdit file (UNICODE): .reg	Source Game Engine Compiled AI Nodegraph: .ain	Unreal Package	Valve Texture File: .vtf
WinHelp: .hlp	WinHelp Contents: .cnt	WinXP Prefetch file: .pfp	Windows Backup File: .bkf
Windows Clipboard file: .clp	Windows Color Profile: .icm	Windows Minidump: .dmp, .mdmp	Windows National locale: .nls
Windows Password file: .pwl	Windows Registry hive: .dat, .hiv	Windows Thumbnail cache: .db	Windows User Interface Module: .wim
Windows shortcut: .lnk	X-Plane Scenery: .dsf	XNA Game Data: .xnb	

**Note:** Using scan for Known File Types, **R-Studio** can successfully recover only un-fragmented files. You may also specify your own file types for scanning. See [Customizing File Types](#) for details. User-defined file types precede over built-in ones, if their definitions overlap. You may set the defaults for known file types on the [R-Studio Settings](#).

**R-Studio Technician/T80+**


Scan (Post Actions) dialog box



**Post Actions Options**

Shutdown the computer on task completion	If this check box is selected, <b>R-Studio</b> will shut down your computer when scan has been completed. You should select the Save to file checkbox and specify a place to save scan info to activate this option.
E-Mail notifications	If this check box is selected, <b>R-Studio</b> will inform you about the outcome of the operation via email.

> **R-Studio starts scanning the object, and its panel will show information about new found objects:**



**R-Studio Main panel**

The screenshot displays the R-Studio software interface. At the top, there is a menu bar with 'Drive', 'Create', 'Tools', 'View', and 'Help'. Below the menu is a toolbar with icons for Refresh, Show Files, Scan, Partition Search, Create Image, Open Image, Create Region, RAIDs, Connect To Remote, and Remove. The main window is titled 'R-STUDIO - Device view' and contains a 'Device view' tab. On the left, a tree view shows the 'Local Computer' with a folder for 'SAMSUNG SP0411N ...'. Below this is a table listing various partitions and files.

Device/Disk	Label	Interfa	Start	Size
Local Computer				
SAMSUNG SP0411N ...	S01J10X6144...	#0 IDE/ATA, HDD		37.31 GB
F:	Test	NTFS	1 MB	37.31 GB
Recognized2	NTFS-Test	NTFS	32 KB	6.76 GB
F: (Recognized3)	Test	NTFS	1 MB	37.31 GB
Recognized5	Ext4FS-Test	Ext4	21.63 ...	6.52 GB
Recognized6	Ext4FS-Test	Ext4	21.63 ...	37.27 GB
Recognized4	Double	NTFS	28.15 ...	9.15 GB
Raw Files				
Recognized72		HFS+	17.23 ...	122.19 ...
Recognized344		HFS+	17.27 ...	61.09 MB
Recognized199		HFS+	17.30 ...	30.55 MB
Recognized200		HFS+	17.30 ...	30.55 MB
Recognized378		HFS+	17.34 ...	47.32 MB
Recognized387		HFS+	17.34 ...	30.55 MB
Recognized388		HFS+	17.34 ...	30.55 MB
Recognized234		HFS+	17.36 ...	30.55 MB
Recognized235		HFS+	17.36 ...	30.55 MB
Recognized313		HFS+	17.36 ...	30.55 MB
Recognized374		HFS+	17.27 ...	30.55 MB

On the right side of the main window, there is a 'Scanning' status bar with a green checkmark and the text 'Drive scan completed successfully.' Below this is a large grid visualization showing the scan results. A legend at the bottom of the grid indicates the following counts:

- Unprocessed: 270
- Unused: 8938
- FAT: 154
- EXT2: 8938
- NTFS: 154
- HFS: 39
- Specific File Documents: 139155

At the bottom of the main window, there is a 'Log' window with the following entries:


Type	Date	Time	Text
System	2/23/2024	8:21:51 AM	Successfully loaded user's file types definitions from "C:\Program Files (x86)\R-Studio Technician\Presets\UserKnownFile..."
System	2/23/2024	8:21:51 AM	Successfully loaded user's RAID layouts from "C:/Program Files (x86)/R-Studio Technician/Presets/RAID6RS.xml"
System	2/23/2024	8:40:23 AM	Scan has been completed for SAMSUNG SP0411N TW100-11 in 14m 24s

The status bar at the bottom of the application shows 'Ready'.




Drives panel after scanning:  
You can select an object by clicking it

Device/Disk	Label	S/Interfac	Start	Size
Local Computer				
SAMSUNG SP0411N TW100-11	S01U10X614426	#0 IDE/ATA, HDD		37.31 GB
F:	Test	NTFS	1 MB	37.31 GB
Recognized2	NTFS-Test	NTFS	32 KB	6.76 GB
F:(Recognized3)	Test	NTFS	1 MB	37.31 GB
Recognized5	Ext4FS-Test	Ext4	21.63 GB	6.52 GB
Recognized6	Ext4FS-Test	Ext4	21.63 GB	37.27 GB
Recognized4	Double	NTFS	28.15 GB	9.15 GB
Raw Files				
Recognized72		HFS+	17.23 GB	122.19 MB
Recognized344		HFS+	17.27 GB	61.09 MB
Recognized199		HFS+	17.30 GB	30.55 MB
Recognized200		HFS+	17.30 GB	30.55 MB
Recognized378		HFS+	17.34 GB	47.32 MB
Recognized387		HFS+	17.34 GB	30.55 MB
Recognized388		HFS+	17.34 GB	30.55 MB
Recognized234		HFS+	17.36 GB	30.55 MB
Recognized235		HFS+	17.36 GB	30.55 MB
Recognized313		HFS+	17.36 GB	30.55 MB
Recognized274		HFS+	17.37 GB	30.55 MB
Recognized351		HFS+	17.37 GB	30.55 MB
Recognized326		HFS+	17.37 GB	61.09 MB
Recognized397		HFS+	17.37 GB	94.63 MB
Recognized92		HFS+	17.38 GB	122.19 MB
Recognized335		HFS+	17.40 GB	61.09 MB
Recognized47		HFS+	17.41 GB	61.09 MB
Recognized169		HFS+	17.42 GB	47.32 MB
Recognized202		HFS+	17.43 GB	61.09 MB
Recognized342		HFS+	17.43 GB	61.09 MB
Recognized346		HFS+	17.43 GB	61.09 MB
Recognized403		HFS+	17.44 GB	23.66 MB
Recognized440		HFS+	17.44 GB	30.55 MB
Recognized444		HFS+	17.44 GB	30.55 MB
Recognized80		HFS+	17.45 GB	30.55 MB
Recognized84		HFS+	17.45 GB	47.32 MB
Recognized122		HFS+	17.45 GB	30.55 MB
Recognized123		HFS+	17.45 GB	30.55 MB
Recognized125		HFS+	17.45 GB	30.55 MB
Recognized130		HFS+	17.45 GB	30.55 MB
Recognized175		HFS+	17.46 GB	15.27 MB




Type	Date	Time	Text
System	2/23/2024	8:21:51 AM	Successfully loaded user's file types definitions from "C:\Program Files (x86)\R-Studio Technician\Presets\UserKnownFile...
System	2/23/2024	8:21:51 AM	Successfully loaded user's RAID layouts from "C:\Program Files (x86)\R-Studio Technician\Presets\RAIDGRS.xml"
System	2/23/2024	8:40:23 AM	Scan has been completed for SAMSUNG SP0411N TW100-11 in 14m 24s

The Log pane will show scan progress. Scan may be stopped by clicking the **Stop** button on the toolbar. Later the scan process may be resumed with different scan parameters. Some scan parameters may also be changed during the scan process. Click the Options button and change them on the Scanning dialog box. You may change some options during the scan process




### Only in the Technician version



You may see which file object(s) is/are on a particular drive part. Click the corresponding rectangle in the Scan Information pane and view the information on the Scan Information dialog box.

### Scan Information dialog box



Double-click an object to view/edit the file object in the [Text/Hexadecimal editor](#).

When an object is scanned, a number of Recognized partitions will appear. **R-Studio** shows them in different colors depending on which elements of the partition have been found.

F:	An existing logical disk or partition
REC. F: (Recognized12)	An existing logical disk or partition after drive scan
REC. Recognized18	A recognized partition. Both boot records and file entries are found for this partition
REC. Recognized22	A recognized partition. Only file entries are found for this partition
REC. Recognized16	A recognized partition. Only boot records are found for this partition
REC. Recognized8	A fast found partition

Empty Space21	Empty space on the object
DeletedPart1	A deleted partition
Raw Files	Files that have been found using <a href="#">scan for known file types</a> (raw file search).

Although such recognized partitions are virtual objects, files can be searched for and recovered from recognized partitions as from real [logical disks](#) using [Basic File Recovery](#).

To see the information about a newly found object, simply click it in the Drives panel. Click this link to see the information about the object Recognized13 on the logical disk H:

Name	Value
Drive Type	Partition
Name	Recognized13
Size	27.54 GB (57760039 Sectors)
Partition Offset	9.77 GB (20482937 Sectors)
Partition Size	27.54 GB (57760039 Sectors)
<b>Recognized FS</b>	
Parsed Boot Records	1
Parsed Directory Entries	96
Estimated Files Count	4104
Estimated Size	27.51 GB (57689352 Sectors)
<b>NTFS Information</b>	
Cluster Size	4 KB (8 Sectors)
MFT Record Size	1 KB
MFT Position	3 GB (6291456 Sectors)
MFT Mirror Position	13.75 GB (28844672 Sectors)

When an object in a scanned drive is selected, **R-Studio** shows the scanned area of the object.

Object's scanned area

The screenshot displays the R-Studio interface. On the left, the 'Device view' pane shows a list of scanned objects on a SAMSUNG SP04... drive. The selected object is 'Recognized6', which is an Ext4FS-Test partition of 21.63 GB. The main window shows a grid representing the scanned area of this object, with various colors indicating different file types and their locations. A legend at the bottom right of the grid identifies the colors: Unprocessed (grey), NTFS (red), Specific File Documents (blue), EXT2 (green), FAT\_270 (purple), and HFS\_39 (orange). The log pane at the bottom shows system messages related to the scan completion.


All scanned information may be deleted on the shortcut menu for a scanned object.

Scan information may be saved in a file. Previously saved scan information may be loaded. This can be done on the **Drive** or shortcut menu for a selected object.

### **Resuming incomplete scans or scanning the object with different parameters**

You may resume the scan of an incompletely scanned object or rescan the already scanned object with different parameters. The Scan dialog will be a little bit different in this case.

## Scan dialog box for incomplete scans




You may rescan the entire drive, scan unscanned areas, or scan an explicitly specified area.

### Scan of multiple areas

You may simultaneously scan several successive or overlapping areas. Click the **Advanced** button, specify an offset and size for a new area to scan on the Advanced Scan dialog box and click the **Add** button. You may specify and add several scan areas. You may select which areas should be scanned. Selected scan areas can be merged. Right-click a necessary area and select either **Merge Down**, **Merge Down All**, and **Merge Selected**. You may also select/unselect unscanned areas.

### Advanced Scan dialog box



**R-Studio** accumulates the information from successive scans and keeps track of changes in this information obtained from different scans.

You may manage the areas

### Managing scan information

Scan information may be saved to a file. Previously saved scan information may be loaded.

#### To save scan information

- 1 Select an object in the **R-Studio Drives panel**
- 2 Select **Save Scan Information** on the **Drive** or **shortcut menu** and save the scan information in a file  
The default file extension is \*.scn.


If a remote computer is connected for [Data Recovery over Network](#), the Save Scan Information File dialog box will appear when you select a place to store scan info. You may save it to the local or remote computer.

### To load scan information

- 1 Select an object in the R-Studio Drives panel
- 2 Select Open Scan Information on the Drive or shortcut menu and select the required file with the scan information

The default file extension is \*.scn.

If a remote computer is connected for [Data Recovery over Network](#), the Open Scan Information File dialog box will appear when you select a place to load scan info from. You may load it from the local or remote computer.



- > The scan information will appear in the Drives panel

### To remove scan information

- 1 Select an object in the R-Studio Drives panel
- 2 Select Remove Scan Information on the Drive or shortcut menu

- > The scan information will disappear from the Drives panel

**NEVER TRY TO SAVE SCAN INFORMATION ON THE OBJECT BEING SCANNED!!!**  
Or you may obtain unpredictable results and lose all your data.

## 2.2.2 Fast Search for Lost Partitions

[Drive scan](#) gives very detailed and accurate results but takes long time. If you want to find only [partitions](#) previously existed on the drive you may use fast search for lost partitions which is much faster.

### To perform fast search for lost partitions,

- 1 Select an object in the R-Studio's Drives panel

#### Fast search for lost partitions

Device/Disk	Label	Interface	Start	Size
KINGSTON SA400S37120G 0...	50026B77843A5...	#0 SATA2_SSD	111.79 GB	
EFI system partition	FAT32	1 MB	100 MB	
Microsoft reserved parti...			101 MB	16 MB
C:	System	NTFS	117 MB	111.18 GB
Windows Recovery Partit...	NTFS		111.29 GB	508 MB
TOSHIBA DT01ACA100 MS2...	44H5ATLKS	#1 SATA2_HDD	931.51 GB	
D:	Data	NTFS	1 MB	931.51 GB
WDC WD3200BEVT-08A23T...	WD-WXCIAB01...	#2 SATA2_HDD	298.09 GB	
Volume1	ext4fs	Ext4	992.50 KB	37.25 GB
Volume2	xfs	XFS	37.25 GB	37.25 GB
Volume3	exFAT	exFAT	74.51 GB	37.25 GB
Volume4	NTFS	NTFS	111.76 GB	44.70 GB
Volume5	FAT32	FAT32	156.46 GB	11.72 GB
Volume6	NTFS	NTFS	168.18 GB	129.91 GB


Name	Value
Drive Type	Physical Drive/Disk
Name	WDC WD3200BEVT-08A23T1 02.01A02
OS Object	\\.\PhysicalDrive2
R-Studio Driver	WinNT\HandlePhysical
Size	298.09 GB (625142448 Sectors)
Logical Sector Size	512 Bytes
Physical Sector Size	512 Bytes
Partition Size	298.09 GB (625142448 Sectors)
I/O Retries	Default
Drive Control	
Maximum Transfer	128 KB
I/O Block Size	512 Bytes
Buffer Alignment	4 Bytes
Physical Drive Geometry	
Cylinders	38913
Tracks Per Cylinder	255

Type	Date	Time	Text
System	2/26/2024	12:11:59 PM	Successfully loaded user's file types definitions from "C:\Program Files (x86)\R-Studio Technician\Presets\UserKnownFile...
System	2/26/2024	12:11:59 PM	Successfully loaded user's RAID layouts from "C:\Program Files (x86)\R-Studio Technician\Presets\RAID6RS.xml"

## 2 Click the Partition Search button


**R-Studio** will start searching for lost partitions showing its progress.

### Fast search for lost partitions



> **R-Studio** will show fast-found partitions in blue.

### Fast search for lost partitions



You may right-click the partition and select **Complete scan** to scan the entire drive.

## 2.2.3 Customizing File Types

You may create your own [known file types](#) and add their file signatures for scanning in Known File Types. They will appear in their respective folders on the [File Types](#) dialog box.

You can do that either by using the **R-Studio's** graphic interface or by direct editing the known file description file specified on the **R-Studio** [Main](#) settings dialog box.

### Creating a Known File Types using a Graphic User's Interface

The easiest way to add your own is to use the **R-Studio's** graphic interface.




## To create a Known File Type,

1 On the [Known File Types](#) settings dialog box, click the **Edit User's File Types...** button


> The **Edit User's File Types** dialog box will appear

### Edit User's File Types dialog box



2 Click the **Create File Types** button and specify **File type properties**

### Edit User's File Types dialog box




### File Types properties

id	digit	Required	Digital file type identifier. Should be unique for each custom file type.
group	string	Optional	Specifies a file type group in which found files will appear. You may specify either your own groups or select those predefined on the <a href="#">File Types</a> dialog box.
description	string	Optional	Brief file description
features	NO_SCAN TXT_ANSI TXT_UNICODE	Optional	<p>Additional properties of the file type. If you want to specify several properties, they should be separated by a space.</p> <p>NO_SCAN: Not to be scanned for. If this flag is used, <b>R-Studio</b> will not search for such file type. Such files will be shown when sorting files by their extensions.</p> <p>TXT_ANSI: The file can be viewed as ANSI text. If this flag is specified, the file can be correctly represented as an ANSI text. When previewing, this file will be immediately sent to <b>Text!/? hexadecimal editor</b>.</p> <p>TXT_UNICODE: The file can be viewed as UNICODE text. If this flag is specified, the file can be correctly represented as a UNICODE</p>

			text. When previewing, this file will be immediately sent to <b>Text/? hexadecimal editor</b> .
extension	<string>	Optional	File extension.

### 3 Click the **Add Signature** button, specify the signature parameters, and click the **Save** button

#### Edit User's File Types dialog box




#### File signature properties

Begin	Specifies from where the signature begins.
End	If End, the offset is from the end of file to the first byte of the signature. That is, if the signature is two bytes long, the offset value should be 2.
AND	Shows the order of the logical operation (union or intersection)
OR	
From	A decimal number specifying the leftmost possible offset for the file signature.
To	A decimal number specifying the rightmost possible offset for the file signature.

You may specify as many signatures as you need. Moreover, you may specify subgroups within a signature using the **Add Subgroup** button. The structure of such possible subgroups is described on the [Customizing File Types-II](#) help page.

### > The newly specified file type will appear on the Edit User's File Types dialog box and the [File Types](#) dialog box

#### Edit User's File Types dialog box



## 2.2.4 Customizing File Types-I

The syntax of signature description is similar to that of the XML language. They are stored in the file specified on the **R-Studio Main** settings dialog box.

More advanced features are described in [Customizing File Types-II](#).



**Signature file example**

```
<?xml version="1.0" encoding="utf-8"?>
  <FileTypeList>
    <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
      <Signature offset="3" count="1">Abc\x5c\x00\x04</Signature>
      <Signature offset="9" count="2">\x23\x01\xf4</Signature>
    </FileType>
  </FileTypeList>
```

**File structure****File header**

The file starts with a standard XML header

```
<?xml version="1.0" encoding="utf-8"?>
```

**Section** FileTypeList

```
<FileTypeList>
```

It requires a closing element `</FileTypeList>`.

**Section** FileType

This is a description of each file signature.

**Attributes:**

id	<u32>	Required	Digital file type identifier. Should be unique for each file type.	
group	<string>	Optional	Specifies a file type group in which found files will appear. You may specify either your own groups or those predefined on the <a href="#">File Types</a> dialog box.	Default: unknown
description	<string>	Optional	Brief file description	Default: null (no description)
features	NO_SCAN TXT_ANSI TXT_UNICODE	Optional	Additional properties of the file type. If you want to specify several properties, they should be separated by a space.	Default: 0
extension	<string>	Optional	File extension.	Default: null (no extension)

**File type properties flags**

NO_SCAN	Not to be scanned for. If this flag is used, <b>R-Studio</b> will not search for such file type. Such files will be shown when sorting files by their extensions.
TXT_ANSI	The file can viewed as ANSI text. If this flag is specified, the file can be correctly represented as an ANSI text. When previewing, this file will be immediately sent to <a href="#">Text/?hexadecimal editor</a> .
TXT_UNICODE	File can viewed as UNICODE text. If this flag is specified, the file can be correctly represented as a UNICODE text. When previewing, this file will be immediately sent to <a href="#">Text/hexadecimal editor</a> .

This section can contain an unlimited number of the `Signature` elements. If there are several `Signature` elements, that means that all those signatures are simultaneously present in the file. Such signatures should have different `offset` attributes and they should not overlap.

**Element** `Signature`

The element contains a string value of the file signature consisting of ASCII characters and hex bytes in the `\xhh` format, where `hh` is a hexadecimal byte code. If there is not a hexadecimal number after `\x`, `\x` are treated as a part of the string section of the signature

**Attributes:**

<code>offset</code>	<u16>	Optional	Decimal offset for the signature	Default: 0
<code>count</code>	<u16>	Optional	Decimal number specifying the number of signatures of the same length. Used when several signatures of the same length starting with the same offset can be present in a file. In this case they should be sequentially written in the element, and the <code>size</code> attribute specifies the length of signature. <code>count*size</code> should be equal to the number of bytes in the element. If only one signature can be on this offset, <code>count</code> should be equal "1", and <code>size</code> should be equal to the length (the number of bytes) of the signature.	Default: 1
<code>size</code>	<u16>	Optional	Decimal number specifying the number of bytes in the signature.	Default: the number of bytes written in the element.
<code>from</code>	<code>begin</code> <code>end</code>	Optional	Specifies from where the <code>offset</code> is calculated. If <code>end</code> , the <code>offset</code> is from the end of file to the first byte of the signature. That is, if the signature is	Default: <code>begin</code>

			two bytes long, the offset value should be 2.	
--	--	--	---	--

### Comments

```
<!-- Comment string -->
```

An XML standard string for a comment.

## 2.2.5 Customizing File Types-II

Currently **R-Studio** supports two versions of file type descriptions. Version 2 extends legacy Version 1 by adding variable signature offsets and AND/OR combination of several signatures in one file type. The version of file type description is specified by the version attribute of the `FileTypeList` section. Version 1 is the default option.

### File structure

#### Elements common to Versions 1 and 2 of file type description

#### File header

The file starts with a standard XML header

```
<?xml version="1.0" encoding="utf-8"?>
```

#### Section `FileTypeList`

```
<FileTypeList>
```

#### Attributes:

version	1.0 2.0	Optional	Version of file type description	Default: 1.0
---------	------------	----------	----------------------------------	--------------

It requires a closing element `</FileTypeList>`.

### Comments

```
<!-- Comment string -->
```

An XML-standard string for a comment.

### Version 1 of file type description

#### Signature file example

```
<FileTypeList>
  <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
    <Signature offset="3" count="1">Abc\x5c\x00\x04</Signature>
    <Signature offset="9" count="2">\x23\x01\xF4</Signature>
  </FileType>
</FileTypeList>
```

#### Section `FileType`

This is a description of each file signature.

#### Attributes:

id	<u32>	Required	Digital file type identifier. Should be unique for each file type.	
group	<string>	Optional	Specifies a file type group in which found files will appear. You may specify	Default: unknown

			either your own groups or those predefined on the <a href="#">File Types</a> dialog box. See the table below.	
description	<string>	Optional	Brief file description	Default: null (no description)
features	NO_SCAN TXT_ANSI TXT_UNICODE	Optional	Additional properties of the file type. If you want to specify several properties, they should be separated by a space.	Default: 0
extension	<string>	Optional	File extension.	Default: null (no extension)

#### ***File type properties flags***

NO_SCAN	Not to be scanned for. If this flag is used, <b>R-Studio</b> will not search for such file type. Such files will be shown when sorting files by their extensions.
TXT_ANSI	The file can be viewed as ANSI text. If this flag is specified, the file can be correctly represented as an ANSI text. When previewing, this file will be immediately sent to <b>Text/Hexadecimal editor</b> .
TXT_UNICODE	The file can be viewed as UNICODE text. If this flag is specified, the file can be correctly represented as a UNICODE text. When previewing, this file will be immediately sent to <b>Text/Hexadecimal editor</b> .

#### ***List of predefined file type groups***

Group	Name on the File Types dialog box.
archive	Archive Files
graphics	Graphics/Picture
internet	Internet-related files
multimedia	Multimedia Files
audio	Multimedia: Audio Files
video	Multimedia: Video Files
font	Font
document	Document
doc_database	Document: Database
doc_sheet	Document: Spreadsheet
exe	Executable/Library/DLL
unknown	Other file types

This section can contain an unlimited number of the `Signature` elements. If there are several `Signature` elements, that means that all those signatures are simultaneously present in the file. Such signatures should have different offset attributes and they should not overlap.

#### **Element** `Signature`

The element contains a string value of the file signature consisting of ASCII characters and hex bytes in the `\xhh` format, where `hh` is a hexadecimal byte code. If that is not a hexadecimal number after `\x`, `\x` are treated as a part of the string section of the signature

**Attributes:**

offset	<ul6>	Optional	Decimal offset for the signature	Default: 0
count	<ul6>	Optional	Decimal number specifying the number of signatures of the same length. Used when several signatures of the same length starting with the same offset can be present in a file. In this case they should be sequentially written in the element, and the <code>size</code> attribute specifies the length of signature. <code>count*size</code> should be equal to the number of bytes in the element. If only one signature can be on this offset, count should be equal to "1", and size should be equal to the length (the number of bytes) of the signature.	Default: 1
size	<ul6>	Optional	Decimal number specifying the number of bytes in the signature.	Default: the number of bytes written in the element.
from	begin end	Optional	Specifies from where the offset is calculated. If end, the offset is from the end of file to the first byte of the signature. That is, if the signature is two bytes long, the offset value should be 2.	Default: begin

**Version 2 of file type description****Signature file example**

```
<?xml version="1.0" encoding="utf-8"?>
<FileTypeList version="2.0">
  <FileType id="5626" group="_Test" description="Test file" extension="tst">
    <Begin combine="and">
      <Signature from="0" to="20">ABC</Signature>
      <Signature offset="1">CDEFG</Signature>
      <AND>
        <Signature offset="0">DE</Signature>
        <Signature offset="0">RTD</Signature>
      <OR>
        <Signature offset="12">CP</Signature>
        <Signature offset="16">RTD</Signature>
      </OR>
    </AND>
  </Begin>
  <End combine="or">
    <Signature from="3" to="20">ABC</Signature>
    <Signature offset="5">CDEFG</Signature>
    <AND>
      <Signature offset="2">DE</Signature>
      <Signature offset="3">RTD</Signature>
    <OR>
```

```

        <Signature offset="12">CP</Signature>
        <Signature offset="16">RTD</Signature>
    </OR>
</AND>
</End>
</FileType>
</FileTypeList>

```

### Section FileType

This is a description of each file signature.

#### Attributes:

Similar to those in Version 1.

The section can contain one element `Begin` and one `End`. It should contain at least one of them.

#### Example

```

<FileTypeList version="2.0">
  <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
    <Begin [attributes]>
      ...
    </Begin>
    <End [attributes]>
      ...
    </End>
  </FileType>
</FileTypeList>

```

### Sections Begin and End

Specify the positions of file type signatures in the file.

#### Attributes

combine	and or	Optional	Shows the order of the logical operation (union or intersection)	Default: and
---------	-----------	----------	--	--------------

These sections can contain one of several elements `Signature`. And one or several elements `OR` or `AND`. If there are several elements inside the section they are combined according to the attribute `combine`.

#### Example:

```

<FileTypeList version="2.0">
  <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
    <Begin combine="or">
      <Signature [attributes]> ... </Signature>
      ...
      <Signature [attributes]> ... </Signature>
    </Begin>
    <AND>
      ...
    </AND>
    <OR>
      ...
    </OR>
  </FileType>
</FileTypeList>

```

```

    <Signature [attributes]> ... </Signature>
    ...
    <Signature [attributes]> ... </Signature>
  </End>
</FileType>
</FileTypeList>

```

### Sections AND and OR

These sections can contain one of several elements `Signature`. And one or several elements `OR` or `AND`. If there are several elements inside the section they are combined according to the section type (logical `AND` or `OR`).

#### Example:

```

<FileTypeList version="2.0">
  <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
    <Begin>
      <Signature [attributes]> ... </Signature>
      ...
      <Signature [attributes]> ... </Signature>
      <AND>
        <Signature [attributes]> ... </Signature>
        <OR>
          <Signature [attributes]> ... </Signature>
        <AND>
          <Signature [attributes]> ... </Signature>
          <Signature [attributes]> ... </Signature>
        </AND>
        <OR>
          <Signature [attributes]> ... </Signature>
          <Signature [attributes]> ... </Signature>
        </OR>
      </OR>
      <Signature [attributes]> ... </Signature>
    </AND>
  </Begin>
</FileType>
</FileTypeList>

```

### Element `Signature`

The element contains a string value of the file signature consisting of ASCII characters and hex bytes in the `\xhh` format, where `hh` is a hexadecimal byte code. If that is not a hexadecimal number after `\x`, `\x` are treated as a part of the string section of the signature

#### Attributes:

Attribute	Value	Optional	Description	Default
<code>offset</code>	<code>&lt;u16&gt;</code>	Optional	Decimal offset for the signature	Default: 0
<code>from</code>	<code>&lt;u16&gt;</code>	Optional	Decimal number specifying the leftmost possible offset for the file signature. Ignored if the <code>offset</code> attribute is specified.	Default: undefined
<code>to</code>	<code>&lt;u16&gt;</code>	Optional	Decimal number specifying the rightmost possible offset for the file signature.	Default: undefined

			Ignored if the <code>offset</code> attribute is specified.	
<code>size</code>	<code>&lt;u16&gt;</code>	Optional	Decimal number specifying the number of bytes in the signature.	Default: the number of bytes written in the element.

**Example:**

```
<FileTypeList version="2.0">
  <FileType id="2" group="archive" description="ARJ Archive" extension="arj">
    <Begin>
      <Signature offset="3">Abc\x5c\x00\x04</Signature>
      <Signature from="9" to="15">\x23\x01\xf4</Signature>
    </Begin>
  </FileType>
</FileTypeList>
```

**2.2.6 Regions**

Scanning large objects may take a long time. Sometimes, only a smaller area of a drive needs to be scanned or searched for files. Such area is called a *region*. A [region](#) can be created on any object in the **R-Studio's** Drives panel.

Created regions can be scanned, and files on them can be recovered in the same way as from drives or [logical disks](#).

Created regions can be deleted or their size can be changed.

**Note:** **R-Studio** does not create anything real on the drive. Regions are virtual objects that do not affect actual data on the drive.

**To create a region****1 Select an object in the R-Studio's Drives panel and click the Create Region button****Other ways to create the region**

- Right-click the selected object and select **Create Region** on the shortcut menu
- or
- Select the object and select **Create Region** on the **Create** menu
- or
- Select the object and press the **F4** key on the keyboard

Device/Disk	Label	/Interfa	Start	Size
Local Computer				
> KINGSTON SA400S37120...	50026877843A...	#0 SATA2_SSD		111.79 GB
> TOSHIBA DT01ACA100 M...	44H5ATLKS	#1 SATA2_HDD		931.51 GB
▼ Hitachi HT5545016B95A0...	100713PBPB08...	#2 SATA2_HDD		149.05 GB
I:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
G:	FAT-TEST	FAT16	54.96 GB	2.01 GB
E:	EXFAT	FAT32	56.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
Reformatted1	NTFS	0 Bytes		33.86 GB

**2 Specify required parameters on the Create region dialog box and click the Create button****Create region dialog box**



### Region options

Drive size:	Shows size of the object where the region is to be created. The region cannot be larger than this size.
Start:	Start point of the region
Size:	Size of the region. Cannot be larger than Drive size.
Numbers in these fields can be in bytes or sectors. See the <a href="#">Data Formats and Multipliers</a> topic for more details on data formats.	

- > **A Region object will appear in the Drives panel.**

Device/Disk	Label	/Interfa	Start	Size
Local Computer				
KINGSTON SA400S37120...	50026B77843A...	#0 SATA2_SSD		111.79 GB
TOSHIBA DT01ACA100 M...	44H5ATLKS	#1 SATA2_HDD		931.51 GB
Hitachi HT545016B95...	100713PBPB...	#2 SATA2_HDD		149.05 GB
Region 0 on Hitachi...			0 Bytes	30 GB
DeletedPart1	NTFS-Test	NTFS	512 KB	28.69 GB
Partition1	NTFS-Test	NTFS	512 KB	28.69 GB
Partition2	FAT32-TEST	FAT32	28.69 GB	26.27 GB
I:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
G:	FAT-TEST	FAT16	54.96 GB	2.01 GB
E:	EXFAT	EXFAT	56.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
Reformatted1	NTFS		0 Bytes	33.86 GB

### To change the size of a region

- \* Right-click the Region in the R-Studio Drives panel, select Edit on the shortcut menu, and enter a new size on the Edit Region dialog box.

### To convert a region into an exclusive one

- \* Right-click the Region in the R-Studio Drives panel and select Exclude area on the shortcut menu

### To remove a region

- \* Select a Region in the R-Studio Drives panel and click the Remove button, or Right-click the selected region and select Remove Region on the shortcut menu.

## 2.2.7 Exclusive Regions

Exclusive regions are areas on any object visible in the **R-Studio's** Drives panel that are excluded from drive operations. **R-Studio** never tries to read/write data from/to such area. Exclusive regions are necessary when, for example, there are areas with [bad sectors](#) on a drive, and it is necessary to avoid any drive operations with such areas to not inflict further damage to such drive and to speed work with it.


**Note:** **R-Studio** does not create anything real on the drive. Exclusive regions are virtual objects that do not affect actual data on the drive.

### To create an exclusive region

- 1 Right-click an object in the **R-Studio's** Drives panel and select Create Exclusive Region on the shortcut menu, or  
Select the object and select **Create Exclusive Region** on the **Create** menu

## 2 Specify required parameters on the Create Exclusive Region dialog box and click the Add button

### Create exclusive region dialog box



### Exclusive Region options


Start:	Start point of the entire exclusive region
Size:	Size of the entire exclusive region. Cannot be larger than Drive size.
Offset:	Offset of the excluded area.
Size:	Size of the excluded area.

Numbers in these fields can be in bytes or sectors. See the [Data Formats and Multipliers](#) topic for more details on data formats.

### > An Exclusive Region object will appear in the Drives panel.

Device/Disk	Label	/Interfa	Start	Size
Microsoft reserved ...			101 MB	16 MB
C:	System	NTFS	117 MB	111.18 GB
Windows Recovery ...		NTFS	111.29 GB	508 MB
TOSHIBA DT01ACA100 ...	44H5ATLKS	#1 SATA2_HDD		931.51 GB
D:	Data	NTFS	1 MB	931.51 GB
Hitachi HTSS45016B9... (selected)	100713PBPB...	#2 SATA2_HDD		149.05 ...
Exclusive region 0 o...		NTFS	0 Bytes	149.05 GB
Partition1	NTFS-Test	NTFS	512 KB	28.69 GB
Partition2			28.69 GB	26.27 GB
Partition3	FAT-TEST	FAT16	54.96 GB	2.01 GB
Partition4	EXFAT	FAT32	56.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
H:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB

Its properties can be seen on the Excluded Areas tab.



### To remove an exclusive region

- \* Select an Exclusive Region in the R-Studio Drives panel and click the Remove button, or Right-click the selected region and select Remove Region on the shortcut menu.

### To change the size of an exclusive region

- \* Right-click an Exclusive Region in the R-Studio Drives panel, select Edit on the shortcut menu, and add/remove excluded areas on the Edit Exclusive Region dialog box.  
You may remove an excluded area by right-clicking it and selecting Remove on the shortcut menu.

## 2.2.8 Images

An *image* is an exact, byte by byte, copy of any object in the Drives panel. When created, images can be processed like their original objects.

Images are very useful if there is a risk of total data loss due to hardware malfunction. If bad blocks are constantly appearing on a drive, you must immediately create an image of this drive. All data search, scan and restoring can be done from this image.

While creating images, **R-Studio** can simultaneously perform drive scan and save scan information to lessen time necessary to process the drive.

The image can be saved on the remote computer if it is created [via network](#). **R-Studio** can also load and process images created with the **DeepSpar Disk Imager**<sup>TM</sup>.

An imaging process can be stopped and then resumed later on.

**R-Studio Corporate** version and higher can create images directly on hard drives making in fact disk clones.

### To create an *image*,

- 1 Select an object in the **R-Studio's** Drives panel and click the **Create Image** button

#### **Other ways to create the image**

- Select the object and select **Create Image** on the **Drive** menu


OR

- Right-click the selected object and select **Create Image File** on the shortcut menu


- 2 Specify image options, a file name, and destination for the *image* on the Create Image dialog box

**Note:** To store an image file, you need a [free space](#) equal to at least the object size.


#### Create Image (Main) dialog box



## Create Image (Bad sector processing) dialog box



## Create Image (Scan Information) dialog box




## Image Options

Image filename	Specifies the name and path for the image file
Image type:	<p>Compressed image (R-Drive Image compatible): If this option is selected, <b>R-Studio</b> will create an image file which can be compressed, split into several parts, and password-protected. This image file is fully compatible with the images created by <b>R-Drive Image</b>, but incompatible with very old versions of <b>R-Studio</b>.</p> <p>Byte by byte image to a file: If this option is selected, <b>R-Studio</b> will create a simple exact copy of the object.</p> <p>Byte to byte image to a physical disk: <b>R-Studio</b> will create an exact copy of the disk on another hard drive. Data on the target drive will be overwritten. Available in the Corporate, Technician, and T80+ licenses.</p> <p>Some other image formats are also available in the Technician, and T80+ licenses. You may read more about these formats in the <a href="#">Supported Virtual Disk and Disk Image Formats</a> page.</p>
Image compression ratio	You may <a href="#">compress</a> the data in the image to save space. Active only if the Compressed image (R-Drive Image compatible) is selected.
Estimated size	Shows the estimated size of the image file. An actual image size depends on how much empty space is on the selected <a href="#">partition</a> and what file types are there. Active only if the Compressed image (R-Drive Image compatible) is selected.

Image split size	You may set this option to Automatic and let Windows decide how to split the image file. This mostly depends on the file system on the destination drive. You may also either explicitly specify the split size, or choose a preset for various devices with removable storage. Select Fixed size for that. Active only if the Compressed image (R-Drive Image compatible) is selected.
Password Encrypt image	You may protect your image file with a password. <b>Note:</b> If you leave the Encrypt image option clear this feature will provide a relatively moderate protection against conventional unauthorized access. If this option is selected, <b>R-Studio</b> will encrypt the image using the <a href="#">AES-XTS</a> algorithm. <b>Note:</b> Only files in the RDR format can be password protected and encrypted.
Create scan information file	If this option is selected, <b>R-Studio</b> will perform drive scan simultaneously with image creation. See the <a href="#">Drive Scan</a> help page to learn scan options.
Read retries	Specifies a value for I/O Tries, or how many times <b>R-Studio</b> will try to read a <a href="#">bad sector</a> . <b>R-Studio</b> treats bad sectors in the following way: It reads a certain part of drive (predefined by Windows) and <ul style="list-style-type: none"> <li>• If Default read attempts is set to 0, the entire part with bad sectors will be filled with the specified pattern.</li> <li>• If Default read attempts is set to a non-zero value, <b>R-Studio</b> reads again that part sector by sector, repeating the attempts the specified number of times. If <b>R-Studio</b> still cannot read a bad sector, it fills the sectors with the specified pattern. In this case only the bad sectors will be filled with the pattern, but that extremely slows the drive read process.</li> </ul> For example, if you set Default read retries to 1, a bad sector will be read 2 times.
Pattern to fill bad blocks	Specifies a pattern <b>R-Studio</b> will use to fill bad sectors in this image. You may specify the pattern either in the ANSI or Hex data format. <b>Note:</b> <b>R-Studio</b> will never ever try to write anything on the drive from which data is to recover or an image is to create. This pattern fills bad sectors only in the image.
<a href="#">Drive sector map file</a> Enable multi-pass image creation	These options are available only in the <b>Technician/T80+</b> versions. Read more about these options in the <a href="#">I/O Monitor and Sector Map files</a> and <a href="#">Multi-pass imaging</a> help page.


If a remote computer is connected for [Data Recovery over Network](#), the Create Image dialog box will have a different look. You may save the image to the local or remote computer.



### R-Studio Technician/T80+

These options are available only in the **Technician/T80+** versions.

### Create Image (Additional output folders) dialog box




#### Additional output folders

Additional output folders

Additional output folders where image files will be stored when **R-Studio** runs out of space.

### Create Image (Post Actions) dialog box



#### Post Actions Options

Shutdown the computer on all tasks completion

If this check box is selected, **R-Studio** will shut down your computer when all task, including this image creation have been completed.


E-Mail notifications

If this check box is selected, **R-Studio** will inform you about the outcome of the operation via email.

> **R-Studio** will start creating the image, the Progress message showing the progress.


You may change some options during the imaging process. Click the **Options** button and change them as necessary/

You may stop the imaging process and then resume it later on. Click the **Stop** button and the Cancel drive operation dialog box will appear. Select **Stop** if you want to keep the partially created image or **Discard** if you don't need this image file.



To resume the creation of the image for the same object, select the same file name for the image. You'll be able to create a new image file or continue to create the image for the object.

### Resuming image creation



**R-Studio** will create a new file for every new start of imaging for the `.rdi` and `.vmdk` file types.


To process an already created *Image*, the image file should be opened.

### To open an image

1 Click the **Open Image** button, or

Select **Open Image File** on the **Drive** menu


If a remote computer is connected for [Data Recovery over Network](#), the Open Image File dialog box will appear when you select a place to load the image file from. You may load it from the local or remote computer.



## 2 Select the required image file

If the image is a multi-volume one, and not all parts are at the same place, the dialog box will appear

### Multi-volume image dialog box



Specify paths to other image parts and click the OK button.

### > An *Image* object will appear in the Drives panel

Depending whether this is a byte-by-byte, compressed (**R-Drive Image compatible**), multi-volume, or VMDK image, its appearance in the Drives panels is different.

You may perform all data search, scan, and recovery from this image as it were a regular drive/disk object.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2...	0 Bytes	931.51 GB
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASIO409502	#1 SATA2...	0 Bytes	931.51 GB
Image				
QUANTUM FIREBALL CR8.4A ASU.1200	828907412585	#0 ATA (...)	0 Bytes	7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Partition3	FAT-TEST	FAT16	5.87 GB	2.01 GB

A compressed (R-Drive Image compatible) image

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2...	0 Bytes	931.51 GB
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASIO409502	#1 SATA2...	0 Bytes	931.51 GB
Image Files				
X:\Images\QUANTUM FIREBALL CR...				7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Partition3	FAT-TEST	FAT16	5.87 GB	2.01 GB

A byte by byte image

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2...	0 Bytes	931.51 GB
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASIO409502	#1 SATA2...	0 Bytes	931.51 GB
Image				
12/12/2021 11:33:49 - Incomplete				
QUANTUM FIREBALL CR8.4A ASU...	828907412585	#0 ATA (...)	0 Bytes	7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Empty Space37			5.87 GB	2.01 GB
12/13/2021 13:28:59 - Incomplete				
QUANTUM FIREBALL CR8.4A ASU...	828907412585	#0 ATA (...)	0 Bytes	7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Empty Space40			5.87 GB	2.01 GB
12/13/2021 13:31:28				
QUANTUM FIREBALL CR8.4A ASU...	828907412585	#0 ATA (...)	0 Bytes	7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Partition3	FAT-TEST	FAT16	5.87 GB	2.01 GB

A multi-volume image


Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2...	0 Bytes	931.51 GB
ST1000DM003-1CH162 CC44	51DC12W0	#1 SATA2...	0 Bytes	931.51 GB
E:	Images	NTFS	1 MB	931.51 GB
Image				
QUANTUM FIREBALL CR8.4A ASU.1200	828907412585	Local	0 Bytes	7.87 GB
Partition1	NTFS-Test	NTFS	32 KB	2.93 GB
Partition2	FAT32-TEST	FAT32	2.93 GB	2.94 GB
Partition3	FAT-TEST	FAT16	5.87 GB	2.01 GB

A VMDK image

## To close an image

- \* Select the image and click the **Close Image** button,
  - or right-click the image and select **Close Image** on the shortcut menu
  - or select the image and press the **F8** key.






## To close all image

- \* **Select Close All Images on the Tools menu**

A [logical disk](#) (or disks) containing in an image can be mounted in the operating system as a device which makes its content accessible to any program including any other data recovery software.

## To mount a logical disk in an image


- 1 **Right-click the logical disk in the image in the Drives panel and select Mount on the shortcut menu**




- 2 **Select a disk letter to assign to the mounted logical disk and click OK**



- > **A Virtual disk object will appear in the Drives panel**



and this virtual disk will be available to system in the read-only mode



## To unmount a virtual disk from the system

- 1 **Right-click the virtual disk in the image in the Drives panel and select Unmount on the shortcut menu**

## 2.2.9 Wiping Objects

Disk objects can be [wiped](#) in order to completely destroy its data.

### Supported Wipe Algorithms

File wiping is necessary only for files stored on conventional hard drives. Files stored on new [SSD storage devices](#) cannot be effectively wiped out due to the principles of operation of these devices.

Currently **R-Studio** supports 6 wiping algorithms:

<b>Zeroes</b>	The disk object or file is filled with zeroes through 1 pass. The fastest but the least secure algorithm. Also it does not conceal the fact that the disk or file has been wiped.
<b>Pseudo-random numbers</b>	The disk object or file is filled with pseudo-random numbers through 1 pass. A slower but little bit more secure algorithm than the <b>Zeroes</b> algorithm and it also conceals to some degree the fact that the disk or file has been wiped.
<b>DoD 5220.22-M(3)</b>	The disk object or file is wiped using Department of Defense standard 5220.22-M(3). Provides high-grade data wiping filling the unused space or file with a special digital pattern through 3 passes This algorithm is very secure, but slow.
<b>DoD 5200.28-STD(7)</b>	The disk object or file is wiped using Department of Defense standard 5200.28-STD(7). Provides high-grade data wiping filling the unused space or file with a special digital pattern through 7 passes. This algorithm is very secure, but very slow.
<b>Bruce Schneier(7)</b>	The disk object or file is wiped using the Bruce Schneier(7) algorithm. The first pass overwrites the drive with the bit pattern "00", the second with "11", and the next five with a randomly generated bit pattern. This algorithm is very secure, but very slow.
<b>Peter Gutmann (35)</b>	The disk object or file is wiped using the Peter Gutmann's algorithm. Provides high-grade data wiping filling the unused space or file with a special digital pattern through 35 passes. This algorithm is military-level secure, but horribly slow.

What algorithm is to choose, depends on your specific needs. All of these wiping algorithms make recovery of wiped data with any software-based data recover utility impossible. So if you want to protect your information from a casual snooper, you may safely choose either the **Zeroes** or **Pseudo-random numbers** algorithm. The latter also conceals the fact that you wiped the data.

**If you want more security**, you need to know the following:

There are some techniques for recovery of wiped data. These techniques are based on the fact that magnetic medium on the hard drive's platters "store" some information about previously written data. Such information cannot be completely removed. Wiped data may be recovered even from mechanically damaged platters. So the only safe way to completely remove data from a hard drive is to mechanically grind the magnetic medium off the drive platters or dissolve them in special chemical solvents.

But in order to recover the wiped data using one of these techniques, a hard drive must be disassembled, its platters placed in a precise magnetic field measurement system, and the results of such measurement statistically processed. All that is very expensive and requires a very qualified and experienced personnel and a specially developed equipment. Only a very advanced organization such as a law enforcement or intelligence agency of a developed nation, or a special high-tech firm can afford this. Moreover, each successive wiping pass makes such

data recovery much and much harder. So, the **DoD 5220.22-M(3)** clearing and sanitizing standard overwriting the data with a special pattern through 3 passes is a rather reliable and safe choice for this case.


If you need the ultimate security, use the **DoD 5220.22-M(7)** clearing and sanitizing standard, the **Bruce Schneier(7)**, or even the **Peter Gutmann (35)** wiping algorithms. They render data almost unrecoverable, but they are extremely slow.

### Wiping Disk Objects:

#### To wipe a disk object,

- 1 Right-click the disk object in the Device view pane and select Wipe...
- > The Wipe an object dialog box will appear.

#### Wiping Disk Objects



- 2 Select the desired wiping algorithms and click the OK button.  
You may wipe only unused space on the object.
- > R-Studio will start wiping the object.

## 2.3 Mass File Recovery

### Recovery of multiple files

If you need to recover multiple files you may do it through the following steps:

- 1 Find and mark all the necessary files  
Go to the [Find and Mark Multiple Files](#) topic for more information
- 2 Recover all marked files in a single file recovery step  
Go to the [Recover Multiple Files](#) topic for more information
- 3 Create file recovery lists to manually edit the list of files to recovery (Technician/T80+ version)  
Go to the [File Recovery Lists](#) topic for more information

### Memory considerations

R-Studio stores information about found files in computer memory. If there are too many files, R-Studio may run out of it. To avoid this, you have two options:

## Recover all files

If you want to recover data from an entire file system object (a [logical disk](#), [partition](#), [partition image](#), etc.), you may use the **Recover All Files** command from the **Drive** or shortcut menu. Right click the object in the Drives panel to access the shortcut menu. A [Recover](#) dialog box will appear. Select required restore settings, including file mask. This command restores unlimited number of files without memory restrictions.

## View file information in steps

As soon as **R-Studio** nearly runs out of memory, a Too many files... message appears. You may temporarily stop file listing and browse through found files. Then you can resume file listing. You also may skip this file section and continue file listing.

In all cases, **R-Studio** keeps information about the entire file structure.

- [Find and Mark Multiple Files](#)
- [Recover Multiple Files](#)

### 2.3.1 Find and Mark Multiple Files

If you need to find and mark many files at once, you may do that in the following ways:

***By sorting them by their extensions or creation/~~m~~odification/~~a~~ccessed time***

**To sort files by their extensions or creation/~~m~~odification/~~a~~ccessed time,**

\* In the **Folders** panel select the tab

**Extensions** to sort the files by their extensions

**Creation Time** to sort the files by their creation time

**Modification Time** to sort the files by their modification time

**Accessed Time** to sort the files by their accessed time

▣ ***Other ways to sort files by their extensions or creation/~~m~~odification/~~a~~ccessed time***

- Select the disk in Drives panel, select **Open Drive Files Sorted By** on the **Drive** menu, and select the respective option,

or


- In the Drives panel, right-click the disk and select **Open Drive Files Sorted By** on the shortcut menu and select the respective option,

or

- In the Folders panel, right-click the disk letter and select **Show Files Sorted By** on the shortcut menu and select the respective option,

> **R-Studio will show the sorted files in the Folders and Content panels, showing the path to each file:**

Folders panel for files sorted by their extensions



Content panel with files/folders sorted by their extensions

Contents									
	Name	Path	Size	Created	Modified	Accessed	Fileid	ParentId	
<input type="checkbox"/>	AlbumArt_00FEB343-A4EF-48C...	Root/Music/Manu_Chaoc/	14542 Bytes	12/4/2012 6:55:38 PM	12/4/2012 6:55:40 PM	12/3/2012 11:00:00 PM	57 (53)	26 (31)	
<input type="checkbox"/>	AlbumArt_00FEB343-A4EF-48C...	Root/Music/Elton_John/	14418 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:05:46 PM	12/3/2012 11:00:00 PM	38 (32)	26 (31)	
<input type="checkbox"/>	AlbumArt_00FEB343-A4EF-48C...	Root/Music/Manu_Chaoc/	3340 Bytes	12/4/2012 6:55:38 PM	12/4/2012 6:55:38 PM	12/3/2012 11:00:00 PM	55 (51)	26 (31)	
<input type="checkbox"/>	AlbumArt_00FEB343-A4EF-48C...	Root/Music/Elton_John/	3186 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:04:58 PM	12/3/2012 11:00:00 PM	39 (33)	26 (31)	
<input type="checkbox"/>	AlbumArt_6609CAD8-CCF6-4F...	Root/Music/Elton_John/	7327 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:10:04 PM	12/3/2012 11:00:00 PM	40 (34)	26 (31)	
<input type="checkbox"/>	AlbumArt_6609CAD8-CCF6-4F...	Root/Music/Elton_John/	2245 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:08:22 PM	12/3/2012 11:00:00 PM	41 (35)	26 (31)	
<input type="checkbox"/>	AlbumArt_758956AA-1FD8-41D...	Root/Music/Elton_John/	7967 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:10:32 PM	12/3/2012 11:00:00 PM	42 (36)	26 (31)	
<input type="checkbox"/>	AlbumArt_758956AA-1FD8-41D...	Root/Music/Elton_John/	2243 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:09:22 PM	12/3/2012 11:00:00 PM	43 (37)	26 (31)	
<input checked="" type="checkbox"/>	AlbumArt_A0F31A58-545E-402...	Root/Music/Marley/	12034 Bytes	12/4/2012 6:55:59 PM	4/27/2008 6:03:20 PM	12/3/2012 11:00:00 PM	71 (64)	59 (31)	
<input checked="" type="checkbox"/>	AlbumArt_A0F31A58-545E-402...	Root/Music/Marley/	2780 Bytes	12/4/2012 6:55:59 PM	4/27/2008 6:03:06 PM	12/3/2012 11:00:00 PM	72 (65)	59 (31)	
<input type="checkbox"/>	AlbumArt_AD88489E-F38C-494...	Root/Music/Elton_John/	10136 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:08:08 PM	12/3/2012 11:00:00 PM	44 (38)	26 (31)	
<input type="checkbox"/>	AlbumArt_AD88489E-F38C-494...	Root/Music/Elton_John/	2577 Bytes	12/4/2012 6:55:55 PM	4/27/2008 5:07:06 PM	12/3/2012 11:00:00 PM	45 (39)	26 (31)	
<input type="checkbox"/>	AlbumArtSmall.jpg	Root/Music/Elton_John/	2243 Bytes	12/4/2012 6:55:54 PM	4/27/2008 5:09:22 PM	12/3/2012 11:00:00 PM	37 (29)	26 (31)	
<input checked="" type="checkbox"/>	AlbumArtSmall.jpg	Root/Music/Marley/	2780 Bytes	12/4/2012 6:55:59 PM	4/27/2008 6:03:06 PM	12/3/2012 11:00:00 PM	70 (63)	59 (31)	
<input type="checkbox"/>	AlbumArtSmall.jpg	Root/Music/Elton_John/	3340 Bytes	12/4/2012 6:55:38 PM	12/4/2012 6:55:38 PM	12/3/2012 11:00:00 PM	54 (50)	26 (31)	
<input checked="" type="checkbox"/>	Folder.jpg	Root/Music/Marley/	12034 Bytes	12/4/2012 6:55:59 PM	4/27/2008 6:03:20 PM	12/3/2012 11:00:00 PM	74 (67)	59 (31)	
<input type="checkbox"/>	Folder.jpg	Root/Music/Manu_Chaoc/	14542 Bytes	12/4/2012 6:55:38 PM	12/4/2012 6:55:40 PM	12/3/2012 11:00:00 PM	56 (52)	26 (31)	
<input type="checkbox"/>	Folder.jpg	Root/Music/Elton_John/	7967 Bytes	12/4/2012 6:55:57 PM	4/27/2008 5:10:32 PM	12/3/2012 11:00:00 PM	53 (49)	26 (31)	
<input type="checkbox"/>	IMG_6001.JPG	Root/SRECYCLE.BIN/	656192 Bytes	12/4/2012 6:57:49 PM	5/17/2010 4:17:56 PM	12/3/2012 11:00:00 PM	172 (116)	146 (31)	
<input type="checkbox"/>	IMG_6002.JPG	Root/SRECYCLE.BIN/	937070 Bytes	12/4/2012 6:57:49 PM	5/17/2010 4:18:14 PM	12/3/2012 11:00:00 PM	173 (117)	146 (31)	
<input type="checkbox"/>	IMG_6003.JPG	Root/SRECYCLE.BIN/	1180895 Bytes	12/4/2012 6:57:49 PM	5/17/2010 4:18:36 PM	12/3/2012 11:00:00 PM	174 (118)	146 (31)	
<input type="checkbox"/>	Picture 113.jpg	Root/	3048786 Bytes	2/24/2009 2:42:33 PM	4/23/2007 12:13:32 PM	12/3/2012 11:00:00 PM	167 (113)	146 (31)	
<input type="checkbox"/>	Picture 149.jpg	Root/	1678083 Bytes	2/24/2009 2:43:12 PM	4/23/2007 12:15:22 PM	12/3/2012 11:00:00 PM	168 (114)	146 (31)	
<input type="checkbox"/>	Picture 197.jpg	Root/	2034548 Bytes	2/24/2009 2:44:51 PM	4/23/2007 12:20:16 PM	12/3/2012 11:00:00 PM	169 (115)	146 (31)	

## To return to the conventional view,

- \* In the Drives panel, right-click the logical disk, select **Open Drive Files Sorted By** on the shortcut menu, and select **Real File System Structure**,

or

In the Folders panel, select **Show Files Sorted By** on the **Drive** menu and select **Real File System Structure**

or

Select the **Real** tab

## By finding and marking multiple files using the [Find/Mark](#) dialog box


You may find and mark all the files on the entire disk by using **Mark matched files** in the **Find/Mark** mode option. You may specify all the necessary search options and mark all the found files. Please note that each find and mark/unmark operation is independent from previous ones. That is, if a file matches the search criteria, it will be marked/unmarked regardless of its previous marked/unmarked state.

For example, if you first mark all `doc` files, and then all `txt` files, all `doc` files remain marked, too. If you then decide to unmark all files smaller than 2 kB, all `doc` and `txt` files will stay marked except those that less than 2 kB.

## 2.3.2 Recover Multiple Files

If **R-Studio** while recovering files encounters either an already existing file or file with a broken name, normally it will stop working and ask you what to do with the file. If you recover multiple files, that may require you answer a lot of the same questions. You may use **Mass File Recovery Options** on the [Recover](#) dialog box to instruct **R-Studio** what to do in those cases for all files.

## Recover (Advanced) dialog box



### Advanced file recovery options

File Already Exists	These options instruct <b>R-Studio</b> what to do if there already exists a file with the same name.
Extended options	If this option is selected, <a href="#">more advanced options</a> become accessible to process multiple duplicates of the file.
Prompt	If this option is selected, <b>R-Studio</b> asks the user what to do for each such file. It stops file recovery until it receives the answer.
Rename	If this option is selected, <b>R-Studio</b> adds a File ID to the file name. If a file already exists with the same name and that file ID, a number will be added to the file name and file ID.
Skip	If this option is selected, <b>R-Studio</b> skips all new files with the same name.
Overwrite	If this option is selected, <b>R-Studio</b> overwrites the existing file with the new one.
Overwrite Older	If this option is selected, <b>R-Studio</b> overwrites the existing file with the new one if the existing file is older than the new file. The time stamp used is Modified.
Overwrite Smaller	If this option is selected, <b>R-Studio</b> overwrites the existing file with the new one if the existing file is smaller than the new file. The time stamp used is Modified.
Overwrite Bigger	If this option is selected, <b>R-Studio</b> overwrites the existing file with the new one if the existing file is bigger than the new file. The time stamp used is Modified.
Broken File Name	These options instruct <b>R-Studio</b> what to do if a file to be recovered appears to have an invalid name.
Prompt	If this option is selected, <b>R-Studio</b> shows the standard <a href="#">Broken File Name</a> dialog box for each file with a broken file name. It stops file recovery until it receives the answer.
Rename and change all invalid symbols to:	If this option is selected, <b>R-Studio</b> changes all invalid characters to the character specified.
Skip	If this option is selected, <b>R-Studio</b> skips all files with broken file names.
Hidden Attribute	These options instruct <b>R-Studio</b> what to do if a file to be recovered appears to have the Hidden attribute.
Prompt	If this option is selected, <b>R-Studio</b> asks the user what to do with the attribute. It stops file recovery until it receives the answer.

Remove	If this option is selected, <b>R-Studio</b> removes the Hidden attribute from all files.
Keep	If this option is selected, <b>R-Studio</b> keeps the Hidden attribute for all files.

### **Extended options**

These options give you more flexible ways to process multiple files with the same name. You may compare files by time (Modified) and size, and decide what **R-Studio** should do with those duplicates. If any of the files has an invalid time, the comparison by time is skipped. In this case, if comparison by size is not active, **R-Studio** goes to the default action..

#### **Extended advanced file recovery options**

First compare time First compare size	These options instruct <b>R-Studio</b> which condition to use first, file time or size.
Compare time Compare size	These options instruct <b>R-Studio</b> to enable comparison by time and size..
Actions	These selectable actions instruct <b>R-Studio</b> what to do if the condition is met.
Empty field	If this option is selected, <b>R-Studio</b> skips the condition.
Prompt	If this option is selected, <b>R-Studio</b> asks the user what to do for each such file. It stops file recovery until it receives the answer.
Rename	If this option is selected, <b>R-Studio</b> adds a File ID to the file name. If a file already exists with the same name and that file ID, a number will be added to th file name and file ID.
Skip	If this option is selected, <b>R-Studio</b> skips all new files with the same name.
Overwrite	If this option is selected, <b>R-Studio</b> overwrites the existing file with the new one.
Time conditions	If the Modified time stamp is invalid, <b>R-Studio</b> will skip the comparison.
Equal time	Two time stamps are the same.
Older	The existing file is older than the new one.i
Newer	The existing file is newer than the new one.i
Size conditions	
Equal size	Two files have the same size.
Smaller	The existing file is smaller than the new one.i
Bigger	The existing file is bigger than the new one.i
By default	The action <b>R-Studio</b> takes when none of the comparison conditions have been met. That may happen when the comparison by size is not enabled.

### **2.3.3 Recovery Lists**

You may create a file containing a list of files and folder found on a [disk/partition](#). Then such file may be manually edited to specify files to recover, and then loaded back into **R-Studio**. **R-Studio** will automatically mark the files in this list for recovery. Such lists are very useful, for example, when it is necessary to have many files approved for recovery by someone else who is far away from the computer where **R-Studio** is running.

You may create recovery lists for the entire disk or for specific folders. Moreover, you may create a recovery list for all files within the disk/folder, or for marked files/folders only.

All versions of **R-Studio** can create recovery lists in the plain text format with basic functionality. **R-Studio Technician/T80+** can create [custom recovery lists](#) in other formats with more advanced options

### Creating a simple recovery list

#### To create a recovery list


**1 For an entire disk, select Export Recovery List on the File menu, or**

Right-click the uppermost folder (higher than **Root**, usually the letter or the name of the disk) and select **Export Recovery List** on the shortcut menu.


**For a specific folder, right-click the folder and select Export Recovery List on the shortcut menu.**

**2 Specify the place to save the recovery list and other necessary options on the Export Recovery List dialog box**

Export Recovery List **dialog box**



Options **dialog box**



#### **Export Recovery List options**

Export the entire folder/file tree Export marked file/folder names Export file/folder names	Specifies which file and folder names will be exported.
File format:	A file format for the recovery list. Only text format is available for the standalone and corporate versions. <b>R-Studio Technician/T80+</b> can create <a href="#">custom recovery lists</a> in other formats with more advanced options The following formats are available for <b>R-Studio Technician/T80+</b> version: Plain Text HTML XML JSON CSV
File name:	Specifies a file name of the recovery list.

### Editing the file recovery list

All files without any marks in the recovery list will be marked when the list is loaded into **R-Studio**. So, if you have some files in the recovery list that don't need to be recovered, just delete them from the list. In addition, you may use the following marks to specify some options

:+ Mark the file, or the folder, all its files, and subfolders within the folder.



- : \* Mark the file, or the folder and its files, don't mark subfolders in the folder.
- : - Unmark the file, or the folder, its files, and subfolders in the folder.
- : = Unmark the file or the folder and its files, dont unmark subfolders in the folder.
- : ! Provide the information on the file. (**R-Studio Technician/T80+** only)

**R-Studio** processes records in the list consequently. That is, if there are the following lines in the file,

```
:+Files_to_Recover\  
:-Files_to_Delete\File_2.jpg
```

the file `File_2.jpg` won't be marked for recovery, while for the lines

```
:-Files_to_Recover\File_2.jpg  
:+Files_to_Recover\  
file File_2.jpg will be.
```

### Loading the edited recovery list

#### To load a recovery list into R-Studio,

- \* **Select Import Recovery List from the File menu and select the file, or** Right-click the uppermost folder (higher than **Root**, usually the letter or the name of the disk) and select **Import Recovery List** on the shortcut menu.
- > **R-Studio will load the file and mark the files accordingly.**


### An example of a simple recovery list

As an example, we'll create a simple recovery list, edit it to mark only those files that are to be recovered, and load it back to mark those files.

#### To create such recovery list

- \* **Mark the necessary folders, right-click the Root folder, and select Export Recovery List on the shortcut menu.** Right-click the uppermost folder (higher than **Root**, usually the letter or the name of the disk) and select **Export Recovery List** on the shortcut menu.

#### Export Recovery List



Specify the necessary options and click the **OK** button.

> **R-Studio will save the file.**

### ***Structure of a simple recovery list file created by R-Studio***

```
:# Version = 1
:# Sort = by real
:# PathDelim = /
:# CaseSensitive
:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs test";
fs:"NTFS";
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";
Diving/
Diving/Aquarium/
Diving/Aquarium/20190822_100644.jpg
Diving/Aquarium/20190822_101620.jpg
Diving/Aquarium/20190822_102526.jpg
Diving/Aquarium/20190822_103830.jpg
Diving/Aquarium/20190822_104333.jpg
Diving/MyPhoto1.jpg
Diving/MyPhoto2.jpg
Diving/MyPhoto3.jpg
Diving/MyPhoto4.JPG
Diving/MyPhoto5.jpg
SF/
SF/Sea-Lions/
SF/Sea-Lions/IMG_3493.JPG
SF/Sea-Lions/IMG_3535.JPG
SF/Sea-Lions/IMG_3542.JPG
SF/Sea-Lions/IMG_3579.JPG
SF/Sea-Lions/IMG_3580.JPG
SF/Sea-Lions/IMG_3581.JPG
SF/Sea-Lions/IMG_3589.JPG
SF/IMG_0869.JPG
SF/IMG_0873.JPG
SF/IMG_0890.JPG
SF/IMG_1739.JPG
SF/IMG_3460.JPG
SF/IMG_3461.JPG
SF/IMG_3476.JPG
SF/IMG_3478.JPG
SF/IMG_3479.JPG
SF/IMG_3480.JPG
SF/IMG_3481.JPG
SF/IMG_3493.JPG
SF/IMG_3535.JPG
SF/IMG_3542.JPG
SF/IMG_3579.JPG
SF/IMG_3580.JPG
SF/IMG_3581.JPG
SF/IMG_3589.JPG
SF/IMG_3590.JPG
SF/IMG_3591.JPG
SF/IMG_3592.JPG
```

```
SF/IMG_3593.JPG
SF/IMG_3594.JPG
SF/IMG_3595.JPG
SF/IMG_3596.JPG
SF/IMG_3608.JPG
SF/IMG_3627.JPG
MyPhoto6.JPG
MyPhoto7.JPG
MyPhoto8.JPG
MyPhoto9.JPG
```

If such recovery list is created from an entire logical disk/partition, it will contain several virtual folders. For example, they'll have the following structure for an NTFS partition.

```
///m/$Extend/
///m/$Extend/$Deleted/
///m/$Extend/$RmMetadata/
///m/$Extend/$RmMetadata/$Txf/
///m/$Extend/$RmMetadata/$TxfLog/
///m/$Extend/$RmMetadata/$TxfLog/$Tops
///m/$Extend/$RmMetadata/$TxfLog/$TxfLog.blf
///m/$Extend/$RmMetadata/$TxfLog/$TxfLogContainer0000000000000000000001
///m/$Extend/$RmMetadata/$TxfLog/$TxfLogContainer0000000000000000000002
///m/$Extend/$RmMetadata/$Repair
///m/$Extend/$ObjId
///m/$Extend/$Quota
///m/$Extend/$Reparse
///m/$AttrDef
///m/$BadClus
///m/$Bitmap
///m/$Boot
///m/$LogFile
///m/$MFT
///m/$MFTMirr
///m/$Secure
///m/$UpCase
///m/$Volume
```

Now we need to edit this file to mark for recovery the following folders/files:

1. All files in the root folder;
2. Two files `MyPhoto1.jpg` and `MyPhoto3.jpg` in the `Diving` subfolder;
3. All files in the `Diving/Aquarium/` folder;
4. All files in the `SF/` folder except the `SF/Sea-Lions/` subfolder.

### ***The edited simple recovery list***

The final simple recovery list will be the following:

```
:# Version = 1
:# Sort = by real
:# PathDelim = /
:# CaseSensitive
```

```

:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs test";
fs:"NTFS";
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";
:= Diving/
:+ Diving/Aquarium/
:+ Diving/MyPhoto1.jpg
:+ Diving/MyPhoto3.jpg
:+ SF/
:- SF/Sea-Lions/
MyPhoto6.JPG
MyPhoto7.JPG
MyPhoto8.JPG
MyPhoto9.JPG

```

### Loading the edited recovery list

When we load this recovery list into **R-Studio**, will see the following results;

The root folder

Name	Recovery chance	Bad sectors	Size, Bytes	Created	Mod
Diving				11/22/2022 12:35:18 PM	11/22/2022
NY				11/22/2022 12:35:20 PM	11/22/2022
SF				11/22/2022 12:35:27 PM	11/22/2022
System Volume Information				11/22/2022 12:34:36 PM	11/22/2022
Vegas				11/22/2022 12:35:48 PM	11/22/2022
MyPhoto6.JPG	Good (Existin OK)		1,123,560	11/22/2022 12:35:56 PM	4/29/2009 0
MyPhoto7.JPG	Good (Existin OK)		862,983	11/22/2022 12:35:56 PM	4/29/2009 0
MyPhoto8.JPG	Good (Existin OK)		1,021,937	11/22/2022 12:35:56 PM	4/29/2009 0
MyPhoto9.JPG	Good (Existin OK)		3,533,017	11/22/2022 12:35:57 PM	4/29/2009 0

The Diving folder

Name	Recovery chance	Bad sectors	Size, Bytes	Created	Mod
Aquarium				11/22/2022 01:59:07 PM	11/22/2022
MyPhoto1.jpg	Good (Existin OK)		2,682,000	11/22/2022 12:35:28 PM	4/29/2009 0
MyPhoto2.jpg	Good (Existin OK)		1,830,252	11/22/2022 12:35:19 PM	4/29/2009 0
MyPhoto3.jpg	Good (Existin OK)		1,816,964	11/22/2022 12:35:19 PM	4/29/2009 0
MyPhoto4.JPG	Good (Existin OK)		901,269	11/22/2022 12:35:19 PM	4/29/2009 0
MyPhoto5.jpg	Good (Existin OK)		3,286,883	11/22/2022 12:35:20 PM	4/29/2009 0

The SF folder

Name	Recovery chance	Bad sectors	Size, Bytes	Created	Mod
Sea-Lions				11/22/2022 01:24:57 PM	11/22/2022
IMG_0869.JPG	Good (Existin OK)		3,698,659	11/22/2022 12:35:27 PM	5/30/200
IMG_0873.JPG	Good (Existin OK)		5,881,104	11/22/2022 12:35:28 PM	5/30/200
IMG_0890.JPG	Good (Existin OK)		5,663,358	11/22/2022 12:35:29 PM	5/30/200
IMG_1739.JPG	Good (Existin OK)		4,266,181	11/22/2022 12:35:30 PM	6/5/2000
IMG_3460.JPG	Good (Existin OK)		4,593,453	11/22/2022 12:35:31 PM	6/5/2000
IMG_3461.JPG	Good (Existin OK)		4,102,032	11/22/2022 12:35:31 PM	6/5/2000
IMG_3476.JPG	Good (Existin OK)		4,114,595	11/22/2022 12:35:32 PM	6/5/2000
IMG_3478.JPG	Good (Existin OK)		4,968,784	11/22/2022 12:35:33 PM	6/5/2000
IMG_3479.JPG	Good (Existin OK)		4,484,110	11/22/2022 12:35:34 PM	6/5/2000
IMG_3480.JPG	Good (Existin OK)		4,491,209	11/22/2022 12:35:34 PM	6/5/2000
IMG_3481.JPG	Good (Existin OK)		3,541,845	11/22/2022 12:35:35 PM	6/20/200
IMG_3493.JPG	Below Averag OK		4,985,023	11/22/2022 12:35:36 PM	6/5/2000
IMG_3535.JPG	Below Averag OK		3,718,479	11/22/2022 12:35:37 PM	6/5/2000
IMG_3542.JPG	Below Averag OK		4,110,749	11/22/2022 12:35:37 PM	6/5/2000

## 2.4 Volume Sets and RAIDs

**R-Studio** detects and processes valid hardware volume sets and RAIDs like regular drives/volumes.

**R-Studio** can analyze and recover data from software volume sets and RAIDs. If a software volume set or RAID is present in your system, **R-Studio** detects it, and a *Volume sets and RAIDs* object appears in the Drives panel. This object can be searched for files, scanned, and files found on it can be recovered the same way as from normal drives/volumes.

If, due to hardware failure, a hardware volume set or RAID cannot be accessed, or due to data loss your system does not recognize a software volume set or RAID, and you know what drives were in it, you may create a

*Virtual volume set* or *RAID* and process it like a real software volume set or RAID or hardware volume set or RAID.

You may find more information on RAID types in our article [What is Hardware RAID](#).

You may turn [numerical indexes](#) for objects to distinguish them better while creating virtual RAIDs.

- [Volume Sets, Stripe Sets, and Mirrors](#)
- [Basic RAID 4 and RAID 5 Operations](#)
- [Working with RAID 6 Presets](#)
- [Working with RAID6 \(Double Xor\)](#)
- [Working with RAIDs with Parity Delays](#)
- [Working with Advanced RAID Layouts](#)
- [Nested and Non-Standard RAID Levels](#)
- [Finding RAID Parameters](#)
- [Checking RAID Consistency](#)
- [Syntax of a Description File for RAID Configurations](#)
- [Description Files for RAID Configurations](#)
- [Reverse RAIDs](#)
- [Various Disk and Volume Managers](#)
- [Mounting Virtual Objects in the System](#)

### **Managing your own RAID layouts**

#### **To save your own RAID layout in the presets**

- 1 Click the **More...** button on **Parents** tab and select **Save** on the shortcut menu.
- 2 Specify the name for the configuration on the **Preset name** dialog box.

Preset name dialog box



- > The new RAID configuration will be saved in the presets

The configurations are stored in the [user's RAID layout file](#). The path and name for this file is specified on the [R-Studio Settings](#) dialog box. If no file is specified, **R-Studio** will ask you to enter the name.

#### **Loading your RAID configuration**

If there're objects in the **Parents** tab, the preset will be applied to them. If the **Parents** tab is empty, **R-Studio** will search the drives listed in the **Drives** tab for the parents in the [user's RAID layout file](#). If the search fails, **R-Studio** will show the Reference Parents not found message.

#### **To load your RAID configuration**


- 1 Click the **More...** button on **Parents** tab and select the preset you want to load
- > The new RAID configuration will be loaded

#### **To edit your own RAID configuration**

- 1 Click the **More...** button on **Parents** tab and select **Edit...** on the shortcut menu

## 2 Select the required configuration on the Edit Block RAID Layout Presets dialog box.

Edit Block RAID Layout Presets dialog box



## 3 Edit the parameters of the configuration and save it

> The new configuration parameters will be saved.

### Turning Drives On-Line and Off-Line on-the-fly

You may turn the objects in the virtual RAID or volume set on-line and off-line by selecting/clearing the checkbox on the Parents tab. It may be useful, for example, if you need to see which drive is non-actual in a RAID 5.

Actually, when you turn an object off-line, **R-Studio** substitutes it with a *Missing Drive* or *Empty Space* object.

### Missing Drives and Empty Space

If one [partition](#) from a hardware volume set or RAID or software volume set or RAID is absent, due to hardware failure, for example, you need to add a virtual missing drive or empty space in order to correctly reconstruct the hardware volume set or RAID or software volume set or RAID structure. The missing drive/empty space should be placed in the same place as the missing partition.

**Note:** **R-Studio** does not write anything real on the drive. Missing drives/empty space are virtual objects that do not affect actual data on the drive.

### To add a Missing drive/Empty space object

- 1 Select a *Volume sets and RAID's* object in the R-Studio's Drives panel
- 2 Right-click in the Parents tab in the right pane and select Add Missing Drive or Add Empty Space on the shortcut menu or select Add Missing Drive or Add Empty Space on the Create menu. Which object type is necessary, **R-Studio** decides automatically.

For the **Empty space** object, Specify its size on the Add Empty Space dialog box.

Add Empty Space dialog box



> A *Missing Drive* or *Empty Space* object will appear in the Parents tab

## 2.4.1 Volume Sets, Stripe Sets, and Mirrors

### To create a Volume set object

- 1 Click the Create Virtual RAID button and select Create Virtual Volume set or select the Create Virtual Volume set on the Create menu

## > A Virtual Volume set object will appear in the Drives panel

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adfc-...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJ80 01.01B01	WD-WCASJ0409502	#0 USB (...)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\VolumeSet\VolumeSetDisk1.bin		NTFS		897.75 MB
Y:\VolumeSet\VolumeSetDisk2.bin		NTFS		897.75 MB
Virtual Volume sets and RAID's				
Virtual volume set 1				

## 2 Drag the required partitions from the Drives panel to the Parents tab

### Other ways to add objects

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

**Note:** Objects should be placed in the same order as they were in the original volume set. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

Locate	Device/Disk	Info/Bus	Start/Serial	Size
N				
A	Y:\VolumeSet\VolumeSetDisk1.bin	NTFS		897.75 MB
B	Y:\VolumeSet\VolumeSetDisk2.bin			897.75 MB

## > The *Virtual volume set* or *RAID's* object can now be processed like regular drives/volumes


If **R-Studio** detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adfc-...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJ80 01.01B01	WD-WCASJ0409502	#0 USB (...)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\VolumeSet\VolumeSetDisk1.bin		NTFS		897.75 MB
Y:\VolumeSet\VolumeSetDisk2.bin		NTFS		897.75 MB
Virtual Volume sets and RAID's				
Virtual volume set 1		NTFS	0 Bytes	1.75 GB
Direct Volume		NTFS	0 Bytes	1.75 GB

## To create a Stripe set object (RAID 0)

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu

> **A Virtual Block RAID object will appear in the Drives panel**



**2 Select RAID 0 (Stripe set) on the RAID type**

**3 Drag the required partitions from the Drives panel to the Parents tab**

**Other ways to add objects**

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the Apply changes immediately checkbox on the Parents tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original volume set. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

**Object control buttons**


Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The Block size and Offset (in sectors) parameters must be set the same as for the original volume set.

You also need to specify Block order. You may select it on the Blocks order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but they cannot be recovered.






- > The Virtual Block RAID object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on the newly created RAID object, a partition object will appear in the Drives panel.


The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.



You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

## To create a Mirror set object (RAID 1)

- 1 Click the Create Virtual RAID button and select Create Virtual Mirror or select the Create Virtual Mirror on the Create menu
- > A Virtual Mirror object will appear in the Drives panel



## 2 Drag the required partitions from the Drives panel to the Parents tab

### Other ways to add objects

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

	Device/Disk	Info/Bus	Start/Serial	Size	Offset
A	Y:/RAID1/RAID1Disk1.bin	NTFS		897.75 MB	0 Sectors
B	Y:/RAID1/RAID1Disk2.bin	NTFS		897.75 MB	0 Sectors

### > The Virtual Mirror object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on the newly created RAID object, a partition object will appear in the Drives panel.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20...	44H5ATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume3303cc57-3e4d-45...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volumee0a573f2-14d5-40...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1...				
E:				
WDC WD10EACS-00ZJB0 01.01...	WD-WCASJ04095...	#0 USB...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:/RAID1/RAID1Disk1.bin		NTFS		897.75 MB
Y:/RAID1/RAID1Disk2.bin		NTFS		897.75 MB
Virtual Volume sets and RAID's				
Virtual mirror 1		NTFS	0 Bytes	897.75 MB
Direct Volume		NTFS	0 Bytes	897.75 MB

## 2.4.2 Basic RAID 4 and RAID 5 Operations

RAID 4 and RAID 5 are much similar. You may create and edit a RAID 4 object the same way as a RAID 5 one.

### To create a RAID 5 object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu

### > A Virtual Block RAID object will appear in the Drives panel

Device/Disk	Label	FS	Start	Size
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volumee0a573f2-14d5-4047...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Image: Y:/RAIDS/RAID5Disk3.dsk				
Promise1+0 JBOD1.10		0 Bytes	37.31 GB	
Empty Space30			512 Bytes	37.31 GB
Empty Space29			31.50 KB	37.31 GB
Image: Y:/RAIDS/RAID5Disk2.dsk				
Promise1+0 JBOD1.10		0 Bytes	37.31 GB	
Image: Y:/RAIDS/RAID5Disk1.dsk				
Promise1+0 JBOD1.10		0 Bytes	37.31 GB	
Empty Space24			512 Bytes	37.31 GB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Virtual Volume sets and RAID's				
Virtual Block RAID 1				

### 2 Select RAID 5 on the RAID type

### 3 Drag the required partitions from the Drives panel to the Parents tab

#### ▣ Other ways to add objects

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the Apply changes immediately checkbox on the Parents tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 5. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

#### ▣ Object control buttons

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 5.

You also need to specify Block order for virtual RAID 5. You may select it on the Block order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but files from the RAID 5 cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 5. Find a file and preview it. If the file appears correct, you have created a correct RAID 5 layout.

If your RAID 5 has an unusual configuration, you may create them manually. See [Working with Advanced RAID Layouts](#) for details.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2 (3...	0 Bytes	931.51 GB
Volume3303cc57-3e4d-4507-872f-6ad5ef68209f	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volumee0a573f2-14d5-4047-adfc-387ed02237b9		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Image: Y:\RAIDS\RAID5Disk3.dsk				
Promise1+0 JBOD1.10			0 Bytes	37.31 GB
Empty Space30			512 Bytes	37.31 GB
Empty Space29			31.50 KB	37.31 GB
Image: Y:\RAIDS\RAID5Disk2.dsk				
Promise1+0 JBOD1.10			0 Bytes	37.31 GB
Image: Y:\RAIDS\RAID5Disk1.dsk				
Promise1+0 JBOD1.10			0 Bytes	37.31 GB
Empty Space24			512 Bytes	37.31 GB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB (0:0)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Virtual Volume sets and RAID5				
Virtual Block RAID 1			0 Bytes	74.62 GB
Empty Space34			512 Bytes	7.84 MB
Partition1	RAID5	NTFS	7.88 MB	74.49 GB
Empty Space35			74.50 GB	123.78 MB

### Parents tab

Virtual Block RAID 1

Drag disks or volumes to the list box to create a RAID set. Also you can use the shortcut menu to manage the RAID set.

N	Device/Disk	Info/Bus	Start/Serial	Size	Offset
A	Promise1+0 JBOD1.10 -> Image	#1 SCSI (3:0)		37.31 GB	0 Sectors
B	Promise1+0 JBOD1.10 -> Image	#2 SCSI (3:1)		37.31 GB	0 Sectors
C	Promise1+0 JBOD1.10 -> Image	#3 SCSI (3:2)		37.31 GB	0 Sectors

RAID Parameters

Choose Variants

RAID type: RAID5

Block order for: Left Asynchronous (Conf)

Parity delay: Not used

First parity: [ ]

Number of rows: 3

Block size: 64KB

Legend:

- Parity block
- Invalid block order
- Not ordered block
- Current sequence block
- Parity block of current sequence
- Member block of selected parity block

Apply changes immediately

More... Reset changes Apply

#### > The RAID 5 object can now be processed like regular drives/volumes

If R-Studio detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

### Creating and saving your own RAID 5 configuration

You may create and save your own RAID configurations for non-standard RAID5s. You may specify Offset, Block order/size and Row count. See [Working with Advanced RAID 5 Layouts](#) for details.

### 2.4.3 Working with RAID6 (Double Xor) Presets

R-Studio allows you to create and process RAID 6 Double Xor layouts with the following presets:

EVENODD

RAID DP

X-Code(2)

Adaptec 3805


In addition you may create your own RAID 6 configurations.

### Creating a RAID 6 (Double Xor) object from a preset:

We will use the EVENODD preset as an example.

#### To create a RAID 6 (Double Xor) object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A **Virtual Block RAID** object will appear in the **Drives** panel




- 2 Select **RAID 6/Double Xor** on the **RAID type**
- 3 Drag the required partitions from the **Drives** panel to the **Parents** tab

#### Other ways to add objects

- Right-click the **Parents** tab and select the required partition from the shortcut menu,
- OR
- Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the **Apply changes immediately** checkbox on the **Parents** tab. Click the **Apply** button to apply the changes when are you through.

#### Parents tab



**Note:** Objects should be placed in the same order as they were in the original volume set. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

#### Object control buttons

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original volume set. You also need to specify Blocks order (EVENODD for our case) for virtual RAID 6 (Double Xor). You may select it on the Blocks order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but they cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original volume set or RAID. Find a file and preview it. If the file appears correct, you have created a correct RAID layout.

#### > The Virtual Block RAID object can now be processed like regular drives/volumes

If R-Studio detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel. The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

The screenshot shows the 'Drives' panel with a tree view of storage devices. At the bottom, under 'Virtual Volume sets and RAID's, there is a 'Virtual Block RAID 1' entry. It is expanded to show a 'Direct Volume' sub-entry. The 'Direct Volume' entry has a file system of 'NTFS', a size of '0 Bytes', and a start offset of '0 Bytes'. Above it, the 'Virtual Block RAID 1' entry has a file system of 'NTFS' and a size of '3.51 GB'.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44HSATLKS	#1 SATA...	0 Bytes	931.51 GB
Volume{330cc57-3e4d-4507-87...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adf...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvel 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB (...)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID62X\RAID62X1.bin		NTFS		897.75 MB
Y:\RAID62X\RAID62X2.bin				897.75 MB
Y:\RAID62X\RAID62X3.bin				897.75 MB
Y:\RAID62X\RAID62X4.bin				897.75 MB
Y:\RAID62X\RAID62X5.bin				897.75 MB
Y:\RAID62X\RAID62X6.bin				897.75 MB
Virtual Volume sets and RAID's				
Virtual Block RAID 1		NTFS	0 Bytes	3.51 GB
Direct Volume		NTFS	0 Bytes	3.51 GB

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

## 2.4.4 Working with RAID 6 Presets

R-Studio allows you to create and process RAID 6 layouts. You may use either presets for several RAID 6 layouts, or use your own custom ones.

R-Studio provides presets for the following RAID 6 layouts:

**Reed-Solomon**

Left Synchronous  
(standard),

Left Asynchronous  
(continuous),

Right Synchronous

Right Asynchronous

**Creating a RAID 6 object from a preset:**

We will use the Reed-Solomon (Left Synchronous (standard)) preset as an example.

**To create a RAID 6 object**

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A **Virtual Block RAID** object will appear in the **Drives** panel

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB ...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID6RS\img.1.bin				897.75 MB
Y:\RAID6RS\img.2.bin		NTFS		897.75 MB
Y:\RAID6RS\img.3.bin				897.75 MB
Y:\RAID6RS\img.4.bin				897.75 MB
Y:\RAID6RS\img.5.bin				897.75 MB
Virtual Volume sets and RAIDs				
Virtual Block RAID 1				

- 2 Select **RAID 6/Reed-Solomon** on the **RAID type**
- 3 Drag the required partitions from the **Drives** panel to the **Parents** tab

**Other ways to add objects**


- Right-click the **Parents** tab and select the required partition from the shortcut menu,

OR

- Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the **Apply changes immediately** checkbox on the **Parents** tab. Click the **Apply** button to apply the changes when are you through.





**Note:** Objects should be placed in the same order as they were in the original volume set. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

#### Object control buttons

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original volume set.

You also need to specify Blocks order (Left Synchronous (standard) for our case) for virtual RAID 6. You may select it on the Blocks order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but they cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original volume set or RAID. Find a file and preview it. If the file appears correct, you have created a correct RAID layout.

#### > The Virtual Block RAID object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel. The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.



Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-x}	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0e573f2-14d5-4047-x}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB ...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID6RS\img1.bin				897.75 MB
Y:\RAID6RS\img2.bin		NTFS		897.75 MB
Y:\RAID6RS\img3.bin				897.75 MB
Y:\RAID6RS\img4.bin				897.75 MB
Y:\RAID6RS\img5.bin				897.75 MB
Virtual Volume sets and RAIDs				
Virtual Block RAID 1		NTFS	0 Bytes	2.63 GB
Direct Volume		NTFS	0 Bytes	2.63 GB

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

## 2.4.5 Working with RAID5 with Parity Delays

**R-Studio** allows you to create RAID5 with parity delays (any level that allows that). For example, let us create a RAID 5 with the parity delays with the following layout:

- Three drives,
- Delay=16
- Block size: 16 KB
- Offset: 1088 sectors (544 KB)
- Block order: Left Asynchronous (Continuous)

**Block order table:**

	A	B	C	
1	1	2	PD	Delay=16
2	3	4	PD	
3	5	6	PD	
4	7	8	PD	
5	9	10	PD	
6	11	12	PD	
7	13	14	PD	
8	15	16	PD	
9	17	18	PD	
10	19	20	PD	
11	21	22	PD	
12	23	24	PD	
13	25	26	PD	
14	27	28	PD	
15	29	30	PD	
16	31	32	PD	
17	33	PD	34	Delay=16
18	35	PD	36	

19	37	PD	38
20	39	PD	40
21	41	PD	42
22	43	PD	44
23	45	PD	46
24	47	PD	48
25	49	PD	50
26	51	PD	52
27	53	PD	54
28	55	PD	56
29	57	PD	58
30	59	PD	60
31	61	PD	62
32	63	PD	64
33	PD	65	66
34	PD	67	68
35	PD	69	70
36	PD	71	72
37	PD	73	74
38	PD	75	76
39	PD	77	78
40	PD	79	80
41	PD	81	82
42	PD	83	84
43	PD	85	86
44	PD	87	88
45	PD	89	90
46	PD	91	92
47	PD	93	94
48	PD	95	96

Delay=16

### To create such RAID 5,

- 1 Click the **Create virtual volume sets or RAID's** button and select **Create Virtual Block RAID & Autodetect** or select **Create Virtual Block RAID & Autodetect** on the **Create** menu

Check that the **Apply changes immediately** check box is clear on the **Parents** tab. This will prevent **R-Studio** from trying to start processing the RAID configuration until you specify it completely.

- 2 **Drag the required objects from the Drives pane to the Parents tab and select RAID 5 on the RAID type**

**Other ways to add objects**

- Right-click the **Parents** tab and select the required partition from the shortcut menu,

or


- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

These objects may be drives, logical drives, or images. Check that the objects are correctly placed.

**Note:** Objects should be placed in the same order as they were in the original RAID 5. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

**Object control buttons**

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)



**3 Specify the Block size and Offset parameters on the Parents tab**

Disregard the Block order field.

**4 Specify the parity delay number in the Parity delay control on the Parents tab.**


The number of rows will change to 48.

- ▣ If necessary, adjust the First parity parameter


By default, this parameter is set equal to Parity delay. By changing it, you may "shift" the block order table. For example, when the First parity parameter is set as 1 for the RAID 5 of 3 drives with Parity delay of 3., the block order table will be the following:

	1	2	PD
1	1	2	PD
2	3	PD	4
3	5	PD	6
4	7	PD	8
5	PD	9	10
6	PD	11	12
7	PD	13	14
8	15	16	PD
9	17	18	PD

## 5 Select Left Asynchronous (Continuous) on the Block Order Field and click the Apply button on the Parents tab



- > The created Virtual Block RAID 1 object can now be processed like regular drives/volumes. If R-Studio detects a valid file system Disk on this RAID object, a [partition](#) object will appear in the Drives panel.



The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

### 2.4.6 Working with Advanced RAID Layouts

R-Studio allows you to create and process very complex custom RAID layouts.

#### Advanced RAID 5

For example, let us create a RAID 5 with the following layout:

- Three drives,
- Block size: 4 KB
- Offset: 32768 sectors (64 KB)
- Block order:

	A	B	C
1	PD	1	2
2	PD	3	4

3	PD	5	6
4	7	PD	8
5	9	PD	10
6	11	PD	12
7	13	14	PD
8	15	16	PD
9	17	18	PD

### To create such RAID 5,

- 1 Click the **Create virtual volume sets or RAID**s button and select **Create Virtual Block RAID & Autodetect** or select **Create Virtual Block RAID & Autodetect** on the **Create** menu  
Check that the **Apply changes immediately check box** is clear on the **Parents** tab. This will prevent **R-Studio** from trying to start processing the RAID configuration until you specify it completely.
- 2 **Drug the required objects from the Drives pane to the Parents tab and select Custom on the RAID type**


#### Other ways to add objects

- Right-click the **Parents** tab and select the required partition from the shortcut menu,  
or
- Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

These objects may be drives, [logical disks](#), or images. Check that the objects are correctly placed.

#### Object control buttons

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)



### 3 Specify the Block size and Offset parameters on the Parents tab

Disregard the Block order for field.


### 4 Manually enter 9 to Number of rows on the Parents tab

The Block order table will expand.

### 5 Enter the block order in the table on the Parents tab


Use the RAID Sequence window to move from one row to another.

Sequences window




**Using the keyboard:** arrow keys to navigate, digit and p keys to enter the block order.

**Using the mouse:** right-click the cell and select the number or parity from the shortcut menu. If the block table is too large, you better use the keyboard to enter the digits.




**Corrections:** R-Studio will tell you if some digits are not correct. Navigate to the required cell and enter the correct value. Use the **Delete** key to clear a cell.




Clear the table: Right-click the table and select **Clear all** on the shortcut menu.

**6** When you finishes entering the information, click the **Apply** button on the Parents tab



- > The created Virtual Block RAID 1 object can now be processed like regular drives/volumes. If **R-Studio** detects a valid file system on this RAID object, a [partition](#) object will appear in the Drives panel. The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.





You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

### Advanced RAID 5

Another example is a RAID with the following layout, similar to that used in Mac Pro internal RAID cards with 4 drives.

- Four drives,
- Block size: 512 KB (1024 sectors)
- Offset: 32768 sectors (64 KB)
- Block order:

Sequence 1			Sequence 2			Sequence 3			Sequence 4		
A	B	C	D	A	B	C	D	A	B	C	D
PD	1	2	PD	3	4	PD	5	6	PD	7	8

As you see, this layout cannot be fit directly into a standard 2D block order table. Still, it's possible to create such RAID layout using the RAID Sequence window.

### To create such RAID,

- 1 **Click the Create virtual volume sets or RAID's button and select Create Virtual Block RAID & Autodetect** or select **Create Virtual Block RAID & Autodetect** on the **Create** menu

Check that the Apply changes immediately check box is clear on the Parents tab. This will prevent **R-Studio** from trying to start processing the RAID configuration until you specify it completely.

- 2 **Drag the required objects from the Drives pane to the Parents tab and select Custom on the RAID type**

#### **Other ways to add objects**

- Right-click the Parents tab and select the required partition from the shortcut menu,
- or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

These objects may be drives, logical disks, or images. Check that the objects are correctly placed.

#### **Object control buttons**

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)



Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-6ad5ef...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adfc-387ed0...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB (0...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID_MAC_Pro\RAID_MAC_ProDisk1.bin		NTFS		897.75 MB
Y:\RAID_MAC_Pro\RAID_MAC_ProDisk2.bin				897.75 MB
Y:\RAID_MAC_Pro\RAID_MAC_ProDisk3.bin				897.75 MB
Y:\RAID_MAC_Pro\RAID_MAC_ProDisk4.bin				897.75 MB
Virtual Volume sets and RAID5				
Virtual Block RAID 1				

### 3 Specify the Block size and Offset parameters on the Parents tab

Disregard the Block order field.

### 4 Manually enter 3 to Number of rows on the Parents tab and change Block order to Custom

### 5 Right-click the RAID Sequence window and select Remove All. Manually enter 3 to Number of rows on the Parents tab

### 6 Right-click Cell 1 in the block order table and select Create New Sequence.

### 7 Right-click Cell 2 in the block order table and select Add to Sequence, do that for Cell 3, too.

### 8 Right-click Cell 4 in the block order table and select Create New Sequence.

### 9 Right-click Cell 5 in the block order table and select Add to Sequence, do that for Cell 6, too.

Continue those steps for the rest of the table until the RAID Sequence window will have 4 sequences of 3 drives:

### Sequences window

RAID Sequences	
Add Empty	Remove Remove All
A1 B1 C1	
D1 A2 B2	
C2 D2 A3	
B3 C3 D3	

### 10 Select the first line in the RAID Sequence window, right-click Cell 1 in the block order table, and select Parity of Data.


If any unnecessary sequences appear, right-click them in the RAID Sequence window, and select Remove.

### 11 Right-click Cell 2 in the block order table and select 1, do that for Cell 3 selecting 2.


If any unnecessary sequences appear, right-click them in the RAID Sequence window, and select Remove.

### 12 Move to the next sequence in the RAID Sequence window and repeat the procedure for cells 4, 5, and 6.

Do that for the rest of the sequences until you fill all cells in the block order table in the Parents tab.



- > The created Virtual Block RAID 1 object can now be processed like regular drives/volumes. If R-Studio detects a valid file system on this RAID object, a partition object will appear in the Drives panel. The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.



You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

### Advanced RAID 6 Layout

For example, let us create a RAID 6 with the following layout:

- Five drives,
- Block size: 64 KB
- Offset: 0
- Block order:

	A	B	C	D	E
1	RS	1	2	3	PD
2	4	5	6	PD	RS
3	8	9	PD	RS	7
4	12	PD	RS	10	11
5	PD	RS	13	14	15

6	PA	PA	PA	PA	PA
---	----	----	----	----	----

where

PD is parity of data;

PA is parity of all;

RS is Reed-Solomon;

Rows from 1 to 5 use two types of error correction: parity of data (xor) and Reed-Solomon. That is, row 1 uses blocks A1 and E1, row 2 uses blocks D2 and E2, and so on.

Row 6 is used for error correction for columns. That is, column A uses block A6, column B uses B6, and so on. Parity of all is used for error correction.

- 1 **Click the Create virtual volume sets or RAID's button and select Create Virtual Block RAID & Autodetect** or select **Create Virtual Block RAID & Autodetect** on the **Create** menu

Check that the Apply changes immediately check box is clear on the Parents tab. This will prevent **R-Studio** from trying to start processing the RAID configuration until you specify it completely.

- 2 **Drag the required objects from the Drives pane to the Parents tab and select Custom on the RAID type**

**Other ways to add objects**

- Right-click the Parents tab and select the required partition from the shortcut menu,

or

- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

These objects may be drives, logical disks, or images. Check that the objects are correctly placed.

**Object control buttons**

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

Device/Disk	Label	FS	Start	Size
TOSHIBA DT01ACA100 MS20A750	44HSATLKS	#1 SATA2 ...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-6ad5e...}	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adfc-387ed...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21				931.51 GB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00Z1B01 01.01B01	WD-WCASJ0409502	#0 USB (0.0)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID6Complex\img1.bin		NTFS		897.75 MB
Y:\RAID6Complex\img2.bin				897.75 MB
Y:\RAID6Complex\img3.bin				897.75 MB
Y:\RAID6Complex\img4.bin				897.75 MB
Y:\RAID6Complex\img5.bin				897.75 MB
Virtual Volume sets and RAID5				
Virtual Block RAID 1				

### 3 Specify the Block size and Offset parameters on the Parents tab

Disregard the Block order parameter.

### 4 Manually enter 6 to Number of rows on the Parents tab

### 5 Enter the block order in the table on the Parents tab

You may enter either a block number, or an error correction block of the following types:

PD	Parity of data
PA	Parity of all
RS	Reed-Solomon
SP	Spare Part
I	Ignore


**Note:** You should specify an error correction block only when the correct sequence is selected on the RAID Sequences window.

#### Sequences window

Sequence
A1 B1 C1 D1 E1
A2 B2 C2 D2 E2
A3 B3 C3 D3 E3
A4 B4 C4 D4 E4
A5 B5 C5 D5 E5
A6 B6 C6 D6 E6
A1 A2 A3 A4 A5 A6
B1 B2 B3 B4 B5 B6
C1 C2 C3 C4 C5 C6
D1 D2 D3 D4 D5 D6
E1 E2 E3 E4 E5 E6

**Using the keyboard:** arrow keys to navigate, digit, and rs, pd, pa, u, i keys to enter the block order.

**Using the mouse:** right-click the cell and select the number or parity from the shortcut menu. If the block table is too large, you better use the keyboard to enter the digits.

**For the rows:**

Select the required row sequence on the RAID Sequences window, select the cell on the RAID table, and enter the required value. **R-Studio** automatically generates those sequences when you add RAID parents.

**For the columns and arbitrary sequences:**


You need to create those sequences and add the respective blocks to it manually.

**To create a sequence:** Click **Add empty** on the RAID Sequences window or select **Create New Sequence** on the shortcut menu on the Parents tab.

**To add a block to a sequence:** Right-click the respective cell and select **Add To Sequence** on the shortcut menu on the Parents tab.

**To remove a block to a sequence:** Right-click the respective cell and select **Remove From Sequence** on the shortcut menu on the Parents tab.

## 6 When you finishes entering the information, click the Apply button on the Parents tab



### > The created Virtual Block RAID 1 object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on this RAID object, a partition object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adf...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB (...)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID6Complex\img1.bin				897.75 MB
Y:\RAID6Complex\img2.bin		NTFS		897.75 MB
Y:\RAID6Complex\img3.bin				897.75 MB
Y:\RAID6Complex\img4.bin				897.75 MB
Y:\RAID6Complex\img5.bin				897.75 MB
Virtual Volume sets and RAIDs				
Virtual Block RAID 1		NTFS	0 Bytes	2.19 GB
Direct Volume		NTFS	0 Bytes	2.19 GB

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

## 2.4.7 Nested and Non-Standard RAID Levels

R-Studio can work with various [nested and non-standard RAID levels](#). Currently, the following RAID levels are supported:

- [RAID10 \(1+0\)](#)
- [RAID1E](#)
- [RAID5E](#)
- [RAID5EE](#)
- [RAID6E](#)

### 2.4.7.1 RAID10 (1+0)

A RAID 10 (or 1+0) is a stripe of mirrors. Its block order can be represented as:

	A	B	C	D
1	1	1	2	2

#### To create a RAID 10 object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A **Virtual Block RAID** object will appear in the **Drives** panel

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-adf...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB (...)	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID10\RAID10-1.bin				897.75 MB
Partition23			512 Bytes	897.75 MB
Y:\RAID10\RAID10-2.bin				897.75 MB
Partition25			512 Bytes	897.75 MB
Y:\RAID10\RAID10-3.bin				897.75 MB
Y:\RAID10\RAID10-4.bin				897.75 MB
Virtual Volume sets and RAIDs				
Virtual Block RAID 1				897.75 MB

## 2 Drag the required partitions from the Drives panel to the Parents tab

### ▣ Other ways to add objects

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

## 3 Select RAID 10 on the RAID type

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the Apply changes immediately checkbox on the Parents tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 10. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

### ▣ Object control buttons

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 10.

You also need to specify Block order for virtual RAID 10. You may select it on the Block order drop-down or shortcut menu.


If the those parameters are not correct, data on the parents will not be damaged, but files from the RAID 10 cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 10. Find a file and preview it. If the file appears correct, you have created a correct RAID 10 layout.



Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44HSATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-4047-...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB ...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID10\RAID10-1.bin			512 Bytes	897.75 MB
Partition23			512 Bytes	897.75 MB
Y:\RAID10\RAID10-2.bin			512 Bytes	897.75 MB
Partition25			512 Bytes	897.75 MB
Y:\RAID10\RAID10-3.bin			512 Bytes	897.75 MB
Y:\RAID10\RAID10-4.bin			512 Bytes	897.75 MB
Virtual Volume sets and RAIDs				
Virtual Block RAID 1			0 Bytes	1.75 GB
Empty Space33			512 Bytes	7.84 MB
Partition1		NTFS	7.88 MB	74.49 GB

Parents tab



### > The RAID 10 object can now be processed like regular drives/volumes

If R-Studio detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

#### 2.4.7.2 RAID1E

RAID 1E utilizes both the mirroring and striping: data is striped across all drives, as in RAID 0. Additionally, a copy of each stripe is stored on a different drive, as in RAID 1. Its block order can be represented as:


	A	B	C
1	1	1	2
2	2	3	3

#### To create a RAID 1E object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu



> **A Virtual Block RAID object will appear in the Drives panel**



**2 Drag the required partitions from the Drives panel to the Parents tab**

**Other ways to add objects**

- Right-click the Parents tab and select the required partition from the shortcut menu, or
- Right-click the partition in the Drives panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

**3 Select RAID 1E on the RAID type**

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the Apply changes immediately checkbox on the Parents tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 1E. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

**Object control buttons**

Locate	Click this button to locate the selected object in the Drives panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 1E.

You also need to specify Block order for virtual RAID 1E You may select it on the Block order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but files from the RAID 1E cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 1E. Find a file and preview it. If the file appears correct, you have created a correct RAID 1E layout.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A...	44H5ATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-450...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5-404...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.94 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01...	WD-WCASJ0409502	#0 USB...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
Y:\RAID1E\RAID1EDisk1.bin		NTFS		897.75 MB
Y:\RAID1E\RAID1EDisk2.bin				897.75 MB
Y:\RAID1E\RAID1EDisk3.bin				897.75 MB
Virtual Volume sets and RAID:				
Virtual Block RAID 1		NTFS	0 Bytes	1.32 GB
Direct Volume		NTFS	0 Bytes	1.32 GB

### Parents tab

N	Device/Disk	Info/Bus	Start/Serial	Size	Offset
A	Y:\RAID1E\RAID1EDisk1.bin	NTFS		897.75 MB	0 Sectors
B	Y:\RAID1E\RAID1EDisk2.bin			897.75 MB	0 Sectors
C	Y:\RAID1E\RAID1EDisk3.bin			897.75 MB	0 Sectors

RAID Parameters

- RAID type: RAID 1E
- Block order for: Sequential
- Parity delay: Not used
- First parity: Not used
- Number of rows: 2
- Block size: 64 KB

Legends:

- Parity block
- Invalid block order
- Not ordered block
- Current sequence block
- Parity block of current sequence
- Member block of selected parity block

#### > The RAID 1E object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

#### 2.4.7.3 RAID5E


RAID 5E (where E stands for Enhanced) is a RAID 5 layout with an integrated hot-spare drive, where the spare drive is an active part of the block rotation scheme. An example of such RAID layout is in the table below:

	A	B	C	D
1	1	2	3	PD
2	5	6	PD	4
3	9	PD	7	8
4	PD	10	11	12
5	SP	SP	SP	SP

where PD and SP stand for Parity of Data and Spare Part.

## To create a RAID 5E object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A **Virtual Block RAID** object will appear in the **Drives** panel



- 2 Drag the required partitions from the **Drives** panel to the **Parents** tab

### Other ways to add objects

- Right-click the **Parents** tab and select the required partition from the shortcut menu,
- OR
- Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

- 3 Select **RAID 5E** on the **RAID** type

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the **Apply changes immediately** checkbox on the **Parents** tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 5E. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

### Object control buttons


Locate	Click this button to locate the selected object in the <b>Drives</b> panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the <b>Apply</b> button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 5E.


You also need to specify Block order for virtual RAID 5E You may select it on the Block order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but files from the RAID 5E cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 5E. Find a file and preview it. If the file appears correct, you have created a correct RAID 5E layout.



Parents tab



#### > The RAID 5E object can now be processed like regular drives/volumes

If **R-Studio** detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

#### 2.4.7.4 RAID5EE

RAID 5EE (where E stands for Enhanced) is a RAID 5 layout with an integrated hot-spare drive, where the spare drive is an active part of the block rotation scheme. An example of such RAID layout is in the table below:


	A	B	C	D
1	1	2	SP	PD
2	4	SP	PD	3

3	SP	PD	5	6
4	PD	7	8	SP

where PD and SP stand for Parity of Data and Spare Part.

### To create a RAID 5EE object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A Virtual Block RAID object will appear in the **Drives** panel



- 2 Drag the required partitions from the **Drives** panel to the **Parents** tab

#### Other ways to add objects

- Right-click the **Parents** tab and select the required partition from the shortcut menu, or
  - Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.
- 3 Select **RAID 5EE** on the **RAID** type

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the **Apply changes immediately** checkbox on the **Parents** tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 5EE. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

#### Object control buttons

Locate	Click this button to locate the selected object in the <b>Drives</b> panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID
Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the <b>Apply</b> button or immediately after loading)

The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 5EE.

You also need to specify Block order for virtual RAID 5EE. You may select it on the Block order drop-down or shortcut menu.

If those parameters are not correct, data on the parents will not be damaged, but files from the RAID 5EE cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 5EE. Find a file and preview it. If the file appears correct, you have created a correct RAID 5EE layout.

Device/Disk	Label	FS	Start	Size
TOSHIBA DT01ACA100 MS20A7...	44HSATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-450...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e6a573f2-14d5-4047...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				
WDC WD10EACS-00ZJB0 01.01B01	WD-WCASJ0409502	#0 USB ...	0 Bytes	931.51 GB
Y:	Backup II	NTFS	1 MB	931.51 GB
Y:\RAID5EE\RAID5EEDisk1.bin		NTFS		897.75 MB
Y:\RAID5EE\RAID5EEDisk2.bin		NTFS		897.75 MB
Y:\RAID5EE\RAID5EEDisk3.bin		NTFS		897.75 MB
Y:\RAID5EE\RAID5EEDisk4.bin		NTFS		897.75 MB
Virtual Volume sets and RAID5				
Virtual Block RAID 1		NTFS	0 Bytes	3.51 GB
Direct Volume		NTFS	0 Bytes	3.51 GB

### Parents tab

N	Device/Disk	Info/Bus	Start/Serial	Size	Offset
A	Y:\RAID5EE\RAID5EEDisk1.bin	NTFS		897.75 MB	0 Sectors
B	Y:\RAID5EE\RAID5EEDisk2.bin			897.75 MB	0 Sectors
C	Y:\RAID5EE\RAID5EEDisk3.bin			897.75 MB	0 Sectors
D	Y:\RAID5EE\RAID5EEDisk4.bin	NTFS		897.75 MB	0 Sectors

	A	B	C	D
1	1	2	SP	PD
2	4	SP	PD	3
3	SP	PD	5	6
4	PD	7	8	SP

RAID Parameters:

- Auto Detect
- RAID type: RAID5EE
- Block order for: Left Synchronous (Stan)
- Parity delay: Not used
- First parity: [ ]
- Number of rows: 4
- Block size: 64 KB

Legend:

- Parity block
- Invalid block order
- Not ordered block
- Current sequence block
- Parity block of current sequence
- Member block of selected parity block

#### > The RAID 5EE object can now be processed like regular drives/volumes

If R-Studio detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

#### 2.4.7.5 RAID6E


RAID 6E (where E stands for Enhanced) is a RAID 6 layout with an integrated hot-spare drive, where the spare drive is an active part of the block rotation scheme. An example of such RAID layout is in the table below:

	A	B	C	D	E	F
1	RS	1	2	3	4	PD
2	5	6	7	8	PD	RS
3	10	11	12	PD	RS	9
4	15	16	PD	RS	13	14
5	20	PD	RS	17	18	19
6	PD	RS	21	22	23	24
7	SP	SP	SP	SP	SP	SP

where RS, PD and SP stand for Reed-Solomon, Parity of Data, and Spare Part, respectively.

### To create a RAID 6E object

- 1 Click the **Create Virtual RAID** button and select **Create Virtual Block RAID & Autodetect** or select the **Create Virtual Block RAID & Autodetect** on the **Create** menu
- > A **Virtual Block RAID** object will appear in the **Drives** panel



- 2 Drag the required partitions from the **Drives** panel to the **Parents** tab

#### Other ways to add objects

- Right-click the **Parents** tab and select the required partition from the shortcut menu, or
- Right-click the partition in the **Drives** panel, select **Add to RAID** on the shortcut menu, and select the RAID object you want to add the partition to.

- 3 Select **RAID 6E** on the **RAID** type

You may either make **R-Studio** to process your changes immediately or wait until you finish editing the RAID layout. Select or clear the **Apply changes immediately** checkbox on the **Parents** tab. Click the **Apply** button to apply the changes when are you through.

**Note:** Objects should be placed in the same order as they were in the original RAID 6E. If this order is incorrect, you must change it by dragging the parents to place them in the correct order.

#### Object control buttons

Locate	Click this button to locate the selected object in the <b>Drives</b> panel.
Add Empty Space/Add Missing Drive	Click this button to add an empty space or missing drive object to the RAID




Remove	Click this button to remove the selected object from the RAID
Move Up	Click this button to move up the selected object in the RAID
Move Down	Click this button to move down the selected object in the RAID
Synchronize Offsets	Click this button to make the offsets the same for all objects in the RAID
Reset changes	Click this button to return the configuration to the initial state (after clicking the Apply button or immediately after loading)


The RAID block size and Offset (in sectors) parameters must be set the same as for the original RAID 6E. You also need to specify Block order for virtual RAID 6E. You may select it on the Block order drop-down or shortcut menu.

If the those parameters are not correct, data on the parents will not be damaged, but files from the RAID 6E cannot be recovered.

**Note:** You may check how correctly you have reconstructed the original RAID 6E. Find a file and preview it. If the file appears correct, you have created a correct RAID 6E layout.



Parents tab





> **The RAID 6E object can now be processed like regular drives/volumes**

If **R-Studio** detects a valid file system on the newly created RAID object, a [partition](#) object will appear in the Drives panel.

The [Description Files for RAID Configurations](#) topic shows the RAID description file for this RAID configuration.

You also may check the RAID consistency, if necessary. See the [Checking RAID Consistency](#) help page for details.

## 2.4.8 Finding RAID Parameters

**R-Studio** can find parameters for RAID 5 and 6. RAID parameters can be found automatically or manually.


The number of drives in the RAID should be between 3 and 32. RAID parameters can be found only when all original drives (or their images) are present. Even one substitute object in a RAID (like a missing drive) makes finding RAID parameters impossible.

### To find RAID parameters automatically,

**1 Click the Auto Detect button on the Parents tab**

> **R-Studio will start searching for the RAID parameters and show the most probable one on the RAID Parameter Detection dialog box**

#### RAID Parameter Detection dialog box



**2 Click the Apply button and R-Studio will change the RAID layout to the selected one on the Parents tab.**

**3 Click the Apply button on the Parents tab**

> **R-Studio will use the found parameters for the RAID.**


If necessary, you may return to the RAID Parameter Detection dialog box by clicking the **Choose Variants** button, and select another RAID layout.

### To find RAID parameters manually,

**1 Click the drop-down Auto Detect list on the Parents tab and select Advanced Detection.**

- Specify the necessary detection parameters on the RAID Parameter Detection dialog box and click the Start detection button

### Raid Parameters Detection dialog box



You may change the drive order, offset for drive(s), and enable/disable drives.


#### Advanced Parameters

Max offset:	The area on the drive to find RAID parameters in.
Offset search performance	Cumulative parameters that estimates the probability of certain found RAID parameters. Moving it to the right increases accuracy but slows the process. Moving it to the left reduces the accuracy but makes the process faster.
RAID layouts search performance	

You may add your own RAID offsets. Right-click empty space in the **Found offsets** pane and select **Add Custom offset** on the shortcut menu and specify the offset individually for every drive.

- Select an offset and click the Click here to find RAID Layouts button on the RAID Parameters Detection dialog box

### RAID Parameters Detection dialog box



- Select a RAID variant in the Found RAID layouts pane and click the Apply button
- Click the Apply button on the Parents tab

> **R-Studio will use the found parameters for the RAID.**

If necessary, you may return to the RAID Parameter Detection dialog box by clicking the **Choose Variants** button, and select another RAID layout.


## 2.4.9 Checking RAID Consistency

You may check RAID consistency (whether the data parity values are valid) for RAID layouts with parity blocks.

### To check RAID consistency,

- \* **Right-click the RAID and select Check RAID consistency... on the shortcut menu**
- > **The RAID consistency check window will appear showing the progress.**

RAID consistency check **window**



When the check is finished, you may inspect the results.

Block color	
Green	Data parity values are valid.
Red	Data parity values are not valid.
White	0's

When a mouse pointer hovers over a block, a tooltip will show the sector range within the block and number of consistent and inconsistent sectors. Double-clicking the block moves it to the upper-leftmost corner and zooms in the data by 2.

### RAID consistency check controls

Sectors	The number of the first sector in the row.
Offset	Offset in the data. Enter the address you want to jump to and press the <b>Enter</b> key.
Sectors/Bytes/KB...	Specifies the dimension of the data in the <b>Offset</b> field.
Previous/Next	Moves to the previous/next part of the data.
+/?	Zooms into/out of, the data.

## 2.4.10 Syntax of a Description File for RAID Configurations

You may create and store your own RAID configurations. The syntax of those files is similar to that of the XML language. They are stored in an `.xml` file specified on the [R-Studio Settings](#).

A number of file examples are shown on the [Description Files for RAID Configurations](#) topic.

There are two types of such description files: for RAID presets and custom-created RAID layouts.

**RAID preset configuration file**

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID5" rows="3" type="5" order="2"
parityDelay="1">
    <Parents>
      <Parent comp="RAID5Disk1.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="1"/>
      <Parent comp="RAID5Disk2.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="2"/>
      <Parent comp="RAID5Disk3.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="3"/>
    </Parents>
  </RAID>
</RAIDList>
```

**Custom-created RAID configuration file example**

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID6Complex" rows="6" type="256">
    <Parents>
      <Parent name="img1.bin" size="941359104" order="1"/>
      <Parent name="img2.bin" fs="NTFS" size="941359104" order="2"/>
      <Parent name="img3.bin" size="941359104" order="3"/>
      <Parent name="img4.bin" size="941359104" order="4"/>
      <Parent name="img5.bin" size="941359104" order="5"/>
    </Parents>
    <Table>
      <Block id="A1">ReedSolomon</Block>
      <Block id="B1">1</Block>
      <Block id="C1">2</Block>
      <Block id="D1">3</Block>
      <Block id="E1">XorOfData</Block>
      <Block id="A2">4</Block>
      <Block id="B2">5</Block>
      <Block id="C2">6</Block>
      <Block id="D2">XorOfData</Block>
      <Block id="E2">ReedSolomon</Block>
      <Block id="A3">8</Block>
      <Block id="B3">9</Block>
      <Block id="C3">XorOfData</Block>
      <Block id="D3">ReedSolomon</Block>
      <Block id="E3">7</Block>
      <Block id="A4">12</Block>
      <Block id="B4">XorOfData</Block>
      <Block id="C4">ReedSolomon</Block>
      <Block id="D4">10</Block>
      <Block id="E4">11</Block>
      <Block id="A5">XorOfData</Block>
      <Block id="B5">ReedSolomon</Block>
      <Block id="C5">13</Block>
      <Block id="D5">14</Block>
```

```

        <Block id="E5">15</Block>
        <Block id="A6" sequence="1">XorOfAll</Block>
        <Block id="B6" sequence="2">XorOfAll</Block>
        <Block id="C6" sequence="3">XorOfAll</Block>
        <Block id="D6" sequence="4">XorOfAll</Block>
        <Block id="E6" sequence="5">XorOfAll</Block>
    </Table>
    <Sequences>
        <Sequence id="1">A1 A2 A3 A4 A5 A6</Sequence>
        <Sequence id="2">B1 B2 B3 B4 B5 B6</Sequence>
        <Sequence id="3">C1 C2 C3 C4 C5 C6</Sequence>
        <Sequence id="4">D1 D2 D3 D4 D5 D6</Sequence>
        <Sequence id="5">E1 E2 E3 E4 E5 E6</Sequence>
    </Sequences>
</RAID>
</RAIDList>

```

### File structure

#### File header

The file starts with a standard XML header:

```
<?xml version="1.0" encoding="utf-8"?>
```

#### Section RAIDList

```
<RAIDList>
```

It can contain any number of the <RAID> sections and requires a closing element </FileTypeList>.

#### Section structure example:

```

<RAIDList>
    <RAID [attributes]>
        ...
    </RAID>
    ...
    <RAID [attributes]>
        ...
    </RAID>

```

#### Section RAID

This section describes each RAID layout.

It must contain at least one <Table> and <Parents> sections and can contain one block <Sequences>..

```

<RAIDList version="1">
    <RAID blockSize="65536" name="RAID5" rows="3" type="5" order="2"
parityDelay="1">
        <Parents>

            ...

        </Parents>
        <Table>

            ...

        </Table>
        <Sequences>

            ...

        </Sequences>
    </RAID>
</RAIDList>

```

**Attributes:**

blocksize	<u32>	Required	The block size of the RAID in bytes
name	<string>	Optional	The name of the RAID layout
rows	<u16>	Required	The number of rows in the RAID layout table.
type	<u16>	Required	The type of the RAID preset. The following types are supported: 1: RAID0 (Stripe set) 2: RAID10 3: RAID1E 4: RAID4 5: RAID5 6: RAID5E 7: RAID5EE 8: RAID6 / Reed-Solomon Encoding 9: RAID6E / Reed-Solomon Encoding 10: RAID6 / Vertical Xor Encoding 256: Custom Raid Table If the RAID type parameter contradicts to the RAID table, the RAID table always prevails.
order	<u16>	Required/Optional	The RAID sub-type. For example, order="2" means Left Asynchronous for RAID5 layouts. Any value for the custom RAID layouts will be ignored.
parityDelay	<u16>	Required	The Parity delay parameter.

**Section structure example:**

```
<RAID blockSize="65536" rows="6" type="256">
  <Parents>

  </Parents>

  <Table>

  </Table>
  <Sequences>

  </Sequences>
</RAID>
```

**Section Parents**

This section describes the RAID parents. It contains the <Parent> elements of the RAID.

**Section structure example:**

```
<Parents>
  <Parent comp="RAID5Disk1.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="1"/>
  <Parent comp="RAID5Disk2.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="2"/>
```

```

    <Parent comp="RAID5Disk3.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="3"/>
  </Parents>

```

**Element** Parent

The element specifies the parent of the RAID.

**Attributes:**

comp	<string>	Required/Optional	The file-container with the parent object.
name	<string>	Required	The object name of the RAID parent.
offset	<ul6>	Required is not 0	The offset value in bytes
size=	<ul6>	Required	The object size in bytes
order	<ul6>	Required	The order of the RAID object

**Section** Table

This section describes the RAID layout table. It contains the <Block> elements which number is a product of two attributes in the <RAID> section: <parents> x <rows>.

**Section structure example:**

```

<RAIDList>
  <RAID name="example" parents="2" rows="2" blocksize="16777216">
    <Table>
      <Block [attributes]> ... </Block>
      <Block [attributes]> ... </Block>
      <Block [attributes]> ... </Block>
      <Block [attributes]> ... </Block>
    </Table>
  </RAID>
</RAIDList>

```

**Element** Block

The element specifies the block number in the RAID layout table (a positive integer number) or an error correction block of the following types:

- PD OR ParityOfData
- PA OR ParityOfAll
- RS OR ReedSolomon
- U OR Unknown
- I OR Ignore

Any other value is treated as Unknown.

**Attributes:**

id	<string>	Required	The alpha-numerical identifier of the block in the RAID layout table. The element in the 3-rd column of the 2-nd line is designated as C2. AA is used after letter z, and so on.
sequence	<string>	Optional	The numerical identifier for non-default sequences.

## Section Sequences

This section describes the non-default data checksum sequences used to preserve data integrity. It is not necessary to explicitly list default sequences (the table rows). Sequences can contain any number of the `<Sequence>` elements.

### Section structure example:

```
<RAIDList>
  <RAID name="example" parents="4" rows="4" blocksize="16777216">
    <Parents>

    </Parents>
    <Table>
      ...
    </Table>
    <Sequences>
      <Sequence [attributes]> ... </Sequence>
      ...
      <Sequence [attributes]> ... </Sequence>
    </Sequences>
  </RAID>
</RAIDList>
```

### Element Sequence

The element contains the list of the RAID blocks belonging to that sequence. The elements are separated by a space .

#### Attributes:

id	<u16>	Required	The sequence identifier.
----	-------	----------	--------------------------

### Element example:

See the [RAID configuration file example](#).

### Comments

```
<!-- Comment string -->
```

An XML standard string for a comment.

## 2.4.11 Description Files for RAID Configurations

Below are description files for RAID examples described in the [Volume Sets and RAIDs](#) chapter. The syntax of them is described in the [Syntax of a Description File for RAID Configurations](#) topic.

### StripeSet

The stripe set layout is described in the [Volume Sets, Stripe Sets, and Mirrors](#) topic.

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="StripeSet" rows="2" type="1" order="7"
parityDelay="1">
    <Parents>
      <Parent comp="RAID0Disk1.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="1"/>
      <Parent comp="RAID0Disk2.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="2"/>
    </Parents>
  </RAID>
</RAIDList>
```



```

    </Parents>
  </RAID>
</RAIDList>

```

## Basic RAID 5

The RAID layout is described in the [Working with Basic RAID 4 and RAID 5 Operations](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID5" rows="3" type="5" order="2"
parityDelay="1">
    <Parents>
      <Parent comp="RAID5Disk1.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="1"/>
      <Parent comp="RAID5Disk2.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="2"/>
      <Parent comp="RAID5Disk3.dsk" name="Promise1+0 JBOD1.10"
size="40060321792" order="3"/>
    </Parents>
  </RAID>
</RAIDList>

```

## RAID 5 with parity delays

The RAID layout is described in the [RAID5 with Parity Delays Operations](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="16384" name="RAID5HP" rows="48" type="5" order="2"
parityDelay="16" firstParity="16">
    <Parents>
      <Parent name="RAID5HPDisk1.bin" offset="557056" size="941359104"
order="1"/>
      <Parent name="RAID5HPDisk2.bin" offset="557056" size="941359104"
order="2"/>
      <Parent name="RAID5HPDisk3.bin" offset="557056" size="941359104"
order="3"/>
    </Parents>
  </RAID>
</RAIDList>

```

## Advanced RAID 5

The RAID layout is described in the [Working with Advanced RAID Layouts](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="4096" name="RAID5Complex" rows="9" type="256">
    <Parents>
      <Parent name="RAID5CDisk1.bin" offset="16777216" size="941359104"
order="1"/>
      <Parent name="RAID5CDisk2.bin" offset="16777216" size="941359104"
order="2"/>
      <Parent name="RAID5CDisk3.bin" offset="16777216" size="941359104"
order="3"/>
    </Parents>
    <Table>
      <Block id="A1">XorOfData</Block>
      <Block id="B1">1</Block>
    </Table>
  </RAID>
</RAIDList>

```

```

    <Block id="C1">2</Block>
    <Block id="A2">XorOfData</Block>
    <Block id="B2">3</Block>
    <Block id="C2">4</Block>
    <Block id="A3">XorOfData</Block>
    <Block id="B3">5</Block>
    <Block id="C3">6</Block>
    <Block id="A4">7</Block>
    <Block id="B4">XorOfData</Block>
    <Block id="C4">8</Block>
    <Block id="A5">9</Block>
    <Block id="B5">XorOfData</Block>
    <Block id="C5">10</Block>
    <Block id="A6">11</Block>
    <Block id="B6">XorOfData</Block>
    <Block id="C6">12</Block>
    <Block id="A7">13</Block>
    <Block id="B7">14</Block>
    <Block id="C7">XorOfData</Block>
    <Block id="A8">15</Block>
    <Block id="B8">16</Block>
    <Block id="C8">XorOfData</Block>
    <Block id="A9">17</Block>
    <Block id="B9">18</Block>
    <Block id="C9">XorOfData</Block>
  </Table>
</RAID>
</RAIDList>

```

## Advanced RAID 5

The RAID layout is described in the [Working with Advanced RAID Layouts](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="524288" name="RAID_MacPro" rows="3" type="256">
    <Parents>
      <Parent name="RAID_MAC_ProDisk1.bin" fs="NTFS" offset="16777216"
size="941359104" order="1"/>
      <Parent name="RAID_MAC_ProDisk2.bin" offset="16777216" size="941359104"
order="2"/>
      <Parent name="RAID_MAC_ProDisk3.bin" offset="16777216" size="941359104"
order="3"/>
      <Parent name="RAID_MAC_ProDisk4.bin" offset="16777216" size="941359104"
order="4"/>
    </Parents>
    <Table>
      <Block id="A1" sequence="1">XorOfData</Block>
      <Block id="B1">1</Block>
      <Block id="C1">2</Block>
      <Block id="D1" sequence="2">XorOfData</Block>
      <Block id="A2">3</Block>
      <Block id="B2">4</Block>
      <Block id="C2" sequence="3">XorOfData</Block>
      <Block id="D2">5</Block>
    </Table>
  </RAID>
</RAIDList>

```

```

        <Block id="A3">6</Block>
        <Block id="B3" sequence="4">XorOfData</Block>
        <Block id="C3">7</Block>
        <Block id="D3">8</Block>
    </Table>
    <Sequences>
        <Sequence id="1">A1 B1 C1</Sequence>
        <Sequence id="2">D1 A2 B2</Sequence>
        <Sequence id="3">C2 D2 A3</Sequence>
        <Sequence id="4">B3 C3 D3</Sequence>
    </Sequences>
</RAID>
</RAIDList>

```

### RAID 6 Reed-Solomon (Left Synchronous (Standard)) Preset

The RAID layout is described in the [Working with RAID 6 Presets](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
    <RAID blockSize="65536" name="RAID6RS" rows="5" type="8" order="1"
parityDelay="1">
        <Parents>
            <Parent name="img1.bin" size="941359104" order="1"/>
            <Parent name="img2.bin" fs="NTFS" size="941359104" order="2"/>
            <Parent name="img3.bin" size="941359104" order="3"/>
            <Parent name="img4.bin" size="941359104" order="4"/>
            <Parent name="img5.bin" size="941359104" order="5"/>
        </Parents>
    </RAID>
</RAIDList>

```

### RAID6 (Double Xor) Preset

The RAID layout is described in the [Working with RAID 6 Presets](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
    <RAID blockSize="65536" name="RAID62X" rows="4" type="10" order="1"
parityDelay="1">
        <Parents>
            <Parent name="RAID62X1.bin" fs="NTFS" size="941359104" order="1"/>
            <Parent name="RAID62X2.bin" size="941359104" order="2"/>
            <Parent name="RAID62X3.bin" size="941359104" order="3"/>
            <Parent name="RAID62X4.bin" size="941359104" order="4"/>
            <Parent name="RAID62X5.bin" size="941359104" order="5"/>
            <Parent name="RAID62X6.bin" size="941359104" order="6"/>
        </Parents>
    </RAID>
</RAIDList>

```

### Advanced RAID 6

The RAID layout is described in the [Working with Advanced RAID Layouts](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
    <RAID blockSize="65536" name="RAID6Complex" rows="6" type="256">
        <Parents>
            <Parent name="img1.bin" size="941359104" order="1"/>

```

```

    <Parent name="img2.bin" fs="NTFS" size="941359104" order="2"/>
    <Parent name="img3.bin" size="941359104" order="3"/>
    <Parent name="img4.bin" size="941359104" order="4"/>
    <Parent name="img5.bin" size="941359104" order="5"/>
</Parents>
<Table>
  <Block id="A1">ReedSolomon</Block>
  <Block id="B1">1</Block>
  <Block id="C1">2</Block>
  <Block id="D1">3</Block>
  <Block id="E1">XorOfData</Block>
  <Block id="A2">4</Block>
  <Block id="B2">5</Block>
  <Block id="C2">6</Block>
  <Block id="D2">XorOfData</Block>
  <Block id="E2">ReedSolomon</Block>
  <Block id="A3">8</Block>
  <Block id="B3">9</Block>
  <Block id="C3">XorOfData</Block>
  <Block id="D3">ReedSolomon</Block>
  <Block id="E3">7</Block>
  <Block id="A4">12</Block>
  <Block id="B4">XorOfData</Block>
  <Block id="C4">ReedSolomon</Block>
  <Block id="D4">10</Block>
  <Block id="E4">11</Block>
  <Block id="A5">XorOfData</Block>
  <Block id="B5">ReedSolomon</Block>
  <Block id="C5">13</Block>
  <Block id="D5">14</Block>
  <Block id="E5">15</Block>
  <Block id="A6" sequence="1">XorOfAll</Block>
  <Block id="B6" sequence="2">XorOfAll</Block>
  <Block id="C6" sequence="3">XorOfAll</Block>
  <Block id="D6" sequence="4">XorOfAll</Block>
  <Block id="E6" sequence="5">XorOfAll</Block>
</Table>
<Sequences>
  <Sequence id="1">A1 A2 A3 A4 A5 A6</Sequence>
  <Sequence id="2">B1 B2 B3 B4 B5 B6</Sequence>
  <Sequence id="3">C1 C2 C3 C4 C5 C6</Sequence>
  <Sequence id="4">D1 D2 D3 D4 D5 D6</Sequence>
  <Sequence id="5">E1 E2 E3 E4 E5 E6</Sequence>
</Sequences>
</RAID>
</RAIDList>

```

## RAID10 (1+0)

The RAID layout is described in the [RAID10 \(1+0\)](#) topic.

```

<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID10" rows="1" type="2" order="7"
parityDelay="1">

```

```
<Parents>
  <Parent name="RAID10-1.bin" size="941359104" order="1"/>
  <Parent name="RAID10-2.bin" size="941359104" order="2"/>
  <Parent name="RAID10-3.bin" size="941359104" order="3"/>
  <Parent name="RAID10-4.bin" size="941359104" order="4"/>
</Parents>
</RAID>
</RAIDList>
```

## RAID1E

The RAID layout is described in the [RAID1E](#) topic.

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID1E" rows="2" type="3" order="1"
parityDelay="1">
  <Parents>
    <Parent name="RAID1EDisk1.bin" fs="NTFS" size="941359104" order="1"/>
    <Parent name="RAID1EDisk2.bin" size="941359104" order="2"/>
    <Parent name="RAID1EDisk3.bin" size="941359104" order="3"/>
  </Parents>
</RAID>
</RAIDList>
```

## RAID5E

The RAID layout is described in the [RAID5E](#) topic.

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID5E" rows="5" type="6" order="1"
parityDelay="1">
  <Parents>
    <Parent name="RAID5EDisk1.bin" fs="NTFS" size="941359104" order="1"/>
    <Parent name="RAID5EDisk2.bin" size="941359104" order="2"/>
    <Parent name="RAID5EDisk3.bin" size="941359104" order="3"/>
    <Parent name="RAID5EDisk4.bin" size="941359104" order="4"/>
  </Parents>
</RAID>
</RAIDList>
```

## RAID5EE

The RAID layout is described in the [RAID5EE](#) topic.

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID5EE" rows="4" type="7" order="1"
parityDelay="1">
  <Parents>
    <Parent name="RAID5EEDisk1.bin" fs="NTFS" size="941359104" order="1"/>
    <Parent name="RAID5EEDisk2.bin" size="941359104" order="2"/>
    <Parent name="RAID5EEDisk3.bin" size="941359104" order="3"/>
    <Parent name="RAID5EEDisk4.bin" fs="NTFS" size="941359104" order="4"/>
  </Parents>
</RAID>
</RAIDList>
```

## RAID6E

The RAID layout is described in the [RAID6E](#) topic.

```
<?xml version="1.0" encoding="UTF-8"?>
<RAIDList version="1">
  <RAID blockSize="65536" name="RAID6E" rows="7" type="9" order="1"
parityDelay="1">
  <Parents>
    <Parent name="RAID6E1.bin" size="941359104" order="1"/>
    <Parent name="RAID6E2.bin" fs="NTFS" size="941359104" order="2"/>
    <Parent name="RAID6E3.bin" size="941359104" order="3"/>
    <Parent name="RAID6E4.bin" size="941359104" order="4"/>
    <Parent name="RAID6E5.bin" size="941359104" order="5"/>
    <Parent name="RAID6E6.bin" size="941359104" order="6"/>
  </Parents>
</RAID>
</RAIDList>
```

### 2.4.12 Various Disk and Volume Managers

**R-Studio** can work with objects created by various disk and volume managers. Currently, the following managers are supported:

- [BitLocker Drive Encryption](#)
- [Windows Dynamic Disks](#)
- [Windows Storage Spaces](#)
- [Apple RAIDs](#)
- [Apple CoreStorage/File Vault/Fusion Drive Volumes](#)
- [Linux mdadm RAIDs](#)
- [Linux Logical Volume Manager \(LVM and LVM2\)](#)

**R-Studio** can automatically recognize and add their physical components, component images, or the user can manually add the components when their data is damaged so severely that **R-Studio** cannot recognize them.

In addition, **R-Studio** can work with various [virtual disk and disk image formats](#).

#### 2.4.12.1 BitLocker Drive Encryption

**BitLocker Drive Encryption**, or **BitLocker**, is a data protection feature introduced by Microsoft since Windows Vista. It implements some hard/software measures to encrypt either USB external flash drives or internal system SSD/HDD devices. You may read more about **BitLocker Drive Encryption** on the [Microsoft site](#) or [Wikipedia](#).

There are following encryption methods (protectors in the Microsoft terms) that can be utilized in the **BitLocker** protection:

- A [TPM/TPM+PIN](#) chip
- A USB key (a flash drive containing a .bek file)
- A user's password (not to confuse with a user's logon password) / recovery key

These methods can be used either individually or as a combination thereof. If they are used as a combination, knowing the decryption information for only one method is enough to unlock the device.

R-Studio can unlock devices encrypted with **BitLocker** provided that all the necessary information is known.


### BitLocker ToGo

This is the method used to lock external removable devices. The password or a recovery key is necessary to know to unlock the device. A recovery key may be in the printed form or contained in a file. A name of such a file has the following pattern: BitLocker Recovery Key 600397A9-48AA-4DE4-B775-C71EB130EA1B.txt, where the last characters is the **BitLocker** volume identifier. That file contains the **BitLocker** volume identifier and a recovery key.

To unlock a BitLocker ToGo device,


- 1 Locate the device and double-click the BitLocker partition.

#### BitLocker ToGo




- 2 Enter the password or recovery key and click the Unlock button.

#### BitLocker ToGo



- > R-Studio will unlock the volume

## BitLocker ToGo



## BitLocker System Drive Encryption

This is the method used to lock internal system drives.


Depending on what methods are used, the following information is necessary to know to unlock the drive.

- A recovery key in the printed form or in a file. A name of such a file has the following pattern: BitLocker Recovery Key FDA7B96C-635E-45AA-BE63-00C3DB3771EE.txt , where the last characters is the **BitLocker** volume identifier. That file contains the **BitLocker** volume identifier and a recovery key.
- A password used to start the preboot process. It shouldn't be confused with the password for the user's logon.
- An external USB flash drive containing its .bek file. Note that Windows sets System and Hidden attributes for such files and Windows doesn't show such files by default.

To unlock a system drive with a BitLocker partition,

- 1 Locate the device and double-click the BitLocker partition.


## BitLocker System Drive Encryption



- 2 Enter the password or recovery key and click the Unlock button.




## BitLocker System Drive Encryption



If you have the .bek file, click the **Unlock by key file** button and load the file.

### > R-Studio will unlock the volume

## BitLocker System Drive Encryption




## TPM/TPM+PIN modes

Only in registered **R-Studio Technician/T80+** versions.

If only the TPM/TPM+PIN hardware was used to encrypt the partition, you must have either the FVEK (Full Volume Encryption Key) or VMK (Volume Master Key) data. Obtaining these keys is a very hard task, only quite advanced forensic professionals can do that using specialized hardware. Sometimes it may be possible to extract a FVEK from memory dumps and/or hibernation files, but this is still not a trivial process.

If you have FVEK or VMK data, click the **Advanced** button, select the key type of the data, enter the key or load a file with the key.

## BitLocker TPM/TPM+PIN modes




**R-Studio** will unlock the volume.

You may also save and load encryption information from a BitLocker Encryption volume.

### 2.4.12.2 Windows Dynamic Disks


**R-Studio** supports [dynamic disks](#), including [Windows software RAID5](#), mirrors, and spanned volumes. When **R-Studio** detects components from such dynamic disks, it assembles them accordingly.

#### Windows dynamic disks (RAID5)



**R-Studio** detects components from dynamic disks and creates those dynamic disks automatically. At the same time, **R-Studio** gives access to the parents of the dynamic disks (drives and images).

## Windows dynamic disks (RAID5) in R-Studio




If recognized parents of a dynamic disk, including drive images, are added to **R-Studio** later, it automatically adds them to their respective dynamic disk.

When an automatically created dynamic disk is selected, **R-Studio** highlights its components.


Also, **R-Studio** automatically detects inconsistent components of dynamic disks and marks them accordingly.

## Windows dynamic disks (RAID5) with unsynced parent




**R-Studio** shows the components of the selected dynamic disk on its LDM Components tab.

## LDM Components tab




**R-Studio** shows broken dynamic disks in pink.

## Broken dynamic disks in R-Studio



The LDM Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken dynamic disk. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the dynamic disk in blue.


## Adding a component manually



You may immediately switch to the dynamic disk configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows dynamic disks with manually added components in blue:

## Dynamic disks with added components in R-Studio



### 2.4.12.3 Windows Storage Spaces


[Storage pools and spaces](#) is a new storage technology, first introduced in Windows 8 and Windows Server 2012, that allows the user to combine various (not always similar) drives into a kind of a RAID or compound

volume. First, the drives are combined into a storage pool, then several storage spaces with striping (similar to RAID0), mirroring (similar to RAID1), and parity (similar to RAID5) can be created in that storage pool. You may read more about storage pools and spaces in the Microsoft's [Storage Spaces: FAQ](#).

**R-Studio** supports Windows Storage Spaces created by Windows 8/8.1 and Windows 10/Threshold 2/ Anniversary/Fall Creators updates.


When drives from a storage pool are connected to a Windows computer, it automatically detects them and assembles storage spaces accordingly.

### Storage spaces




Storage pools and spaces can be managed using the **Storage Spaces** item in the **Control Panel**.

### Storage spaces



**R-Studio** detects drives (or their images) from storage pools and creates storage pools and spaces automatically. At the same time, **R-Studio** gives access to the parents of the storage spaces (drives and images).

## Storage spaces in R-Studio




If recognized parents of a storage space, including drive images, are added to **R-Studio** later, it automatically adds them to their respective storage space.

When an automatically created storage space is selected, **R-Studio** highlights its components. It also highlights the storage space that Windows may itself create from the same components.

**R-Studio** shows the components of the selected storage space on its WSS Components tab.

### WSS Components tab



**R-Studio** shows broken storage spaces in pink.




## Broken storage spaces in R-Studio

Device/Disk	Label	FS	Start	Size
<b>Local Computer</b>				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-4184-a4d5-...}		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44fd3858-351c-43f0-8439-1e...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-adfc-3e...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space24			931.51 GB	1.69 MB
<b>Muft Storage Space 0.1</b>				
HarddiskVolume21	{f6b5bd51-e549-4426-...}	#4 Local ...	1 MB	128 MB
E:	Test_WSS	NTFS	129 MB	55.87 GB
<b>SanDisk Extreme 0001</b>				
Storage pool	0432b0f5	#1 USB (...)	0 Bytes	29.22 GB
Microsoft reserved partition			129 MB	29.10 GB
Microsoft reserved partition			17 KB	128 MB
<b>SanDisk Extreme 0001</b>				
Storage pool	046be964	#2 USB (...)	0 Bytes	29.22 GB
Microsoft reserved partition			129 MB	29.10 GB
Microsoft reserved partition			17 KB	128 MB
<b>Virtual Volume sets and RAID's</b>				
Storage space				56 GB
System Reserved Partition			1 MB	128 MB
GPTPart1	Test_WSS	NTFS	129 MB	55.87 GB

The WSS Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken storage space. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the storage space in blue.

## Adding a component manually



You may immediately switch to the storage space configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows storage spaces with manually added components in blue:


## Storage spaces with added parents in R-Studio

Device/Disk	Label	FS	Start	Size
<b>Local Computer</b>				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-4184-a4d5-...}		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44fd3858-351c-43f0-8439-1e...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-adfc-3e...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space17			931.51 GB	1.69 MB
<b>Muft Storage Space 0.1</b>				
HarddiskVolume11	{f6b5bd51-e549-4426-...}	#4 Local ...	1 MB	128 MB
Volume{06902862-d693-11e6-bf7e-...}	Test_WSS	NTFS	129 MB	55.87 GB
<b>Image</b>				
SanDisk Extreme 0001	046be964	#1 USB (...)	0 Bytes	29.22 GB
Microsoft reserved partition			17 KB	128 MB
Storage pool			129 MB	29.10 GB
<b>SanDisk Extreme 0001</b>				
Storage pool	046be964	#2 USB (...)	0 Bytes	29.22 GB
Storage pool			129 MB	29.10 GB
Microsoft reserved partition			17 KB	128 MB
<b>SanDisk Extreme 0001</b>				
Storage pool	0432b0f5	#3 USB (...)	0 Bytes	29.22 GB
Storage pool			129 MB	29.10 GB
Microsoft reserved partition			17 KB	128 MB
<b>Virtual Volume sets and RAID's</b>				
Storage space				56 GB
System Reserved Partition			1 MB	128 MB
GPTPart1	Test_WSS	NTFS	129 MB	55.87 GB

### 2.4.12.4 Apple RAID's

OS X can create several software RAID's from drives connected to a Mac computer: RAID1 (Mirror set), RAID0 (Stripe set), and Concatenated disk set.

## Apple RAID0 example



**R-Studio** detects components of Apple RAID sets and creates their virtual RAIDs automatically. At the same time, **R-Studio** gives access to the individual components of the Apple RAID sets (drives and images).

## Apple RAID0 in R-Studio

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 M520A750	44HSATLKS	#0 SATA...	0 Bytes	931.51 GB
Volume3302cc57-3e4d-4507-872f-...	Recovery	NTFS	1 MB	300 MB
Volumeedb1042b-3073-4194-a4d5-...		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume44f43858-351c-4390-8439-1...		NTFS	292.09 GB	450 MB
Volumee0a579f2-1445-4047-adfc-3...				400 MB
D:	Data	Apple RAID components		4 GB
Empty Space25			931.51 GB	1.69 MB
UFD 2.0Silicon-PowerAG 1100	AA00000000000485	#1 USB (...)	0 Bytes	3.75 GB
Volume925190b2-d68b-11e6-bf7e-...		FAT32	20 KB	200 MB
Raid Partition 2			200.02 MB	3.43 GB
F:	Boot OS X	HFS+	3.63 GB	128 MB
UFD 2.0Silicon-PowerAG 1100	AA00000000000485	#2 USB (...)	0 Bytes	3.75 GB
Volume9251907a-d68b-11e6-bf7e-...		FAT32	20 KB	200 MB
Raid Partition 1			200.02 MB	3.43 GB
H:	Boot OS X	HFS+	Apple RAID	128 MB
Virtual Volume sets and RAID:				
Test Mac RAID 0	Test Mac RAID 0	HFS+		6.86 GB


If recognized components of an Apple RAID, including drive images, are added to **R-Studio** later, it automatically adds them to their respective Apple RAID.

When an automatically created Apple RAID is selected, **R-Studio** highlights its components.

**R-Studio** shows the components of the Apple RAID on its MacOS Components tab.




## MacOS Components tab




R-Studio shows broken Apple RAID's in pink.

## Broken Apple RAID's in R-Studio



The MacOS Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken Apple RAID. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the Apple RAID in blue.

## Adding a component manually



You may immediately switch to the Apple RAID configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows Apple RAID's with manually added components in blue:

## Apple RAID0s with added components in R-Studio

Device/Disk	Label	FS	Start	Size
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-4184-ad45-...}		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44f43858-351c-43f0-8439-1...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-adfc-3...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			1.69 MB	1.69 MB
Image				
UFD 2.0Silicon-PowerAG 1100	AA0000000000485	#2 USB L...	0 Bytes	3.75 GB
EFI System Partition		FAT32	20 KB	200 MB
Raid Partition 2			200.02 MB	3.43 GB
Booter	Boot OS X	HFS+	3.63 GB	128 MB
UFD 2.0Silicon-PowerAG 1100	AA0000000000485	#1 USB L...	0 Bytes	3.75 GB
Volume{9251907a-d68b-11e6-bf7e-...}		FAT32	20 KB	200 MB
Raid Partition 1				Apple RAID0 with a manually added component
H:	Boot US X	HFS+	3.63 GB	128 MB

### 2.4.12.5 Apple CoreStorage/FileVault/Fusion Drive Volumes

The macOS operating system has the following disk management systems:

[FileVault](#), is a disk encrypted utility;

[Fusion Drive](#) is an Apple's hybrid drive technology;

[CoreStorage](#) is a logical volume management system.

**R-Studio** supports all these technologies and can unlock their encrypted volumes (drives and images) using either their passwords or recovery keys.

## CoreStorage/FileVault

### Locked CoreStorage Volume in R-Studio

Device/Disk	Label	FS	Start	Size
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-6ad5e...}	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44f43858-351c-43f0-8439-1a637...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-adfc-387ed...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space17			1.69 MB	1.69 MB
Image: C:/Containers/Apple_Core_Storage...				
Data				Locked CoreStorage Volume
SanDisk Extreme 0001	04f18af5a	#3 USB ...	0 Bytes	59.63 GB
EFI System Partition		FAT32	20 KB	200 MB
CoreStorage Protective Partition			200.02 MB	59.31 GB
Booter	Boot OS X	HFS+	59.50 GB	128 MB


## To unlock the volume

1. Right-click the encrypted volume and select **Unlock encrypted drive** on the shortcut menu.
2. Enter the password/recovery key on the **Unlock encrypted drive** dialog box



## > R-Studio will unlock the volume

### Unlocked CoreStorage Volume in R-Studio



If the volume is partially encrypted, **R-Studio** can recognize which part is encrypted and which isn't. It will provide a correct access to the unencrypted and encrypted parts of the volume, provided that the correct password is entered.

### Partially encrypted volume



## R-Studio Technician/T80+

In addition to the password, it's possible to enter other decryption data. Click the **Advanced...** button and enter available data.

### Unlock encrypted drive: Advanced



This data is usually very hard to obtain and only very advanced institutions can recover it from actual hardware.


### Data recovery from deleted or damaged APFS volumes

**Note:** this method doesn't always yields positive results.

When macOS deletes an APFS volumes, it also wipes out all decryption information from its APFS container. In this case even knowing the password won't help. Still, there's a trick that may help to open a deleted or damaged encrypted volume.


Let's us have a hard drive with an APFS container with 3 APFS volumes:

### APFS container and its volumes



One of them has been deleted and **R-Studio** cannot unlock (decrypt) it:


### APFS container with a deleted APFS volume



But if we have an image of the disk's previous state, we can extract the necessary encryption information from that image.

Load the image and double-click the existing volume. Click the **Advanced...** button instead of entering its password.


## Export of encryption information



Click the **Export crypto context...** button and save a file with this information. Then click the **Close Image** button to unload the image.


Then double-click the APFS-1 volume and click the **Advanced** button.

## APFS container with a deleted APFS volume



Click the **Load and apply crypto context...** button


## Loading the encryption information



and load the file generated from the image.

Select the required information type (a password for our case), enter the data, and click the **Unlock** button.

## Unlocking the APFS volume




Note that the password will be explicitly shown.

**R-Studio** will open files on the volume.




## Files opened on the deleted APFS volume



## Apple Fusion Drive

**R-Studio** detects components of Apple Fusion Drive and creates virtual Fusion Drives automatically. At the same time, **R-Studio** gives access to the individual components of the Fusion Drives (drives and images).


### Fusion Drive in R-Studio



When an automatically created Fusion Drive is selected, **R-Studio** highlights its components.

**R-Studio** shows the components of the Fusion Drive on its APFS Fusion Components tab.

### Fusion Drive Components tab



**R-Studio** shows broken Fusion Drive s in pink.

## Broken Fusion Drive in R-Studio

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A...	44H5ATLKS	#0 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-45...	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-41...		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44fd3858-351c-43f...		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-40...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space25			931.51 GB	1.69 MB
HGST HTS721010A9E630 JB00...	JR10206P1WPS0F	#1 SAT...	0 Bytes	931.51 GB
Volume{7b838964-3992-4d...		FAT32	20 KB	200 MB
Data	Data	HFSX	200.02 MB	931.19 GB
Empty Space28			931.39 GB	128.00 MB
M4-CT256M4SSD2 0009	000000001112030...	#2 SAT...	0 Bytes	238.47 GB
Volume{523cd3cd-4364-4d...		FAT32	20 KB	200 MB
HarddiskVolume11			201 MB	238.28 GB
Virtual Volume sets and RAID's				
APFS Fusion Container				238.28 GB
APFS_Fusion_Test	APFS_Fusion_Test	APFS	0 Bytes	703.85 GB

Broken Fusion Drive

The Fusion Drive Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken Fusion Drive. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the Fusion Drive in blue.

## Adding a component manually

Disk 0:	APFS Container (M4-CT256M4SSD2 0009 - 000000001112030...)	Disconnect
Size:	238.28 GB	
Drive Name:	APFS Container	
Located On:	M4-CT256M4SSD2 0009	
Serial:	000000001112030#546	
APFS Fusion Host Disk GUID:	79bb3679-f3f9-4b76-8d90-95fc5ee4c54	
Missing disk 1:	[Choose correspondent disk]	Disconnect
Drive Name:	TOSHIBA DT01ACA100 MS20A750 (44H5ATLKS) - 931.51 GB	
APFS Fusion Host Disk GUID:	TOSHIBA DT01ACA100 MS20A750 (44H5ATLKS) - 931.51 GB	
Reassemble		

You may immediately switch to the Fusion Drive configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows Fusion Drive with manually added components in blue:

## Fusion Drive with added members in R-Studio

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A...	44H5ATLKS	#0 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-45...	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-41...		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44fd3858-351c-43f...		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-40...		NTFS	292.53 GB	450 MB
D:	Manually added Fusion Drive component			638.54 GB
Empty Space25			931.51 GB	1.69 MB
HGST HTS721010A9E630 JB00...	JR10206P1WPS0F	#1 SAT...	0 Bytes	931.51 GB
Volume{7b838964-3992-4d...		FAT32	20 KB	200 MB
Data	Data	HFSX	200.02 MB	931.19 GB
APFS Fusion-VirtualPv-75b...			201 MB	931.32 GB
Empty Space28			931.39 GB	128.00 MB
M4-CT256M4SSD2 0009	000000001112030...	#2 SAT...	0 Bytes	238.47 GB
Volume{523cd3cd-4364-4d...		FAT32	20 KB	200 MB
HarddiskVolume11			201 MB	238.28 GB
Virtual Volume sets and RAID's				
APFS Fusion Container				1.14 TB
APFS_Fusion_Test	APFS_Fusion_Test	APFS	0 Bytes	703.85 GB

Fusion Drive with manually added components




### 2.4.12.6 Linux mdadm RAID5

[mdadm](#) is a Linux utility used to manage and monitor software RAID devices.


**R-Studio** supports such devices and when drives from a mdadm RAID are connected to a Windows computer, it automatically detects them and assembles mdadm RAID5s accordingly.

#### Linux mdadm RAID5



**R-Studio** detects components from mdadm RAID5s and creates those RAID5s automatically. At the same time, **R-Studio** gives access to the components of those RAID5s (drives and images).

#### mdadm RAID5s in R-Studio




If recognized components of a mdadm RAID5, including drive images, are added to **R-Studio** later, it automatically adds them to their respective mdadm RAID5.

When an automatically created mdadm RAID5 is selected, **R-Studio** highlights its components.


**R-Studio** shows the components of the mdadm RAID5s on its mdadm Components tab.

## mdadm Components tab




**R-Studio** shows broken mdadm RAID's in pink.

## Broken mdadm RAID's in R-Studio



The mdadm Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken mdadm RAID. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the mdadm RAID in blue.


## Adding a component manually



You may immediately switch to the mdadm RAID configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows mdadm RAID's with manually added components in blue:


## mdadm RAID with added components in R-Studio



### 2.4.12.7 Linux LVM/LVM2


Linux LVM is a logical volume manager for the Linux OS that manages drives and other data storage devices. Using it, It is possible to create single logical volumes on several physical drives, add and replace them in a running system, resize logical volumes, create various RAID configuration, and so on. You may read more about Linux LVM in our article: [What is Logical Volume Manager \(LVM\)](#).

### LVM volume example



**R-Studio** detects drives from LVMs and creates their virtual volumes automatically. At the same time, **R-Studio** gives access to the components of the virtual LVM volumes (drives and images).

### LVM Volumes in R-Studio




If recognized components of an LVM volume, including drive images, are added to **R-Studio** later, it automatically adds them to their respective LVM volume.

When an automatically created LVM volume is selected, **R-Studio** highlights its components.


**R-Studio** shows the components of the LVM volume on its LVM Components tab.

LVM Components **tab**




**R-Studio** shows broken virtual LVM volumes in pink.

Broken LVM volumes in R-Studio



The LVM Components tab also allows you to manually disconnect or connect the components, for example, if they are such damaged that **R-Studio** cannot recognize them as parts of a broken LVM volume. Select the object from the drop-down box and click the **Connect** button. **R-Studio** displays the objects it recognizes as the components of the LVM volume in blue.

Adding a component manually



You may immediately switch to the LVM volume configuration that **R-Studio** believes most probable by clicking the **Reassemble** button.

**R-Studio** shows virtual LVM volumes with manually added components in blue:

## LVM volumes with added components in R-Studio

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-...}	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-4184-a4d5-...}		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.57 GB
Volume{44d3858-351c-43f0-8439-1...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-edfc-3...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space21			931.51 GB	1.69 MB
Image				
UFD 2.0Silicon-PowerAG 1100	AA00000000000485	#1 USB (...)	0 Bytes	3.75 GB
Partition1			1 MB	3.75 GB
UFD 2.0Silicon-PowerAG 1100	AA00000000000485	#1 USB (...)	0 Bytes	3.75 GB
F:				
Virtual Volume sets and RAIDS				
LVM_Test-LVM_Test_Vol	Ext4			7.49 GB

### 2.4.13 Mounting Virtual Objects in the System as Virtual Drives

#### Technician/T80+ version only.


Virtual objects created in the Device view pane of **R-Studio** can be mounted in the system as read-only virtual drives. Such virtual drives become accessible to the system and to other programs. Moreover, such virtual drives remain mounted after **R-Studio** has been closed.

#### To mount a virtual object as a read-only virtual drive in the system

##### 1 Right-click the virtual object and select Mount on the shortcut menu

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-4507-872f-6ad5-...}	Recovery	NTFS	1 MB	300 MB
Volume{edb1043b-3073-4184-a4d5-d22-...}		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	291.06 GB
Volume{2f380b2f-7551-482b-b096-2089-...}		NTFS	291.58 GB	524 MB
Empty Space22			292.09 GB	1 MB
Volume{44d3858-351c-43f0-8439-1a537-...}		NTFS	292.09 GB	450 MB
Volume{e0a573f2-14d5-4047-edfc-387e-...}		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space23			931.51 GB	1.69 MB
WDC WD10EADS-00L5B1 01.01A01	WD-WCAU4D920178	#1 SATA2...	0 Bytes	931.51 GB
E:	Backup II	NTFS	1 MB	931.51 GB
Image Files				
E:/RAIDS/RAIDS-byte/Disk1.dsk				37.31 GB
Empty Space27			512 Bytes	37.31 GB
DeletedPart1		NTFS	31.50 KB	9.77 GB
E:/RAIDS/RAIDS-byte/Disk2.dsk				37.31 GB
E:/RAIDS/RAIDS-byte/Disk3.dsk				37.31 GB
Empty Space32			512 Bytes	37.31 GB
DeletedPart1		NTFS	31.50 KB	9.77 GB
Empty Space31			50 KB	37.31 GB
Virtual Volume sets and RAIDS				
Virtual Block RAID 1			0 Bytes	74.62 GB
Empty Space40			512 Bytes	7.84 MB
DeletedPart1		NTFS	31.50 KB	9.77 GB
Partition1	RAID5	NTFS	7.88 MB	74.49 GB
Empty Space41			74.50 GB	123.78 MB

##### 2 Select the mount type on the Mount as a virtual drive dialog box and click the OK button.



#### Mount options

Mount as:

**Physical drive:** The virtual drive will be mounted as a read-only virtual physical drive. Windows will search for [partitions](#) on it, and if it finds any with supported file systems, it will assign disk letters to them. Recommended if the drive should be accessible to the host Windows and other programs in the system. If the data on

	<p>the drive is severely damaged, it may slow down, lock, or even crash the host Windows.</p> <p><b>Partition:</b> The virtual drive will be mounted as a read-only partition with a virtual partition table created by <b>R-Studio</b>. Recommended if the drive should be accessible only to another data recovery program.</p>
Drive letter	<p>Select the disk letter for the virtual drive if the virtual drive is mounted as a partition. The letter may be assigned automatically by the system, specified manually, or the virtual drive may have no letter at all. The latter is recommended if you don't want Windows to analyze the data on the drive.</p>

> A read-only virtual drive will appear in the Drives panel

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#0 SATA2 ...	0 Bytes	931.51 GB
Volume3303c57-3e4d-4507-872f-6ad5	Recovery	NTFS	1 MB	300 MB
Volumee0b1043b-3073-4184-a4d5-d22		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:				
Volume2f380b2f-7551-482b-b096-2089	System	NTFS	529 MB	291.06 GB
Empty Space22		NTFS	291.58 GB	524 MB
Volume44fd3858-351c-4310-8439-1a637e		NTFS	292.09 GB	1 MB
Volumee0a573f2-14d5-4047-adfc-387e		NTFS	292.53 GB	450 MB
D:				
Empty Space23		NTFS	292.97 GB	638.54 GB
WDC WD10EADS-00L5B1 01.01A01				
Connected virtual drive				
E:	Backup II	NTFS	1 MB	931.51 GB
R-IT Disk Image V1.0 (virtual)	000RITZ	#2 Local C...	0 Bytes	74.62 GB
Empty Space45			512 Bytes	7.84 MB
DeletedPart1		NTFS	31.50 KB	9.77 GB
F:				
Empty Space46		RAID5	7.88 MB	74.49 GB
Image Files				
E:\RAID5\RAID5-byte\Disk1.dsk				37.31 GB
Empty Space27			512 Bytes	37.31 GB
DeletedPart1		NTFS	31.50 KB	9.77 GB
E:\RAID5\RAID5-byte\Disk2.dsk				37.31 GB
E:\RAID5\RAID5-byte\Disk3.dsk				37.31 GB
Empty Space32			512 Bytes	37.31 GB
DeletedPart1		NTFS	31.50 KB	9.77 GB
Empty Space31			31.50 KB	37.31 GB
Virtual Volume-sets and RAID5				
Virtual Block RAID 1			0 Bytes	74.62 GB
Empty Space40			512 Bytes	7.84 MB
DeletedPart1		NTFS	31.50 KB	9.77 GB
Partition1		RAID5	7.88 MB	74.49 GB
Empty Space41			74.50 GB	123.78 MB

And in the system (Windows Disk Management) as a physical drive

Disk	Capacity	Health	Partitions
Disk 0	931.39 GB	Online	Recovery (300 MB), System (C:) (291.06 GB NTFS), Data (D:) (638.54 GB NTFS)
Disk 1	931.51 GB	Online	Backup II (E:) (931.51 GB NTFS)
Disk 2	74.62 GB	Read Only	RAID5 (F:) (74.49 GB NTFS), 123 MB Unallocated

OR

as a partition (Windows Disk Management) as a physical drive

Disk	Capacity	Health	Partitions
Disk 0	931.39 GB	Online	Recovery (300 MB), System (C:) (291.06 GB NTFS), Data (D:) (638.54 GB NTFS)
Disk 1	931.51 GB	Online	Backup II (E:) (931.51 GB NTFS)
Disk 2	74.62 GB	Read Only	74.62 GB (Primary Partition)



And this virtual disk becomes accessible to the system and other programs.

### To unmount a virtual drive

- 1 Right-click the virtual drive in the Drives panel and select Unmount on the shortcut menu

## 2.5 Data Recovery over Network

Available in the **Corporate and Technician/Y80+** versions. The **Standalone** version works with networks only in the Demo mode.

This chapter explains how to perform data recovery operations over network.

**R-Studio** has network capabilities that allow the system administrator, using its computer, to recover files on any computers accessible over network.

**R-Studio** supports the TCP/IP protocol and any protocol supported in Microsoft Network.

**R-Studio Agent** must be installed on computers where files are to be recovered. This program gives **R-Studio** access to local drives on remote computers over network.

If, due to file system crash, the network computer where you are going to recover your data cannot start, you may use [R-Studio Agent Emergency](#) to start the computer.

Files can be recovered without **R-Studio Agent** if the computer where the files are to be recovered runs Windows is accessible from a computer also running Windows. In this case, the administrator must have administrator privileges on the remote computer.

You should always disable a firewall and/or antivirus software on the both computers. As an alternative, advanced users may tune them to allow **R-Studio** and **R-Studio Agent** to communicate via network.

All data transmitted over network are encrypted with a strong algorithm for data security. Restoring data over network is very much the same as that on a local computer.

In addition, **R-Studio** can load/save any files like [drive images](#), [scan info](#) files, [RAID configuration](#) files, from/to the computers to which it has access using **R-Studio Agent**.

- [R-Studio Agent](#)
- [Data Recovery over Network](#)
- [Connecting over the Internet](#)

### 2.5.1 R-Studio Agent

**R-Studio Agent** is a program that provides **R-Studio** with an access to the drives of a network computer. It should be installed and properly registered on the computer which drives are to be accessed. **R-Studio Agent** has versions for the following PC operating systems:

- [Windows](#)
- [Mac OS](#)
- [Linux](#)

and there is [R-Studio Agent Emergency](#) that can be used to start a computer from which you are going to recover data that cannot start other way due to a file system crash, for example. Please, note that you need to use [R-Studio Emergency](#) as an emergency agent if you want to start a Mac computer.

**R-Studio** can work equally with all versions of **R-Studio Agent** and access computers run under Windows, Mac OS, and Linux.

You must have enough rights on the remote computer to install and run *R-Studio Agent*.

### 2.5.1.1 R-Studio Agent for Windows

**R-Studio Agent should be installed under an administrator account.**

When installed, *R-Studio Agent* starts automatically and runs as a service. To configure it, *R-Studio Agent* should be started again manually.

☐ **The following switches are available:**

-?	evokes a help screen;
-install	installs <i>R-Studio Agent</i> as a service
-remove	removes <i>R-Studio Agent</i> services
-console	starts <i>R-Studio Agent</i> as a console application

Started without a switch, *R-Studio Agent* runs as a GUI application and its icon appears on the taskbar tray. In this mode, it can be configured and its log may be viewed.

Simply connect to the remote computer providing a desired password for *R-Studio Agent* in the Connect to Remote Computer dialog box. **R-Studio** checks if there is *R-Studio Agent* running on this computer. If not, a Can't connect... message will appear.

Click the **Yes** button, and **R-Studio** will remotely install *R-Studio Agent*.

**Attention Windows users: R-Studio Agent may be remotely installed over a network from a computer running Windows to another computer running Windows. To do so, you must have administrator accounts on both computers.**


**To access the R-Studio Agent main panel,**

- 1 Click its tray icon



- > The main panel will appear. You may view its log

#### R-Studio Agent main panel




**To configure *R-Studio Agent*,**

- 1 Right-click its tray icon and select **Configure**



- Specify required parameters on the Please configure R-Studio Agent dialog box and click the OK button

Please configure R-Studio Agent dialog box



### R-Studio Agent Options

Password:	Enter a password to obtain access to this computer from a network.
Re-Enter:	Re-enter the password.
<b>Accepted Protocols</b>	
Pipes	supported by Windows. To improve security, this option should be disabled.
TCP/IP	supported by any network OS.
Port	port for incoming connections
<b>Accepted IP Addresses</b>	
IP Address	specifies addresses from which this computer can be accessed.
Subnet Mask	specifies a subnet mask of the network from which this computer can be accessed.

- > *R-Studio Agent* will now run with the specified parameters

#### 2.5.1.2 R-Studio Agent for Mac


You need to have an administrative account on the Mac computer to start *R-Studio Agent for Mac*.

**To start the R-Studio Agent for Mac and access its main panel,**

- Go to the Application folder, double-click *R-Studio Agent for Mac*, and enter the account password

- > The main panel will appear. You may view its log

#### R-Studio Agent for Mac main panel



**To configure *R-Studio Agent for Mac*,**

- Go to the *R-Studio Agent for Mac* menu and select Preferences

- 2 **Specify required parameters on the** Please configure R-Studio Agent **dialog box** and click the **OK** button

Please configure R-Studio Agent Mac **dialog box**



#### [-] R-Studio Agent for Mac Options

Password:	Enter a password to obtain access to this computer from a network.
Re-Enter:	Re-enter the password.
Incoming connection preferences	
Enable incoming connections	Select this checkbox if you want to allow incoming connections.
TCP/IP Port	A TCP/IP port for incoming connections
<a href="#">Accepted IP Addresses</a>	
IP Address	specifies addresses from which this computer can be accessed.
Subnet Mask	specifies a subnet mask of the network from which this computer can be accessed.


- > *R-Studio Agent for Mac* will now run with the specified parameters

#### **Connecting from R-Studio Agent for Mac to R-Studio.**

To establish a connection from R-Studio Agent for Mac to R-Studio,

- 1 Run the **R-Studio Agent for Mac** and select **Connect** from the **Tools** menu
- 2 Enter the necessary information on the **Connect to R-Studio dialog box** and click the **Connect** button.


Connect to R-Studio **dialog box**



#### [-] Connect to R-Studio settings

Server	Specify the DNS name or IP address of the host where <b>R-Studio</b> is running.
Port	Specify the port set on the <b>R-Studio</b> Connect to Remote Computer dialog box.
Password	Specify the password set on the <b>R-Studio</b> Connect to Remote Computer dialog box.

- > **R-Studio Agent for Mac** will connect to the computer where **R-Studio** is running and it will show the drive and logical disk structure of the remote computer.



It can be processed the same way as that on a local computer.

### 2.5.1.3 R-Studio Agent for Linux

You need to have the root privileges to run **R-Studio Agent for Linux**.

Unlike [R-Studio Agent for Windows](#) and [R-Studio Agent for Mac](#), **R-Studio Agent for Linux** is a console application and should be run in the Terminal. You also need to mark it as an executable before start.

When it is started for the first time, **R-Studio Agent for Linux** asks for its configuration.

R-Studio Agent for Linux Configuration **dialog box**

```
File Edit View Terminal Help
root@BCK-Ubuntu:~# cd RSA
root@BCK-Ubuntu:~/RSA# ./rsagent
Configuring R-Studio Agent 6.0.1020
# Specify password for incoming connections >
# Confirm password for incoming connections >
# Specify IP Address (and optional NETMASK delimited by space) to limit incoming
connections or 0 to allow any [] >192.168.1.1 255.255.255.0
# Specify TCP/IP port for listening [3174] >
* Running R-Studio Agent
* This product is licensed to: UNREGISTERED DEMO VERSION
# System: 2 x Intel(R) Core(TM)2 CPU 6300 @ 1.86GHz, 1862 MHz, 993 MB RAM
# OS: Linux 2.6.32-41-generic-pae #91-Ubuntu SMP Wed Jun 13 12:00:09 UTC 2012
? R-Studio Agent is not yet registered, 64KB file size recovery limit is implied
until remotely registered
* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start connection to remote R-Studio ...[]
```

#### ▣ R-Studio Agent for Linux Options

Specify password for incoming connection	Enter a password to obtain access to this computer from a network.
Confirm password for incoming connection	Re-enter the password for confirmation.
Specify IP address...	Specifies addresses and a subnet mask from which this computer can be accessed. Enter 0 to allow connections from any address.
Specify TCP/IP Port for listening	A TCP/IP port for incoming connections. Press Enter for the default one [3174].

Don't pay much attention to the warning about "unregistered demo version". If necessary, you'll be able to register **R-Studio Agent for Linux** through **R-Studio**.

You may see the current configuration by starting **R-Studio Agent for Linux** with the command `rsagent --show_config`.

## R-Studio Agent for Linux Configuration dialog box

```
File Edit View Terminal Help
root@BCK-Ubuntu:~# cd RSA
root@BCK-Ubuntu:~/RSA# ./rsagent --show_config
R-Studio Agent 6.0.1020
Password for incoming connection: present
Accept incoming connection from IP addresses / NetMask: 192.168.1.1 / 255.255.25
5.0
Listening on port: 3174
root@BCK-Ubuntu:~/RSA#
```

You may change the current configuration by starting **R-Studio Agent for Linux** with the command `rsagent --configure`.

### Connecting from R-Studio Agent for Linux to R-Studio.

To establish a connection from R-Studio Agent for Linux to R-Studio,

- 1 Run the **R-Studio Agent for Linux** and press Enter
- 2 Enter the necessary information

#### Connect to R-Studio dialog box

```
File Edit View Terminal Help
root@BCK-Ubuntu:~# cd RSA
root@BCK-Ubuntu:~/RSA# ./rsagent
* Running R-Studio Agent
* This product is licensed to: UNREGISTERED DEMO VERSION
# System: 2 x Intel(R) Core(TM)2 CPU 6300 @ 1.86GHz, 1862 MHz, 993 MB RAM
# OS: Linux 2.6.32-41-generic-pae #91-Ubuntu SMP Wed Jun 13 12:00:09 UTC 2012
? R-Studio Agent is not yet registered, 64KB file size recovery limit is implied
until remotely registered
* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start connection to remote R-Studio ...
# Enter R-Studio IP address or just press ENTER to cancel>192.168.1.10
# Enter password or just press ENTER to connect without one>
Connection with 192.168.1.10:8080 is established successfully.
* You may press ENTER to start connection to remote R-Studio ...
```

- > **R-Studio Agent for Linux** will connect to the computer where **R-Studio** is running and it will show the drive and logical disk structure of the remote computer.

Device/Disk	Label	FS	Start	Size
<b>Local Computer</b>				
TOSHIBA DT01ACA100 MS...	44HSATLKS	#1 SA...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partit...			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0a573f2-14d5...		NTFS	292.53 GB	450 MB
D:	Data	NTFS	292.97 GB	638.54 GB
Empty Space18			931.51 GB	1.69 MB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219...				
E:				
<b>Remote Computer</b> 192.168.1.245				
VBOX HARDDISK 1.0	VBdfb3f256-7ee...	SATA2	0 Bytes	10.09 GB
/media/tester/Storage	Storage	Ext4	0 Bytes	10.09 GB
VBOX HARDDISK 1.0	VB55c0fbcc5-f8e...	SATA2	0 Bytes	103.38 GB
Partition1		Ext4	1 MB	99.38 GB
Partition2			99.39 GB	4.00 GB
/		Ext4	1 MB	99.38 GB

It can be processed the same way as that on a local computer.

## 2.5.2 Data Recovery over Network

Generally, data restoring over network is very much the same as that on a local computer.

**R-Studio Agent** should be running on the network computer where data are to be recovered.


Read the [Connecting over the Internet](#) topic to learn how to establish connection between **R-Studio** and **R-Studio Agent** over the Internet.

### To connect to a remote computer

- 1 Click the **Connect to Remote** button or select **Connect To Remote** on the **Drive** menu and select **Connect to the remote computer**

A list of nearby computers will appear in the [Computer List](#) on the **Connect to Remote Computer** dialog box.

## Connect to Remote Computer dialog box



- 2 **Select a computer from the list on the Connect to Remote Computer dialog box and enter the password**

Otherwise, you need to specify in the Computer: field the name or IP address of the remote computer where data are to be recovered. The Port should coincide with the port specified for the [R-Studio Agent](#).

The Password: field is for the password of **R-Studio Agent** running on the remote computer. If you want to see the entered password, right-click the field and select **Show password** on the shortcut menu.


**Note:** If the remote computer is started with [R-Studio Agent Emergency](#), leave this field blank.

- > **R-Studio will connect to the remote computer and show its drive and logical disk structure of the remote computer below the device/disk structure of your local computer**

Device/Disk	Label	FS	Start	Size
Local Computer				
SAMSUNG SP0411N TW100...	S01J20XC75851	#0 AT...	0 Bytes	37.31 GB
F:	NTFS-Test	NTFS	32 KB	6.76 GB
G:	FAT32-TEST	FAT32	6.76 GB	6.19 GB
H:	FAT-TEST	FAT16	12.95 GB	2.01 GB
Volume{c7e018fa-2f05-...	HFS-Test	HFS+	14.96 GB	6.67 GB
HarddiskVolume5	Ext4FS-Test	Ext4	21.63 GB	6.52 GB
U:	Double	NTFS	28.15 GB	9.15 GB
TOSHIBA DT01ACA100 MS...	44HSATLKS	#1 SA...	0 Bytes	931.51 GB
Marvell 91xx Config 1.01				
PIIONEER DVD-RW DVR-219...				
E:				
Remote Computer	192.168.1.63			
VBOX HARDDISK 1.0	VB737c0ed-546...	#0 AT...	0 Bytes	40 GB
C:	Windows 10	NTFS	1 MB	40.00 GB
VBOX HARDDISK 1.0	VB2fe89676-23e...	#1 AT...	0 Bytes	1 GB
E:	TestVHD	NTFS	64 KB	1021 MB
VBOX CD-ROM 1.0				
D:				

It can be processed the same way as that on a local computer.

## Recover dialog box



When the Recover dialog box appears, you may select whether you want to save recovered files on the local or remote computer. Saving recovered files on a remote computer may be useful when the remote computer has a healthy drive because you do not have to transfer files over network. It may be an external USB drive, for example.

When **R-Studio** connects to the remote computer, it check if **R-Studio Agent** is present and its password. If there is no **R-Studio Agent** installed, **R-Studio** may try to remotely install it. See the [R-Studio Agent](#) topic for details.

### 2.5.3 Connecting over the Internet

**Available in the Technician/T80+ only.**


**R-Studio** and **R-Studio Agent** can be connected over the Internet. The connection can be made either using IP addresses or DNS names.

If hosts where **R-Studio** and **R-Studio Agent** are running have public IP addresses the connection can be made [the same way as for the local network](#), except that the IP address or DNS name should be explicitly specified in the Computer filed the Connect to Remote Computer dialog box

If either (or both) of the hosts are on private networks behind NATs and firewalls and do not have public IP addresses, the corresponding ports should be opened or forwarded. In addition, connection should be made either only from **R-Studio** or from **R-Studio Agent**.


#### Connection directions

\* Both **R-Studio** and **R-Studio Agent** have public IP addresses (no [NAT/firewall](#)) or the ports on the NAT/? firewall are forwarded/@pened.




A connection can be made either from **R-Studio** or from **R-Studio Agent**.

\* **R-Studio** is behind a NAT and R-Studio Agent has a public IP address or the ports on its NAT/firewall are forwarded/opened.




A connection should be made from **R-Studio**.

\* **R-Studio** has a public IP address or the ports on its NAT/firewall are forwarded/opened and R-Studio Agent is behind a NAT.



A connection should be made from **R-Studio Agent**.

\* Both **R-Studio** and **R-Studio Agent** are behind NATs/firewalls.




No connections are possible.

### **Connection from R-Studio Agent to R-Studio**

#### **R-Studio settings**

If a connection is to be made from **R-Studio Agent** to **R-Studio**, **R-Studio** should be set to accept connection on the Connect to Remote Computer dialog box.

#### **Connect to Remote Computer dialog box**



Select **Wait connection from remote computer**, and specify options for incoming connections.

#### **R-Studio Incoming Connection Options**


Password:	Enter a password to obtain access to this computer from a network.
Allow connection from any address	Select this option if you want to allow connections to <b>R-Studio</b> from any IP address
Allow connection from the host	Select this option if you want to allow connections to <b>R-Studio</b> from a specific IP address or a network
IP Address	specifies addresses from which this computer can be accessed.
Subnet Mask	specifies subnet mask of the network from which this computer can be accessed.



Port	port for incoming connections.
------	--------------------------------

**R-Studio** will wait for an incoming connection.

Waiting for remote connection **dialog box**




**Connecting from R-Studio Agent to R-Studio.**

**To establish a connection from R-Studio Agent to R-Studio,**

(See the [R-Studio Agent for Mac](#) or [R-Studio Agent for Linux](#) help page to learn how to establish connections from those **R-Studio Agent** versions).

- 1 **Right-click the R-Studio Agent tray icon and select Connect**
- 2 **Enter the necessary information on the Connect to R-Studio dialog box and click the Connect button.**

Connect to R-Studio **dialog box**



**Connect to R-Studio settings**

Server	Specify the DNS name or IP address of the host where <b>R-Studio</b> is running.
Port	Specify the port set on the <b>R-Studio</b> Connect to Remote Computer dialog box.
Password	Specify the password set on the <b>R-Studio</b> Connect to Remote Computer dialog box.

- > **R-Studio Agent will connect to the computer where R-Studio is running and it will show the drive and logical disk structure of the remote computer.**

Device/Disk	Label	FS	Start	Size
Local Computer				
SAMSUNG SP0411N TW100...	S01J20XC75851	#0 AT...	0 Bytes	37.31 GB
F:	NTFS-Test	NTFS	32 KB	6.76 GB
G:	FAT32-TEST	FAT32	6.76 GB	6.19 GB
H:	FAT-TEST	FAT16	12.95 GB	2.01 GB
Volume{c7e018fa-2f05-...	HFS-Test	HFS+	14.96 GB	6.67 GB
HarddiskVolume5	Ext4FS-Test	Ext4	21.63 GB	6.52 GB
U:	Double	NTFS	28.15 GB	9.15 GB
TOSHIBA DT01ACA100 MS...	44H5ATLKS	#1 SA...	0 Bytes	931.51 GB
Marvell 91xx Config 1.01				
PIONEER DVD-RW DVR-219...				
E:				
Remote Computer	192.168.1.63			
VBOX HARDDISK 1.0	V8737fc0ed-546...	#0 AT...	0 Bytes	40 GB
C:	Windows 10	NTFS	1 MB	40.00 GB
VBOX HARDDISK 1.0	V82fe89676-23e...	#1 AT...	0 Bytes	1 GB
E:	TestVHD	NTFS	64 KB	1021 MB
VBOX CD-ROM 1.0				
D:				

It can be processed the same way as that on a local computer.

### III R-Studio Technician/T80+

**R-Studio Technician/T80+ Demo** can perform all data recovery actions except saving recovered files greater than 256 KB and multi-pass imaging.

The **R-Studio T80+** version requires an active internet connection to run and register. You may read more about **R-Studio T80+** in our article [R-Studio T80+ - A Professional Data Recovery and Forensic Solution for Small Business and Individuals Just for US\\$1/day.](#)

**R-Studio Technician** has additional controls on its main panel.

### R-Studio Main Technician/T80+ panel

The screenshot displays the R-Studio Technician interface. The top toolbar includes buttons for Refresh, Show Files, Scan, Partition Search, Create Image, Open Image, Create Region, Start Runtime Image, RAID's, Connect To Remote, Remove, and I/O Monitor. The main window is split into two panes. The left pane shows a tree view of 'Local Computer' with a list of disks and partitions. The right pane shows properties for the selected disk, including Drive Type, Name, OS Object, R-Studio Driver, Size, Logical Sector Size, Physical Sector Size, Partition Size, I/O Retries, Drive Control (Maximum Transfer, I/O Block Size, Buffer Alignment), and Physical Drive Geometry (Cylinders, Tracks Per Cylinder). At the bottom, there is a 'Log' window showing system messages and a status bar that says 'Ready'.



#### Start runtime image

Click this button to start [runtime imaging](#) of the selected object.

(**Technician/T80+** versions only)



#### I/O Monitor

Click this button to open [I/O Monitor](#).

This chapter covers features that available only in the **R-Studio Technician/T80+** versions have additional features that are not available in other versions:.

- [Portable version](#)
- [Multitasking](#)
- [Additional Recovery Options](#)

- [Hidden Devices](#)
- [File Information](#)
- [Symbolic Link Processing](#)
- [Custom Recovery Lists](#)
- [Drive Copy Wizard](#)
- [File Maps](#)
- [I/O Monitor and Sector Map files](#)
- [Runtime Imaging](#)
- [Multi-pass Imaging](#)
- [Reverse RAIDs](#)
- [Working with the Third-Party Hardware](#)
- [Forensic Mode](#)

Some other information about **R-Studio Technician/T80+** is shown on the following pages:

- [R-Studio Settings](#)
- [Drive Scan](#)
- [Images](#)
- [BitLocker Drive Encryption](#)
- [Apple CoreStorage/File Vault/Fusion Drive Volumes](#)
- [Connecting over the Internet](#)
- [Supported Virtual Disk and Disk Image Formats](#)

### 3.1 Portable version


**R-Studio Technician** may be installed on and run from, a removable device like a USB memory stick. This portable version has all functionality of an installable version and can be used on any Windows computer.

#### R-Studio Technician Portable creation

A device for the portable version should have approximately 500 MB of free space.

Select **Creation a portable version...** on the Installation mode panel during installation.

Installation mode



and continue installation process.


## R-Studio Technician Portable start.

### \* Insert the removable device with R-Studio Technician Portable


**R-Studio Technician** starts automatically if `AutoRun` and `AutoPlay` services are enabled.

If they are disabled, go to the device and start the program manually.

## R-Studio Technician Portable start



## R-Studio Technician Portable start




## R-Studio Technician Portable activation

Sometimes **R-Studio Technician Portable** may need activation. You may do it the following way:

\* If there's a working internet connection for the computer: enter the registration code for **R-Studio Technician Portable**.

## R-Studio Technician Portable start



If there's no internet connections: You need to manually obtain an activation code to complete the registration. The Online Activation dialog window will appear.

## R-Studio Technician Portable Online Activation dialog box




You may copy the url with the activation information and go to it on another computer connected to the Internet, obtain the activation code, and enter it into the respective field on the dialog box.

You may also use your smartphone to activate **R-Studio**. Scan the QR-code and go to the specified URL, obtain the activation code, and finish program activation.

## R-Studio Technician Portable operation

You may work with the same way as with an installed **R-Studio Technician**, including its work with data recovery hardware.

## R-Studio Technician Portable with data recovery hardware




## 3.2 Multitasking

**R-Studio Technician** can perform several tasks simultaneously. For example, you can simultaneously recover files from one disk, create an image of another disk using **USB Stabilizer**, and scan a loaded image. The number of simultaneously running tasks depends on the system performance: CPU power, RAM size, free space on the disks, data transfer speed, and so on.

When, for example, 3 tasks are simultaneously running, **R-Studio Technician** will mark them with a special rotating sign in its Device view pane. In our this example, these 3 tasks are file recovery from a logical disk (partition), had drive image creation, and scanning of an image of a hard drive


### Three tasks running



It also shows a list of running tasks. You may switch to the required task by clicking it. The progress bar at the bottom show the overall progress of all tasks.

Each task runs independently in its own tab, has its own [I/O Monitor](#), and can be independently controlled:

### File recovery





## Image creation

The screenshot shows the 'Image creation' process in R-Studio Technician. The main window displays a list of disks and partitions, including the source disk 'DEEPSPAR: WDC WD120...' and the target disk 'm.2 Smartbuy S11-2...'. The progress bar indicates that the image creation is 32% complete, with a time elapsed of 8m 1s and 1h 31m remaining. The log window shows the following entries:

Type	Date	Time	Text
System	3/5/2024	10:17:11 AM	All file regions are collected.
Recover	3/5/2024	10:17:45 AM	Using file exist rules: By default/Rename;
Recover	3/5/2024	10:17:45 AM	Recover destination: D:\Multipass\


## Image scan

The screenshot shows the 'Image scan' process in R-Studio Technician. The main window displays a list of disks and partitions, including the source disk 'DEEPSPAR: WDC WD120...' and the target disk 'm.2 Smartbuy S11-2...'. The progress bar indicates that the image scan is 34% complete, with a time elapsed of 18m 7s and 1h 7m remaining. The log window shows the following entries:

Type	Date	Time	Text
Recover	3/5/2024	10:17:45 AM	Recover destination: D:\Multipass\
Recover	3/5/2024	10:26:10 AM	Successfully recovered: 644 file.
Recover	3/5/2024	10:26:10 AM	Elapsed: 8m 25s.

When all tasks have been completed, **R-Studio Technician** will show their results with special marks.

## All task completed




These marks will disappear when the corresponding tabs are opened.

## 3.3 Additional Recovery Options

R-Studio Technician has additional Recovery options.

Recover (Additional Output Folders) dialog box






**Additional Output Folders**

Additional Output Folders	Additional output folders where recovered files will be stored when <b>R-Studio</b> runs out of space.
---------------------------	--

**NEVER TRY TO SAVE RECOVERED FILES/FOLDERS TO THE SAME LOGICAL DISK WHERE THEY RESIDE!!!**

**Or you may obtain unpredictable results and lose all of your data.**

**Recover (Post Actions) dialog box**



**Post Actions Options**

Shutdown the computer on task completion	If this check box is selected, <b>R-Studio</b> will shut down your computer when file recovery has been completed. The program will warn you if any option on the Advanced tab is set to Prompt.
E-Mail notifications	If this check box is selected, <b>R-Studio</b> will inform you about the outcome of the operation via email.

### 3.4 Hidden Devices


**R-Studio Technician** can hide unnecessary devices on the Device View pane. Most likely, they may be system drives and drives connected to save recovered data. Hiding those devices doesn't prevent **R-Studio Technician** from saving recovered and service files on them.

**No hidden devices**

Device/Disk	Label	FS/Interface	Start	Size
Local Computer				
KINGSTON SA400S37120G 03090005	50026B77843A5618	#0 SATA2, SSD	111.79 GB	
EPI system partition		FAT32	1 MB	100 MB
Microsoft reserved partition			101 MB	16 MB
C:	System		117 MB	111.18 GB
Windows Recovery Partition		NTFS	111.29 GB	508 MB
TOSHIBA DT01ACA100 MS20A750	44HSATLKS	#1 SATA2, HDD	931.51 GB	
D:	Data	NTFS	1 MB	931.51 GB
Hitachi HT545016B9SA00 PBB0CB45	TU0713PBP808CE4X50F	#2 SATA2, HDD	1149.05 GB	
I:	NTFS-Test	NTFS	512 KB	28.69 GB
F:	FAT32-TEST	FAT32	28.69 GB	26.27 GB
G:	FAT-TEST	FAT32	14.96 GB	2.01 GB
E:	EXFAT	EXFAT	6.97 GB	11.72 GB
Partition5	HFS	HFSX	68.69 GB	21.48 GB
Partition6	EXTFS	Ext4	90.17 GB	25.02 GB
Partition7	XFS	XFS	115.19 GB	33.86 GB
Reformatted!		NTFS	0 Bytes	33.86 GB
PIONEER DVD-RW DVR-219L 1.00				
H:				
WDC WD20SPZX-68UA7 02.01.A02	0123456789ABCDEF	#3 USB, HDD	1.82 TB	
Y:	External USB Disk to Save Recovered Data			1 TB

## To hide unnecessary devices,


- 1 Go to Settings and then to the Hidden Devices tab, mark all devices you want to hide, Hidden Devices tab



and restart **R-Studio Technician**.


- > Only necessary devices will be visible

### Necessary devices



You may make hidden devices visible once again on the Hidden Devices tab.

### Hidden Devices tab



## 3.5 File Information

R-Studio Technician/T80+ shows much more information about files than R-Studio does.

**Info about a file with good chances for recovery**

MyDoc3.odt

Location: F:\Docs  
 Id: 47284139  
 Parent Id: 4887331  
 Size: 177.38 MB (185,991,168 Bytes)  
 Flags: valid first data offset

Created: 4/5/2011 10:42:13 PM  
 Modified: 2/28/2011 11:31:10 PM  
 Accessed: 4/5/2011 10:42:13 PM

MFT number: 73  
 Parent MFT number: 70

File type: OpenOffice Writer Document  
 Recovery chances: Good (Existing file)

Regions

sector 202000 size: 177.38 MB (185,991,168 Bytes) / first data  
 sector 2433982 (offset: 80) size: 72 Bytes / resident  
 sector 2533982 (offset: 120) size: 96 Bytes / resident

**Info for a file with below average recovery chances**

Cirque.Du.Soleil.Kooza.2008.avi

Location: G:\(Recognized0)\RECYCLE.BIN\R0197J\Movies  
 Id: 4901  
 Parent Id: 5327  
 Size: 1.36 GB (1,462,525,952 Bytes)  
 Flags: deleted, link target, valid first data offset

Created: 6/2/2012 10:06:31 PM  
 Modified: 1/22/2011 1:19:16 PM  
 Accessed: 6/1/2012 11:00:00 PM

File type: Windows AVI Video  
 Recovery chances: Below Average (Wrong Signature, File start is overwritten by existing file 1180)

Overlapping files

1180 Cirque.Du.Soleil.Kooza.2008.avi  
 1175 Cirque.Du.Soleil.Kooza.2008.avi  
 1174 PR2GIP3.avi

Regions

sector 1129248 size: 6.27 MB (6,569,984 Bytes) / first data  
 1175 Cirque.Du.Soleil.Kooza.2008.avi  
 1174 PR2GIP3.avi  
 1180 Cirque.Du.Soleil.Kooza.2008.avi  
 > sector 1152000 size: 1.36 GB (1,455,955,968 Bytes) / data

### More information

	Click this button to pin the file information. This panel will show the information about the "pinned" file regardless of the current selected file.
	Click this button to copy all this information
	Click this button to select the file you want to go to.
	Click this button to close all the information.
Overlapping files	Shows the list of files that may occupy the same drive sectors. You may click the file id to see information about this file.
Regions	Shows the list of sectors occupied by the file and corresponding overlapping files. You may click a sector number open the sector in the built-in Hexadecimal editor.

## Examples of file information on other file systems

### File info on an [ext4fs](#) file system

File info window for `VTS_01_2.VOB` on an ext4fs file system. The window shows the following details:

- Location:** HarddiskVolume5 (Recognized)\Movies\San\_Valley\_Serena\VIDEO\_TS
- Id:** [133896]
- Parent Id:** [133896]
- Size:** 1000.01 MB (1,048,584,192 Bytes)
- Flags:** valid first data offset
- Modified:** 1/10/2010 10:06:22 AM
- Accessed:** 9/2/2015 12:45:02 AM
- Owner:** 1000
- Group:** 1000
- Permission:** r-rw-rw- (100664)
- Inode num:** 131088
- File type:** MPEG Video
- Recovery chances:** Good (Existing file)
- Overlapping files:**
  - [590788] 00113.vob
  - [590789] 00114.vob
  - [590790] 00115.vob
  - [590791] 00116.vob
  - [590792] 00117.mpg
  - [590803] 00133.mpg
  - [590787] 00112.vob
  - [590786] VTS\_01\_2.VOB
- Regions:**
  - sector 2375680 size: 16 MB (16,777,216 Bytes) / first data
  - [590786] VTS\_01\_2.VOB
  - sector 2441216 size: 16 MB (16,777,216 Bytes) / data
  - sector 2506752 size: 16 MB (16,777,216 Bytes) / data
  - sector 2572288 size: 16 MB (16,777,216 Bytes) / data
  - sector 2637824 size: 16 MB (16,777,216 Bytes) / data
  - sector 2686976 size: 736 MB (771,751,936 Bytes) / data
  - sector 4489216 size: 40 MB (41,943,040 Bytes) / data
  - sector 4587320 size: 8 MB (8,388,608 Bytes) / data
  - sector 4620288 size: 16 MB (16,777,216 Bytes) / data
  - sector 4633824 size: 8 MB (8,388,608 Bytes) / data
  - sector 4718928 size: 16 MB (16,777,216 Bytes) / data
  - sector 4784128 size: 96.01 MB (100,671,488 Bytes) / data

### File info on an APFS file system

File info window for `Johnny_Cash_1_Got_Stripes.mp3` on an APFS file system. The window shows the following details:

- Location:** Root\Trashes\502\Johnny\_Cash\_1\_Got\_Stripes.mp3
- Id:** [5890000000001f2]
- Parent Id:** [58900000000033e]
- Size:** 2.87 MB (3,008,512 Bytes)
- Created:** 3/3/2022 11:07:38 AM
- Modified:** 4/28/2016 02:38:28 PM
- Accessed:** 6/20/2022 02:08:25 PM
- Owner:** 99
- Group:** 99
- Permission:** rwxrwxrwx (100777)
- CHID:** 242
- File type:** MPEG Layer III Audio
- Recovery chances:** Good (Existing file)
- Region status:** [OK]
- Overlapping files:**
  - [5a0000000000717] Johnny\_Cash\_1\_Got\_Stripes.mp3
  - [5a000000000014b] Johnny\_Cash\_1\_Got\_Stripes.mp3
- Regions:**
  - sector 2379920 size: 2.87 MB (3,008,512 Bytes) / first data
  - [5a0000000000717] Johnny\_Cash\_1\_Got\_Stripes.mp3
  - [5a000000000014b] Johnny\_Cash\_1\_Got\_Stripes.mp3

## 3.6 Symbolic Link Processing

R-Studio Technician/T80+ give its users more control over [symbolic links](#) processing.

[Symbolic links](#) (of symlinks for short) are object that contains references to other files or folders directory in the form of absolute or relative paths and that affect pathname resolution. For example, if a symlink `c:\ProgramData\Documents` points to `D:\Recovered Files\Root\Users\Public\Documents`, entering it will result in entering `D:\Recovered Files\Root\Users\Public\Documents`.

### Info for a file on an HFS+ file system

File info window for `VTS_01_1.VOB` on an HFS+ file system. The window shows the following details:


- Location:** HarddiskVolume4 (Recognized)\Movies\San\_Valley\_Serena\VIDEO\_TS
- Id:** [124]
- Parent Id:** [117]
- Size:** 1000.27 MB (1,048,860,672 Bytes)
- Flags:** valid first data offset
- Created:** 1/10/2010 10:06:22 AM
- Modified:** 1/10/2010 10:06:22 AM
- Accessed:** 5/14/2016 8:00:04 PM
- Recovery chances:** Good (Existing file)
- Overlapping files:**
  - [4294970298] 00039.vob
  - [4294970283] 00024.vob
  - [4294970287] 00038.vob
  - [4294970295] 00037.vob
  - [4294970295] 00036.vob
  - [4294970294] 00035.vob
  - [4294970293] 00034.vob
  - [4294970292] 00033.vob
  - [4294970291] 00032.vob
  - [4294970290] 00031.vob
  - [4294970289] 00030.vob
  - [4294970288] 00029.vob
  - [4294970287] 00028.vob
  - [4294970286] 00027.vob
- Regions:**
  - sector 1200152 size: 856 MB (897,581,056 Bytes) / first data
  - [4294970280] 00022.mpg
  - sector 2953248 size: 144.27 MB (151,279,616 Bytes) / data

### Info for a file on an [XFS](#) file system

File info window for `johnny-cash-san-quentin.mp3` on an XFS file system. The window shows the following details:

- Location:** Root\Music\johnny-cash-san-quentin.mp3
- Id:** [5c00000000007f2]
- Parent Id:** [5c40000000000f1]
- Size:** 3.61 MB (3,787,963 Bytes)
- Flags:** cross link
- Created:** 6/17/2022 12:53:24 PM
- Modified:** 4/28/2016 02:32:14 PM
- Accessed:** 6/17/2022 12:53:24 PM
- Owner:** 1000
- Group:** 1000
- Permission:** rwxrwxrwx (100777)
- File type:** MPEG Layer III Audio
- Recovery chances:** Good (Existing file)
- Region status:** [OK]
- Overlapping files:**
  - [5e0000000000015] \$inodeIndv0000009e
- Regions:**
  - sector 96584 size: 3.61 MB (3,787,963 Bytes) / first data

## Symbolic Links dialog box



### Symbolic Links

Symbolic links display settings	
Don't show symbolic links by default (Technician version)	If this option is selected, <b>R-Studio</b> hides all symbolic links by default. Only real objects will be visible. You may make them visible by clearing the Hide symbolic links option on the <a href="#">Mask</a> dialog box.
Show folder symbolic links as links to their targets, without target content (Technician version)	Only links to their target will be shown in the right pane (Contents). They target content can be reached by clicking those links.
Symbolic links recovery options	
For all options:	When both the symbolic link and its target are selected for recovery, both the symbolic link and its target will be recovered. When only the target is selected fore recovery, only the target will be recovered.
Link conversion (Default)	
Only a symbolic link is selected for recovery:	The selected symbolic link will be recovered as its target.
If both a symbolic link and its target are selected for recovery:	If both a symbolic link and its target are selected for recovery, both the target and its symbolic link will be recovered. The file path in that symbolic link will be converted from absolute to relative. Example: If the object <code>C:\ProgramData\Documents</code> is a symbolic link to <code>C:\Users\Public\Documents</code> , it will be converted to a symbolic link to <code>..\Users\Public\Documents</code> . Therefore, the symbolic link will point to its object regardless of the place to which the object has been recovered.
Recovery as it is (Technician version)	
Only a symbolic link is selected for recovery:	The symbolic link will be recovered as a symbolic link which may contain a path to a nonexistent object.
If both the symbolic link and its target are selected for recovery, the	If both the symbolic link and its target are selected for recovery, the file path in that symbolic link will remain unchanged.

absolute link will remain as the original absolute symbolic link.	<p><b>Example:</b>  The place to store recovered data: D:\Recovered Files.  The object to recover: C:\Users\Public\Documents  The symbolic link: C:\ProgramData\Documents</p> <p><b>After recovery:</b>  The recovered object: D:\Recovered Files\Root\Users\Public\Documents  The recovered symbolic link: D:\Recovered Files\Root\ProgramData\Documents pointing to C:\Users\Public\Documents.  Therefore, if someone tries to enter to the symbolic link, the system will open the object C:\Users\Public\Documents, rather than recovered D:\Recovered Files\Root\Users\Public\Documents.  Usually a recovered target has a new path, therefore its recovered absolute links will point to a wrong place, or to a non-existent object.</p>
---	--

The [Data Recovery Topics](#) topic explains processing of symbolic links recovery in more detail.

### 3.7 Custom Recovery Lists

The **R-Studio Technician/T80+** versions can create more advanced [recovery lists](#).

#### **Export Recovery List options**

Export the entire folder/file tree Export marked file/folder names Export file/folder names	Specifies which file and folder names will be exported.
File format:	<p>A file format for the recovery list.  Only text format is available for the standalone and corporate versions.  <b>R-Studio Technician/T80+</b> can create <a href="#">custom recovery lists</a> in other formats with more advanced options  The following formats are available for <b>R-Studio Technician/T80+</b> version:  Plain Text  HTML  XML  JSON  CSV</p>
File name:	Specifies a file name of the recovery list.

#### **Editing the file recovery list**

All files without any marks in the recovery list will be marked when the list is loaded into **R-Studio**. So, if you have some files in the recovery list that don't need to be recovered, just delete them from the list. In addition, you may use the following marks to specify some options

- :+ Mark the file, or the folder, all its files, and subfolders within the folder.
- :\* Mark the file, or the folder and its files, don't mark subfolders in the folder.
- :- Unmark the file, or the folder, its files, and subfolders in the folder.

:= Unmark the file or the folder and its files, dont unmark subfolders in the folder.

!: Provide the information on the file. (**R-Studio Technician/T80+** only)

**R-Studio** processes records in the list consequently. That is, if there are the following lines in the file,

```
:+Files_to_Recover\  
:-Files_to_Delete\File_2.jpg
```

the file `File_2.jpg` won't be marked for recovery, while for the lines

```
:-Files_to_Recover\File_2.jpg
```

```
:+Files_to_Recover\  
file File_2.jpg will be.
```

#### **A simple recovery list for reference**

##### **Structure of a simple recovery list file created by R-Studio**

```
:# Version = 1  
:# Sort = by real  
:# PathDelim = /  
:# CaseSensitive  
:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs test";  
fs:"NTFS";  
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";  
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";  
Diving/  
Diving/Aquarium/  
Diving/Aquarium/20190822_100644.jpg  
Diving/Aquarium/20190822_101620.jpg  
Diving/Aquarium/20190822_102526.jpg  
Diving/Aquarium/20190822_103830.jpg  
Diving/Aquarium/20190822_104333.jpg  
Diving/MyPhoto1.jpg  
Diving/MyPhoto2.jpg  
Diving/MyPhoto3.jpg  
Diving/MyPhoto4.JPG  
Diving/MyPhoto5.jpg  
SF/  
SF/Sea-Lions/  
SF/Sea-Lions/IMG_3493.JPG  
SF/Sea-Lions/IMG_3535.JPG  
SF/Sea-Lions/IMG_3542.JPG  
SF/Sea-Lions/IMG_3579.JPG  
SF/Sea-Lions/IMG_3580.JPG  
SF/Sea-Lions/IMG_3581.JPG  
SF/Sea-Lions/IMG_3589.JPG  
SF/IMG_0869.JPG  
SF/IMG_0873.JPG  
SF/IMG_0890.JPG  
SF/IMG_1739.JPG  
SF/IMG_3460.JPG  
SF/IMG_3461.JPG  
SF/IMG_3476.JPG  
SF/IMG_3478.JPG  
SF/IMG_3479.JPG  
SF/IMG_3480.JPG
```

```
SF/IMG_3481.JPG
SF/IMG_3493.JPG
SF/IMG_3535.JPG
SF/IMG_3542.JPG
SF/IMG_3579.JPG
SF/IMG_3580.JPG
SF/IMG_3581.JPG
SF/IMG_3589.JPG
SF/IMG_3590.JPG
SF/IMG_3591.JPG
SF/IMG_3592.JPG
SF/IMG_3593.JPG
SF/IMG_3594.JPG
SF/IMG_3595.JPG
SF/IMG_3596.JPG
SF/IMG_3608.JPG
SF/IMG_3627.JPG
MyPhoto6.JPG
MyPhoto7.JPG
MyPhoto8.JPG
MyPhoto9.JPG
```

If such recovery list is created from an entire logical disk/partition, it will contain several virtual folders. For example, they'll have the following structure for an NTFS partition.


```
///m/$Extend/
///m/$Extend/$Deleted/
///m/$Extend/$RmMetadata/
///m/$Extend/$RmMetadata/$Txf/
///m/$Extend/$RmMetadata/$TxfLog/
///m/$Extend/$RmMetadata/$TxfLog/$Tops
///m/$Extend/$RmMetadata/$TxfLog/$TxfLog.blf
///m/$Extend/$RmMetadata/$TxfLog/$TxfLogContainer0000000000000000000001
///m/$Extend/$RmMetadata/$TxfLog/$TxfLogContainer0000000000000000000002
///m/$Extend/$RmMetadata/$Repair
///m/$Extend/$ObjId
///m/$Extend/$Quota
///m/$Extend/$Reparse
///m/$AttrDef
///m/$BadClus
///m/$Bitmap
///m/$Boot
///m/$LogFile
///m/$MFT
///m/$MFTMirr
///m/$Secure
///m/$UpCase
///m/$Volume
```

#### **HTML format**


This is a default format of recovery lists for the **R-Studio Technician/T80+** version. It allows its users to supply their customers with the recovery lists with the easiest way to edit.



## Export Recovery List dialog box for the HTML format




## HTML Options dialog box



You may export the default HTML template and edit it to adapt it for your own purposes.

When the customer loads an HTML recovery list in their browser, they can mark files they want to recover, and export their names into the final recovery list in the plain text format.

## HTML Recovery list in a browser



You may compare this list with the edited simple recovery list.

### ■ An exported recovery list

```

:# Version = 1
:# Sort = by real
:# PathDelim = /
:# CaseSensitive
:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs test";
fs:"NTFS";
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";
Diving/Aquarium/20190822_100644.jpg
:! Id=630001
Diving/Aquarium/20190822_101620.jpg
:! Id=640001
Diving/Aquarium/20190822_102526.jpg
:! Id=650001
Diving/Aquarium/20190822_103830.jpg

```

```
:! Id=660001
Diving/Aquarium/20190822_104333.jpg
:! Id=670001
Diving/MyPhoto1.jpg
:! Id=270001
Diving/MyPhoto2.jpg
:! Id=280001
Diving/MyPhoto3.jpg
:! Id=290001
Diving/MyPhoto4.JPG
:! Id=2a0001
Diving/MyPhoto5.jpg
:! Id=2b0001
SF/IMG_0869.JPG
:! Id=370001
SF/IMG_0873.JPG
:! Id=380001
SF/IMG_0890.JPG
:! Id=390001
SF/IMG_1739.JPG
:! Id=3a0001
SF/IMG_3460.JPG
:! Id=3b0001
SF/IMG_3461.JPG
:! Id=3c0001
SF/IMG_3476.JPG
:! Id=3d0001
SF/IMG_3478.JPG
:! Id=3e0001
SF/IMG_3479.JPG
:! Id=3f0001
SF/IMG_3480.JPG
:! Id=400001
SF/IMG_3481.JPG
:! Id=410001
SF/IMG_3493.JPG
:! Id=1000000
SF/IMG_3535.JPG
:! Id=1000001
SF/IMG_3542.JPG
:! Id=1000002
SF/IMG_3579.JPG
:! Id=1000003
SF/IMG_3580.JPG
:! Id=1000004
SF/IMG_3581.JPG
:! Id=1000005
SF/IMG_3589.JPG
:! Id=1000006
SF/IMG_3590.JPG
:! Id=1000007
SF/IMG_3591.JPG
:! Id=4a0001
```

```
SF/IMG_3592.JPG
:! Id=4b0001
SF/IMG_3593.JPG
:! Id=4c0001
SF/IMG_3594.JPG
:! Id=4d0001
SF/IMG_3595.JPG
:! Id=4e0001
SF/IMG_3596.JPG
:! Id=4f0001
SF/IMG_3608.JPG
:! Id=500001
SF/IMG_3627.JPG
:! Id=510001
MyPhoto6.JPG
:! Id=5e0001
MyPhoto7.JPG
:! Id=5f0001
MyPhoto8.JPG
:! Id=600001
MyPhoto9.JPG
:! Id=610001
```

#### **A manually edited plain text recovery list**

##### ***The edited simple recovery list***


The final simple recovery list will be the following:

```
:# Version = 1
:# Sort = by real
:# PathDelim = /
:# CaseSensitive
:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs test";
fs:"NTFS";
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";
:= Diving/
:+ Diving/Aquarium/
:+ Diving/MyPhoto1.jpg
:+ Diving/MyPhoto3.jpg
:+ SF/
:- SF/Sea-Lions/
MyPhoto6.JPG
MyPhoto7.JPG
MyPhoto8.JPG
MyPhoto9.JPG
```

##### **Plain text format**

Custom recovery lists in the text format contains more information about files than simple recovery lists.

## Export Recovery List dialog box for the plain text format



You may compare two versions of the same plain text recovery list:

### **An advanced text recovery list**

This is an advanced version of the recovery list described on the [Recovery List](#) page.

```

:# Version = 1
:# Sort = by real
:# PathDelim = /
:# CaseSensitive
:# Drive = type:"Volume"; size:"1048576000"; mountpoint:"e:\"; label:"ntfs
test"; fs:"NTFS";
:# Parent = type:"Drive"; size:"1048576000"; serial:"2cca54405a8d3a89";
firmware:"2.00"; product:"01gb i-disk"; vendor:"c-one";
Diving/
:| Id=4000000260001
:| Flags=directory
:| Created=11/22/2022 12:35:18 PM
:| Modified=11/22/2022 01:09:07 PM
:| Accessed=11/22/2022 01:22:18 PM
:| MFT number=38
:| Parent MFT number=5

Diving/Aquarium/
:| Id=4000000620001
:| Flags=directory
:| Created=11/22/2022 01:09:07 PM
:| Modified=11/22/2022 01:09:58 PM
:| Accessed=11/22/2022 01:22:17 PM
:| MFT number=98
:| Parent MFT number=38

Diving/Aquarium/20190822_100644.jpg
:| Id=630001
:| Size=3.63 MB (3,808,537 Bytes)
:| Created=11/22/2022 01:09:56 PM
:| Modified=8/21/2019 11:06:44 PM
:| Accessed=11/22/2022 01:09:56 PM
:| File type=JPEG Digital Camera
:| Recovery chances=Good (Existing file)
:| Regions (sector size=512B):
:| sector 449232 size: 3.63 MB (3,808,537 Bytes) / first data
:| other files: [480000000530001] IMG_0510.JPG
:| sector 682862 (offset: 80 ) size: 72 Bytes / resident
:| other files: [480000000540001] IMG_0516.JPG

```

```
!! sector 682862 (offset: 176 ) size: 104 Bytes / resident
  !! other files: [480000000540001] IMG_0516.JPG
!! MFT number=99
!! Parent MFT number=98

Diving/Aquarium/20190822_101620.jpg
!! Id=640001
!! Size=3.23 MB (3,389,662 Bytes)
!! Created=11/22/2022 01:09:56 PM
!! Modified=8/21/2019 11:16:20 PM
!! Accessed=11/22/2022 01:09:57 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 456672 size: 3.23 MB (3,389,662 Bytes) / first data
  !! other files: [480000000550001] IMG_0525.JPG
!! sector 682864 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000550001] IMG_0525.JPG
!! sector 682864 (offset: 176 ) size: 104 Bytes / resident
  !! other files: [480000000560001] IMG_0539.JPG
!! MFT number=100
!! Parent MFT number=98

Diving/Aquarium/20190822_102526.jpg
!! Id=650001
!! Size=3.06 MB (3,208,377 Bytes)
!! Created=11/22/2022 01:09:57 PM
!! Modified=8/21/2019 11:25:26 PM
!! Accessed=11/22/2022 01:09:57 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 463296 size: 3.06 MB (3,208,377 Bytes) / first data
  !! other files: [480000000560001] IMG_0539.JPG
!! sector 682866 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000570001] IMG_0541.JPG
!! sector 682866 (offset: 176 ) size: 104 Bytes / resident
  !! other files: [480000000570001] IMG_0541.JPG
!! MFT number=101
!! Parent MFT number=98

Diving/Aquarium/20190822_103830.jpg
!! Id=660001
!! Size=3.22 MB (3,381,308 Bytes)
!! Created=11/22/2022 01:09:57 PM
!! Modified=8/21/2019 11:38:30 PM
!! Accessed=11/22/2022 01:09:58 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 469568 size: 3.22 MB (3,381,308 Bytes) / first data
  !! other files: [480000000580001] IMG_0542.JPG
!! sector 682868 (offset: 80 ) size: 72 Bytes / resident
```

```
    :! other files: [480000000580001] IMG_0542.JPG
:! sector 682868 (offset: 176 ) size: 104 Bytes / resident
    :! other files: [480000000590001] IMG_0543.JPG
:! MFT number=102
:! Parent MFT number=98

Diving/Aquarium/20190822_104333.jpg
:! Id=670001
:! Size=3.19 MB (3,344,532 Bytes)
:! Created=11/22/2022 01:09:58 PM
:! Modified=8/21/2019 11:43:33 PM
:! Accessed=11/22/2022 01:09:58 PM
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 476176 size: 3.19 MB (3,344,532 Bytes) / first data
    :! other files: [480000000590001] IMG_0543.JPG
:! sector 682870 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [4800000005a0001] IMG_0545.JPG
:! sector 682870 (offset: 176 ) size: 104 Bytes / resident
    :! other files: [4800000005a0001] IMG_0545.JPG
:! MFT number=103
:! Parent MFT number=98

Diving/MyPhoto1.jpg
:! Id=270001
:! Size=2.56 MB (2,682,000 Bytes)
:! Created=11/22/2022 12:35:18 PM
:! Modified=4/29/2009 02:52:42 AM
:! Accessed=11/22/2022 12:35:19 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 11336 size: 2.56 MB (2,682,000 Bytes) / first data
    :! other files: [480000000460002] IMG_3579.JPG, [480000001000003]
IMG_3579.JPG
:! sector 682742 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [480000000470002] IMG_3580.JPG, [480000001000004]
IMG_3580.JPG
:! sector 682742 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [480000000470002] IMG_3580.JPG, [480000001000004]
IMG_3580.JPG
:! MFT number=39
:! Parent MFT number=38

Diving/MyPhoto2.jpg
:! Id=280001
:! Size=1.75 MB (1,830,252 Bytes)
:! Created=11/22/2022 12:35:19 PM
:! Modified=4/29/2009 02:53:22 AM
:! Accessed=11/22/2022 12:35:19 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
```

```
!! sector 16576 size: 1.75 MB (1,830,252 Bytes) / first data
  !! other files: [480000000480002] IMG_3581.JPG, [480000001000005]
IMG_3581.JPG
!! sector 682744 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000480002] IMG_3581.JPG, [480000001000005]
IMG_3581.JPG
!! sector 682744 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [480000000490002] IMG_3589.JPG, [480000001000006]
IMG_3589.JPG
!! MFT number=40
!! Parent MFT number=38
```

#### Diving/MyPhoto3.jpg

```
!! Id=290001
!! Size=1.73 MB (1,816,964 Bytes)
!! Created=11/22/2022 12:35:19 PM
!! Modified=4/29/2009 02:53:58 AM
!! Accessed=11/22/2022 12:35:19 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 20152 size: 1.73 MB (1,816,964 Bytes) / first data
  !! other files: [480000000490002] IMG_3589.JPG, [480000001000006]
IMG_3589.JPG
!! sector 682746 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000001000007] IMG_3590.JPG
!! sector 682746 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [4800000004a0001] IMG_3591.JPG
!! MFT number=41
!! Parent MFT number=38
```

#### Diving/MyPhoto4.JPG

```
!! Id=2a0001
!! Size=880.15 KB (901,269 Bytes)
!! Created=11/22/2022 12:35:19 PM
!! Modified=4/29/2009 02:54:20 AM
!! Accessed=11/22/2022 12:35:20 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 23704 size: 880.15 KB (901,269 Bytes) / first data
  !! other files: [4800000004b0001] IMG_3592.JPG
!! sector 682748 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [4800000004c0001] IMG_3593.JPG
!! sector 682748 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [4800000004d0001] IMG_3594.JPG
!! MFT number=42
!! Parent MFT number=38
```

#### Diving/MyPhoto5.jpg

```
!! Id=2b0001
!! Size=3.13 MB (3,286,883 Bytes)
!! Created=11/22/2022 12:35:20 PM
```

```

:~ Modified=4/29/2009 03:13:38 AM
:~ Accessed=11/22/2022 12:35:20 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 25472 size: 3.13 MB (3,286,883 Bytes) / first data
:~   :~ other files: [4800000004e0001] IMG_3595.JPG
:~ sector 682750 (offset: 80 ) size: 72 Bytes / resident
:~   :~ other files: [4800000004f0001] IMG_3596.JPG
:~ sector 682750 (offset: 176 ) size: 90 Bytes / resident
:~   :~ other files: [480000000500001] IMG_3608.JPG
:~ MFT number=43
:~ Parent MFT number=38

SF/
:~ Id=4000000360001
:~ Flags=directory
:~ Created=11/22/2022 12:35:27 PM
:~ Modified=11/22/2022 01:24:57 PM
:~ Accessed=11/22/2022 01:25:09 PM
:~ MFT number=54
:~ Parent MFT number=5

SF/Sea-Lions/
:~ Id=4000000420002
:~ Flags=directory
:~ Created=11/22/2022 01:24:57 PM
:~ Modified=11/22/2022 01:25:09 PM
:~ Accessed=11/22/2022 01:27:46 PM
:~ MFT number=66
:~ Parent MFT number=54

SF/Sea-Lions/IMG_3493.JPG
:~ Id=430002
:~ Size=4.75 MB (4,985,023 Bytes)
:~ Created=11/22/2022 01:25:05 PM
:~ Modified=6/5/2009 06:50:22 PM
:~ Accessed=11/22/2022 01:25:05 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 208544 size: 4.75 MB (4,985,023 Bytes) / first data
:~   :~ other files: [4800000002a0001] MyPhoto4.JPG
:~ sector 682798 (offset: 80 ) size: 72 Bytes / resident
:~   :~ other files: [4800000002b0001] MyPhoto5.jpg
:~ sector 682798 (offset: 176 ) size: 90 Bytes / resident
:~   :~ other files: [4800000002b0001] MyPhoto5.jpg
:~ Overlapping files=[480000001000000] IMG_3493.JPG
:~ MFT number=67
:~ Parent MFT number=66

SF/Sea-Lions/IMG_3535.JPG
:~ Id=440002
```



```
!! Size=3.55 MB (3,718,479 Bytes)
!! Created=11/22/2022 01:25:06 PM
!! Modified=6/5/2009 06:55:56 PM
!! Accessed=11/22/2022 01:25:06 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 218288 size: 3.55 MB (3,718,479 Bytes) / first data
!!   other files: [4800000002d0001] IMG_0201.JPG
!! sector 682800 (offset: 80 ) size: 72 Bytes / resident
!!   other files: [4800000002d0001] IMG_0201.JPG
!! sector 682800 (offset: 176 ) size: 90 Bytes / resident
!!   other files: [4800000002e0001] IMG_0211.JPG
!! Overlapping files=[480000001000001] IMG_3535.JPG
!! MFT number=68
!! Parent MFT number=66

SF/Sea-Lions/IMG_3542.JPG
!! Id=450002
!! Size=3.92 MB (4,110,749 Bytes)
!! Created=11/22/2022 01:25:06 PM
!! Modified=6/5/2009 06:57:38 PM
!! Accessed=11/22/2022 01:25:07 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 225552 size: 3.92 MB (4,110,749 Bytes) / first data
!!   other files: [4800000002e0001] IMG_0211.JPG
!! sector 682802 (offset: 80 ) size: 72 Bytes / resident
!!   other files: [4800000002f0001] IMG_0250.JPG
!! sector 682802 (offset: 176 ) size: 90 Bytes / resident
!!   other files: [4800000002f0001] IMG_0250.JPG
!! Overlapping files=[480000001000002] IMG_3542.JPG
!! MFT number=69
!! Parent MFT number=66

SF/Sea-Lions/IMG_3579.JPG
!! Id=460002
!! Size=3.92 MB (4,109,345 Bytes)
!! Created=11/22/2022 01:25:07 PM
!! Modified=6/5/2009 06:59:32 PM
!! Accessed=11/22/2022 01:25:07 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 233584 size: 3.92 MB (4,109,345 Bytes) / first data
!!   other files: [480000000300001] IMG_0283.JPG
!! sector 682804 (offset: 80 ) size: 72 Bytes / resident
!!   other files: [480000000300001] IMG_0283.JPG
!! sector 682804 (offset: 176 ) size: 90 Bytes / resident
!!   other files: [480000000310001] IMG_0389.JPG
!! Overlapping files=[480000001000003] IMG_3579.JPG
!! MFT number=70
```

```

:! Parent MFT number=66

SF/Sea-Lions/IMG_3580.JPG
:! Id=470002
:! Size=3.35 MB (3,510,477 Bytes)
:! Created=11/22/2022 01:25:08 PM
:! Modified=6/5/2009 06:59:40 PM
:! Accessed=11/22/2022 01:25:08 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 241616 size: 3.35 MB (3,510,477 Bytes) / first data
   :! other files: [480000000310001] IMG_0389.JPG
:! sector 682806 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000320001] IMG_0390.JPG
:! sector 682806 (offset: 176 ) size: 90 Bytes / resident
   :! other files: [480000000320001] IMG_0390.JPG
:! Overlapping files=[480000001000004] IMG_3580.JPG
:! MFT number=71
:! Parent MFT number=66

SF/Sea-Lions/IMG_3581.JPG
:! Id=480002
:! Size=4.09 MB (4,285,353 Bytes)
:! Created=11/22/2022 01:25:08 PM
:! Modified=6/5/2009 06:59:48 PM
:! Accessed=11/22/2022 01:25:09 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 248480 size: 4.09 MB (4,285,353 Bytes) / first data
   :! other files: [480000000330001] IMG_0391.JPG
:! sector 682808 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000330001] IMG_0391.JPG
:! sector 682808 (offset: 176 ) size: 90 Bytes / resident
   :! other files: [480000000340001] IMG_3694.JPG
:! Overlapping files=[480000001000005] IMG_3581.JPG
:! MFT number=72
:! Parent MFT number=66

SF/Sea-Lions/IMG_3589.JPG
:! Id=490002
:! Size=4.44 MB (4,651,043 Bytes)
:! Created=11/22/2022 01:25:09 PM
:! Modified=6/5/2009 07:00:18 PM
:! Accessed=11/22/2022 01:25:10 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 256856 size: 4.44 MB (4,651,043 Bytes) / first data
   :! other files: [480000000340001] IMG_3694.JPG
:! sector 682810 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000350001] IMG_3699.JPG
```

```
!! sector 682810 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [480000000350001] IMG_3699.JPG
!! Overlapping files=[480000001000006] IMG_3589.JPG
!! MFT number=73
!! Parent MFT number=66

SF/IMG_0869.JPG
!! Id=370001
!! Size=3.53 MB (3,698,659 Bytes)
!! Created=11/22/2022 12:35:27 PM
!! Modified=5/30/2009 10:13:46 AM
!! Accessed=11/22/2022 01:22:26 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 111224 size: 3.53 MB (3,698,659 Bytes) / first data
  !! other files: [480000000010000] $MFTMirr
!! sector 682774 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000010000] $MFTMirr
!! sector 682774 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [480000000020000] $LogFile
!! MFT number=55
!! Parent MFT number=54

SF/IMG_0873.JPG
!! Id=380001
!! Size=5.61 MB (5,881,104 Bytes)
!! Created=11/22/2022 12:35:28 PM
!! Modified=5/30/2009 10:15:56 AM
!! Accessed=11/22/2022 01:22:28 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 118448 size: 5.61 MB (5,881,104 Bytes) / first data
  !! other files: [480000000020000] $LogFile
!! sector 682776 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000040000] $AttrDef
!! sector 682776 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [480000000040000] $AttrDef
!! MFT number=56
!! Parent MFT number=54

SF/IMG_0890.JPG
!! Id=390001
!! Size=5.40 MB (5,663,358 Bytes)
!! Created=11/22/2022 12:35:29 PM
!! Modified=5/30/2009 10:47:26 AM
!! Accessed=11/22/2022 01:22:29 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 129936 size: 5.40 MB (5,663,358 Bytes) / first data
  !! other files: [480000000060000] $Bitmap
```

```

:~ sector 682778 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [480000000060000] $Bitmap
:~ sector 682778 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [480000000070000] $Boot
:~ MFT number=57
:~ Parent MFT number=54

SF/IMG_1739.JPG
:~ Id=3a0001
:~ Size=4.07 MB (4,266,181 Bytes)
:~ Created=11/22/2022 12:35:30 PM
:~ Modified=6/3/2009 09:59:04 AM
:~ Accessed=11/22/2022 01:22:30 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 141000 size: 4.07 MB (4,266,181 Bytes) / first data
  :~ other files: [480000000070000] $Boot
:~ sector 682780 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [480000000070000] $Boot
:~ sector 682780 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [4800000000a0000] $UpCase
:~ MFT number=58
:~ Parent MFT number=54

SF/IMG_3460.JPG
:~ Id=3b0001
:~ Size=4.38 MB (4,593,453 Bytes)
:~ Created=11/22/2022 12:35:31 PM
:~ Modified=6/5/2009 04:58:08 PM
:~ Accessed=11/22/2022 01:22:30 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 149336 size: 4.38 MB (4,593,453 Bytes) / first data
  :~ other files: [4800000000a0000] $UpCase
:~ sector 682782 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [4800000000a0000] $UpCase
:~ sector 682782 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [480000000200001] $Tops
:~ MFT number=59
:~ Parent MFT number=54

SF/IMG_3461.JPG
:~ Id=3c0001
:~ Size=3.91 MB (4,102,032 Bytes)
:~ Created=11/22/2022 12:35:31 PM
:~ Modified=6/5/2009 04:58:26 PM
:~ Accessed=11/22/2022 01:22:31 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 158312 size: 3.91 MB (4,102,032 Bytes) / first data
```

```
    :! other files: [480000000200001] $Tops
:! sector 682784 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [480000000200001] $Tops
:! sector 682784 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [480000000210001] $TxfLog.blf
:! MFT number=60
:! Parent MFT number=54

SF/IMG_3476.JPG
:! Id=3d0001
:! Size=3.92 MB (4,114,595 Bytes)
:! Created=11/22/2022 12:35:32 PM
:! Modified=6/5/2009 05:02:50 PM
:! Accessed=11/22/2022 01:22:32 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 166328 size: 3.92 MB (4,114,595 Bytes) / first data
    :! other files: [480000000210001] $TxfLog.blf
:! sector 682786 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [480000000220001] $TxfLogContainer000000000000000000000001
:! sector 682786 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [480000000220001] $TxfLogContainer000000000000000000000001
:! MFT number=61
:! Parent MFT number=54

SF/IMG_3478.JPG
:! Id=3e0001
:! Size=4.74 MB (4,968,784 Bytes)
:! Created=11/22/2022 12:35:33 PM
:! Modified=6/5/2009 05:03:22 PM
:! Accessed=11/22/2022 01:22:33 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
:! sector 174376 size: 4.74 MB (4,968,784 Bytes) / first data
    :! other files: [480000000230001] $TxfLogContainer000000000000000000000002
:! sector 682788 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [480000000230001] $TxfLogContainer000000000000000000000002
:! sector 682788 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [480000000250001] WPSettings.dat
:! MFT number=62
:! Parent MFT number=54

SF/IMG_3479.JPG
:! Id=3f0001
:! Size=4.28 MB (4,484,110 Bytes)
:! Created=11/22/2022 12:35:34 PM
:! Modified=6/5/2009 05:03:42 PM
:! Accessed=11/22/2022 01:22:34 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Existing file)
:! Regions (sector size=512B):
```

```

:~ sector 184088 size: 4.28 MB (4,484,110 Bytes) / first data
  :~ other files: [480000000250001] WPSettings.dat
:~ sector 682790 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [480000000250001] WPSettings.dat
:~ sector 682790 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [480000000270001] MyPhoto1.jpg
:~ MFT number=63
:~ Parent MFT number=54

SF/IMG_3480.JPG
:~ Id=400001
:~ Size=4.28 MB (4,491,209 Bytes)
:~ Created=11/22/2022 12:35:34 PM
:~ Modified=6/5/2009 05:03:48 PM
:~ Accessed=11/22/2022 01:24:01 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 192848 size: 4.28 MB (4,491,209 Bytes) / first data
  :~ other files: [480000000270001] MyPhoto1.jpg
:~ sector 682792 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [480000000280001] MyPhoto2.jpg
:~ sector 682792 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [480000000280001] MyPhoto2.jpg
:~ MFT number=64
:~ Parent MFT number=54

SF/IMG_3481.JPG
:~ Id=410001
:~ Size=3.38 MB (3,541,845 Bytes)
:~ Created=11/22/2022 12:35:35 PM
:~ Modified=6/20/2009 11:00:56 AM
:~ Accessed=11/22/2022 01:23:57 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
:~ sector 201624 size: 3.38 MB (3,541,845 Bytes) / first data
  :~ other files: [480000000290001] MyPhoto3.jpg
:~ sector 682794 (offset: 80 ) size: 72 Bytes / resident
  :~ other files: [480000000290001] MyPhoto3.jpg
:~ sector 682794 (offset: 176 ) size: 90 Bytes / resident
  :~ other files: [4800000002a0001] MyPhoto4.JPG
:~ MFT number=65
:~ Parent MFT number=54

SF/IMG_3493.JPG
:~ Id=1000000
:~ Size=4.75 MB (4,985,023 Bytes)
:~ Flags=deleted
:~ Created=11/22/2022 12:35:36 PM
:~ Modified=6/5/2009 06:50:22 PM
:~ Accessed=11/22/2022 12:35:37 PM
:~ File type=JPEG Digital Camera
```

```
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000430002])
!! Regions (sector size=512B):
!! sector 208544 size: 4.75 MB (4,985,023 Bytes) / first data
!! other files: [4800000005b0001] IMG_0547.JPG
!! sector 682796 (offset: 80 ) size: 72 Bytes / resident
!! other files: [4800000005b0001] IMG_0547.JPG
!! sector 682796 (offset: 176 ) size: 90 Bytes / resident
!! other files: [4800000005c0001] IMG_0550.JPG
!! Overlapping files=[480000000430002] IMG_3493.JPG
!! MFT number=66
!! Parent MFT number=54
```

SF/IMG\_3535.JPG

```
!! Id=1000001
!! Size=3.55 MB (3,718,479 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:37 PM
!! Modified=6/5/2009 06:55:56 PM
!! Accessed=11/22/2022 12:35:37 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000440002])
!! Regions (sector size=512B):
!! sector 218288 size: 3.55 MB (3,718,479 Bytes) / first data
!! other files: [4800000005c0001] IMG_0550.JPG
!! sector 682798 (offset: 80 ) size: 72 Bytes / resident
!! other files: [4800000005d0001] IMG_0551.JPG
!! sector 682798 (offset: 176 ) size: 90 Bytes / resident
!! other files: [4800000005d0001] IMG_0551.JPG
!! Overlapping files=[480000000440002] IMG_3535.JPG
!! MFT number=67
!! Parent MFT number=54
```

SF/IMG\_3542.JPG

```
!! Id=1000002
!! Size=3.92 MB (4,110,749 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:37 PM
!! Modified=6/5/2009 06:57:38 PM
!! Accessed=11/22/2022 12:35:38 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000450002])
!! Regions (sector size=512B):
!! sector 225552 size: 3.92 MB (4,110,749 Bytes) / first data
!! other files: [4800000005e0001] MyPhoto6.JPG
!! sector 682800 (offset: 80 ) size: 72 Bytes / resident
!! other files: [4800000005e0001] MyPhoto6.JPG
!! sector 682800 (offset: 176 ) size: 90 Bytes / resident
!! other files: [4800000005f0001] MyPhoto7.JPG
!! Overlapping files=[480000000450002] IMG_3542.JPG
!! MFT number=68
```

```
!! Parent MFT number=54

SF/IMG_3579.JPG
!! Id=1000003
!! Size=3.92 MB (4,109,345 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:38 PM
!! Modified=6/5/2009 06:59:32 PM
!! Accessed=11/22/2022 12:35:39 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000460002])
!! Regions (sector size=512B):
!! sector 233584 size: 3.92 MB (4,109,345 Bytes) / first data
!! other files: [4800000005f0001] MyPhoto7.JPG
!! sector 682802 (offset: 80 ) size: 72 Bytes / resident
!! other files: [480000000600001] MyPhoto8.JPG
!! sector 682802 (offset: 176 ) size: 90 Bytes / resident
!! other files: [480000000600001] MyPhoto8.JPG
!! Overlapping files=[480000000460002] IMG_3579.JPG
!! MFT number=69
!! Parent MFT number=54

SF/IMG_3580.JPG
!! Id=1000004
!! Size=3.35 MB (3,510,477 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:39 PM
!! Modified=6/5/2009 06:59:40 PM
!! Accessed=11/22/2022 12:35:39 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000470002])
!! Regions (sector size=512B):
!! sector 241616 size: 3.35 MB (3,510,477 Bytes) / first data
!! other files: [480000000610001] MyPhoto9.JPG
!! sector 682804 (offset: 80 ) size: 72 Bytes / resident
!! other files: [480000000610001] MyPhoto9.JPG
!! sector 682804 (offset: 176 ) size: 90 Bytes / resident
!! other files: [480000000630001] 20190822_100644.jpg
!! Overlapping files=[480000000470002] IMG_3580.JPG
!! MFT number=70
!! Parent MFT number=54

SF/IMG_3581.JPG
!! Id=1000005
!! Size=4.09 MB (4,285,353 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:39 PM
!! Modified=6/5/2009 06:59:48 PM
!! Accessed=11/22/2022 12:35:40 PM
!! File type=JPEG Digital Camera
```



```
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000480002])
!! Regions (sector size=512B):
!! sector 248480 size: 4.09 MB (4,285,353 Bytes) / first data
!! other files: [480000000630001] 20190822_100644.jpg
!! sector 682806 (offset: 80 ) size: 72 Bytes / resident
!! other files: [480000000640001] 20190822_101620.jpg
!! sector 682806 (offset: 176 ) size: 90 Bytes / resident
!! other files: [480000000640001] 20190822_101620.jpg
!! Overlapping files=[480000000480002] IMG_3581.JPG
!! MFT number=71
!! Parent MFT number=54
```

SF/IMG\_3589.JPG

```
!! Id=1000006
!! Size=4.44 MB (4,651,043 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:40 PM
!! Modified=6/5/2009 07:00:18 PM
!! Accessed=11/22/2022 12:35:41 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Below Average (Integrity OK, Beginning overwritten by
existing file [480000000490002])
!! Regions (sector size=512B):
!! sector 256856 size: 4.44 MB (4,651,043 Bytes) / first data
!! other files: [480000000650001] 20190822_102526.jpg
!! sector 682808 (offset: 80 ) size: 72 Bytes / resident
!! other files: [480000000650001] 20190822_102526.jpg
!! sector 682808 (offset: 176 ) size: 90 Bytes / resident
!! other files: [480000000660001] 20190822_103830.jpg
!! Overlapping files=[480000000490002] IMG_3589.JPG
!! MFT number=72
!! Parent MFT number=54
```

SF/IMG\_3590.JPG

```
!! Id=1000007
!! Size=4.67 MB (4,899,941 Bytes)
!! Flags=deleted
!! Created=11/22/2022 12:35:41 PM
!! Modified=6/5/2009 07:00:22 PM
!! Accessed=11/22/2022 12:35:42 PM
!! File type=NTFS Directory Entries
!! Recovery chances=Average (Signature, Unfragmented)
!! Regions (sector size=512B):
!! sector 265944 size: 4.67 MB (4,899,941 Bytes) / first data
!! other files: [480000000660001] 20190822_103830.jpg
!! sector 682810 (offset: 80 ) size: 72 Bytes / resident
!! other files: [480000000670001] 20190822_104333.jpg
!! sector 682810 (offset: 176 ) size: 90 Bytes / resident
!! other files: [480000000670001] 20190822_104333.jpg
!! MFT number=73
!! Parent MFT number=54
```

```
SF/IMG_3591.JPG
:! Id=4a0001
:! Size=4.08 MB (4,280,042 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:42 PM
:! Modified=6/5/2009 07:00:22 PM
:! Accessed=11/22/2022 12:35:42 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Integrity OK, Unfragmented)
:! Regions (sector size=512B):
:! sector 275520 size: 4.08 MB (4,280,042 Bytes) / first data
   :! other files: [480000000370001] IMG_0869.JPG
:! sector 682812 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000370001] IMG_0869.JPG
:! sector 682812 (offset: 176 ) size: 90 Bytes / resident
   :! other files: [480000000380001] IMG_0873.JPG
:! MFT number=74
:! Parent MFT number=54

SF/IMG_3592.JPG
:! Id=4b0001
:! Size=5.04 MB (5,285,211 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:42 PM
:! Modified=6/5/2009 07:00:22 PM
:! Accessed=11/22/2022 12:35:43 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Good (Integrity OK, Unfragmented)
:! Regions (sector size=512B):
:! sector 283880 size: 5.04 MB (5,285,211 Bytes) / first data
   :! other files: [480000000380001] IMG_0873.JPG
:! sector 682814 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000390001] IMG_0890.JPG
:! sector 682814 (offset: 176 ) size: 90 Bytes / resident
   :! other files: [480000000390001] IMG_0890.JPG
:! MFT number=75
:! Parent MFT number=54

SF/IMG_3593.JPG
:! Id=4c0001
:! Size=4.74 MB (4,969,442 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:43 PM
:! Modified=6/5/2009 07:00:26 PM
:! Accessed=11/22/2022 12:35:44 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Average (Signature, Unfragmented)
:! Regions (sector size=512B):
:! sector 294208 size: 4.74 MB (4,969,442 Bytes) / first data
   :! other files: [4800000003a0001] IMG_1739.JPG
:! sector 682816 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [4800000003a0001] IMG_1739.JPG
:! sector 682816 (offset: 176 ) size: 90 Bytes / resident
```

```
    :! other files: [4800000003b0001] IMG_3460.JPG
:! MFT number=76
:! Parent MFT number=54

SF/IMG_3594.JPG
:! Id=4d0001
:! Size=4.69 MB (4,917,237 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:44 PM
:! Modified=6/5/2009 07:00:30 PM
:! Accessed=11/22/2022 12:35:45 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Average (Signature, Unfragmented)
:! Regions (sector size=512B):
:! sector 303920 size: 4.69 MB (4,917,237 Bytes) / first data
    :! other files: [4800000003b0001] IMG_3460.JPG
:! sector 682818 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [4800000003c0001] IMG_3461.JPG
:! sector 682818 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [4800000003c0001] IMG_3461.JPG
:! MFT number=77
:! Parent MFT number=54

SF/IMG_3595.JPG
:! Id=4e0001
:! Size=5.09 MB (5,338,697 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:45 PM
:! Modified=6/5/2009 07:00:32 PM
:! Accessed=11/22/2022 12:35:46 PM
:! Recovery chances=Average (Unrecognized, Unfragmented)
:! Regions (sector size=512B):
:! sector 313528 size: 5.09 MB (5,338,697 Bytes) / first data
    :! other files: [4800000003d0001] IMG_3476.JPG
:! sector 682820 (offset: 80 ) size: 72 Bytes / resident
    :! other files: [4800000003d0001] IMG_3476.JPG
:! sector 682820 (offset: 176 ) size: 90 Bytes / resident
    :! other files: [4800000003e0001] IMG_3478.JPG
:! MFT number=78
:! Parent MFT number=54

SF/IMG_3596.JPG
:! Id=4f0001
:! Size=4.93 MB (5,174,072 Bytes)
:! Flags=deleted
:! Created=11/22/2022 12:35:46 PM
:! Modified=6/5/2009 07:00:34 PM
:! Accessed=11/22/2022 12:35:47 PM
:! File type=JPEG Digital Camera
:! Recovery chances=Average (Signature, Unfragmented)
:! Regions (sector size=512B):
:! sector 323960 size: 4.93 MB (5,174,072 Bytes) / first data
    :! other files: [4800000003e0001] IMG_3478.JPG
```

```

:~ sector 682822 (offset: 80 ) size: 72 Bytes / resident
:~ other files: [4800000003f0001] IMG_3479.JPG
:~ sector 682822 (offset: 176 ) size: 90 Bytes / resident
:~ other files: [4800000003f0001] IMG_3479.JPG
:~ MFT number=79
:~ Parent MFT number=54

SF/IMG_3608.JPG
:~ Id=500001
:~ Size=5.01 MB (5,257,021 Bytes)
:~ Flags=deleted
:~ Created=11/22/2022 12:35:47 PM
:~ Modified=6/5/2009 07:01:28 PM
:~ Accessed=11/22/2022 12:35:48 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Average (Signature, Unfragmented)
:~ Regions (sector size=512B):
:~ sector 334072 size: 5.01 MB (5,257,021 Bytes) / first data
:~ other files: [480000000400001] IMG_3480.JPG
:~ sector 682824 (offset: 80 ) size: 72 Bytes / resident
:~ other files: [480000000400001] IMG_3480.JPG
:~ sector 682824 (offset: 176 ) size: 90 Bytes / resident
:~ other files: [480000000410001] IMG_3481.JPG
:~ MFT number=80
:~ Parent MFT number=54

SF/IMG_3627.JPG
:~ Id=510001
:~ Size=3.48 MB (3,651,691 Bytes)
:~ Flags=deleted
:~ Created=11/22/2022 12:35:48 PM
:~ Modified=6/5/2009 07:02:36 PM
:~ Accessed=11/22/2022 12:35:48 PM
:~ Recovery chances=Average (Unrecognized, Unfragmented)
:~ Regions (sector size=512B):
:~ sector 344344 size: 3.48 MB (3,651,691 Bytes) / first data
:~ other files: [480000000410001] IMG_3481.JPG
:~ sector 682826 (offset: 80 ) size: 72 Bytes / resident
:~ other files: [480000001000000] IMG_3493.JPG
:~ sector 682826 (offset: 176 ) size: 90 Bytes / resident
:~ other files: [480000001000000] IMG_3493.JPG
:~ MFT number=81
:~ Parent MFT number=54

MyPhoto6.JPG
:~ Id=5e0001
:~ Size=1.07 MB (1,123,560 Bytes)
:~ Created=11/22/2022 12:35:56 PM
:~ Modified=4/29/2009 02:54:46 AM
:~ Accessed=11/22/2022 12:35:56 PM
:~ File type=JPEG Digital Camera
:~ Recovery chances=Good (Existing file)
:~ Regions (sector size=512B):
```

```
!! sector 436440 size: 1.07 MB (1,123,560 Bytes) / first data
  !! other files: [4800000004c0001] IMG_3593.JPG
!! sector 682852 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [4800000004d0001] IMG_3594.JPG
!! sector 682852 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [4800000004d0001] IMG_3594.JPG
!! MFT number=94
!! Parent MFT number=5
```

#### MyPhoto7.JPG

```
!! Id=5f0001
!! Size=842.76 KB (862,983 Bytes)
!! Created=11/22/2022 12:35:56 PM
!! Modified=4/29/2009 02:55:06 AM
!! Accessed=11/22/2022 12:35:56 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 438640 size: 842.76 KB (862,983 Bytes) / first data
  !! other files: [4800000004e0001] IMG_3595.JPG
!! sector 682854 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [4800000004e0001] IMG_3595.JPG
!! sector 682854 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [4800000004f0001] IMG_3596.JPG
!! MFT number=95
!! Parent MFT number=5
```

#### MyPhoto8.JPG

```
!! Id=600001
!! Size=997.99 KB (1,021,937 Bytes)
!! Created=11/22/2022 12:35:56 PM
!! Modified=4/29/2009 02:55:30 AM
!! Accessed=11/22/2022 12:35:57 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
!! Regions (sector size=512B):
!! sector 440328 size: 997.99 KB (1,021,937 Bytes) / first data
  !! other files: [4800000004f0001] IMG_3596.JPG
!! sector 682856 (offset: 80 ) size: 72 Bytes / resident
  !! other files: [480000000500001] IMG_3608.JPG
!! sector 682856 (offset: 176 ) size: 90 Bytes / resident
  !! other files: [480000000500001] IMG_3608.JPG
!! MFT number=96
!! Parent MFT number=5
```

#### MyPhoto9.JPG

```
!! Id=610001
!! Size=3.37 MB (3,533,017 Bytes)
!! Created=11/22/2022 12:35:57 PM
!! Modified=4/29/2009 02:56:50 AM
!! Accessed=11/22/2022 12:35:57 PM
!! File type=JPEG Digital Camera
!! Recovery chances=Good (Existing file)
```

```

:! Regions (sector size=512B):
:! sector 442328 size: 3.37 MB (3,533,017 Bytes) / first data
   :! other files: [480000000510001] IMG_3627.JPG
:! sector 682858 (offset: 80 ) size: 72 Bytes / resident
   :! other files: [480000000510001] IMG_3627.JPG
:! sector 682858 (offset: 176 ) size: 90 Bytes / resident
   :! other files: [480000000530001] IMG_0510.JPG
:! MFT number=97
:! Parent MFT number=5


```

### Other recovery list formats

You may export recovery lists in the following formats:

#### XML format


##### Export Recovery List dialog box for the XML format



#### JSON format

Custom recovery lists in the text format contains more information about files than simple recovery lists.


##### Export Recovery List dialog box for the JSON format




#### CSV format

Custom recovery lists in the text format contains more information about files than simple recovery lists.

##### Export Recovery List dialog box for the CSV format



### CSV Options dialog box




## 3.8 Drive Copy Wizard

You may copy any object in the Drives panel to any other object, if there is enough space on the target one. Before **Copy object to...** becomes enabled on the **Create** menu, you need to enable writing.



To enable writing,

- 1 In the **R-Studio** main panel, select the **Tools** menu, then **Settings**, and select **Enable Write** on the [Settings](#) dialog box.
- > **The Copy object to... will be enabled on the Create menu.**  
Now objects can be copied.

While the objects are being copied, you may change some parameters and view the [I/O monitor](#) on the Object Copy Progress dialog box.



You may change some options during the copy process



Depending on the objects to copy and your tasks, you may do:


### Binary (byte to byte copy)

An exact copy of the source object (or a part thereof) to the destination device (from its beginning or a specified offset). Any object may be copied to any object this way.

### To perform a binary copy of an object,


- 1 Select **Copy object to...** on the **Create menu**
- 2 Select a **source and destination objects in the Drives Copy Wizard panel and click the Next button**

Drives Copy Wizard



- 3 Select **Binary (byte to byte) copy** on the **Copy Options dialog box, specify copy options, and click the Next button**

Copy options dialog box



### Copy options


Source	
Copy whole object	Select this option if you want to copy the entire source object to the destination one
Copy range	Select this option if you want to copy a part of the source object



Offset	Specify the offset from which the source object data will be copied to the destination object
Size	Specify the size of the source object data which will be copied to the destination object
<b>Destination</b>	
Offset	Specify the offset on the destination object to which the source object data will be copied

### 3 View the copy task settings on the Drives Copy Wizard and click the Finish button

Drives Copy Wizard



or click the <- Drive Copy Wizard button to edit the copy parameters

#### > R-Studio will start copying data from the source object to the destination one.

### Smart partition copy


Only [partitions](#) can be copied with this option to other partitions or empty spaces. You may change some parameters of the the copied partition(s) on the destination drive.

### To perform a smart partition copy of a partition,

#### 1 Select Copy object to... on the Create menu


## 2 Select source and destination partitions in the Drives Copy Wizard panel and click the Next button

Drives Copy Wizard



## 3 Select Smart partition copy in the Copy Options panel, specify copy options, and click the Next button

Copy options dialog box




### Copy options

Destination	
Copy without stretching	Select this option if you want to copy the partition exactly to the destination place
Copy to:	Select this option if you want to change some parameters of the copied partition on the destination place
Free space before	Specify how much space will be left empty before the start of the copied partition
Partition size	Select this option and specify the new size of the copied partition
Partition type Primary (Active)? Primary/Logical	Specify the type of the partition to be copied. Do not change this setting unless you have serious reasons to do so.

### 3 View the copy task settings on the Drives Copy Wizard and click the Finish button

#### Drives Copy Wizard



or click the **Drive Copy Wizard** button to edit the copy parameters

- > **R-Studio will start copying data from the source partition to the destination place.**


#### Smart drive copy

Only whole drives can be copied with this option to other drives. You may change some parameters of the copied drives.


To perform a smart drive copy of a drive,

- 1 Select **Copy object to...** on the **Create** menu
- 2 Select a source and destination drives in the **Drives Copy Wizard** panel and click the **Next** button

#### Drives Copy Wizard



### 3 Select Smart drive copy in the Copy Options panel, specify copy options, and click the Next button Copy options dialog box




#### Copy options

Copying mode	
Copy all partitions onto original places	Select this option if you want to copy all partitions to their original places.
One partition after another	Select this option if you want to copy the partitions one after another preserving their space. If there is empty space between the partitions, it will be omitted. Otherwise it is similar to Copy all partitions onto original places. If Fixed active partition is selected, the original offset/size of the active partition will be preserved (in case the loader has links to it).
Expand/shrink partition to whole drive	Specify this option if you want to proportionally expand/shrink the selected partitions to occupy the entire target drive. If Fixed active partition is selected, the original offset/size of the active partition will be preserved (in case the loader has links to it).

### 3 View the copy task settings on the Drives Copy Wizard and click the Finish button

#### Drives Copy Wizard




or click the **Cancel** button to cancel this process.

- > R-Studio will start copying data from the source drive to the destination one.

## 3.9 File Maps

R-Studio can show file maps. Right-click the file and select **Map of file** in their shortcut menu.

#### File Map



## 3.10 I/O Monitor and Sector Map Files


These features greatly improves working with failing drives for **R-Studio**.

### I/O Monitor

**I/O Monitor** allows you to inspect the process of drive input/output operations in real time. When **R-Studio** performs a disk operation the **I/O Monitor** button becomes active.

Click this button, and the **I/O Monitor** will appear.

### I/O Monitor



You may also start **I/O Monitor** from the shortcut menu and progress dialog boxes during various drive operations.

### Sector Map Files

[Sector map files](#) are files that contain information about conditions of drive sectors, which may be good, bad, slow, and unstable. **R-Studio** estimates chances for successful file recovery basing on these files and avoiding unnecessary attempts to read [bad sectors](#). Sector map files are crucial for [multi-pass imaging](#).


**R-Studio** creates its own sector map files or can import such files created from other disk imaging programs. Currently **R-Studio** supports sector map files from [HDDSuperClone](#) and [DDRescue](#).

**To open, save or clean a sector map file for an object,**

- \* **Right-click the object and select Open Sector Map, Save Sector Map, or Clean Sector Map, respectively, on the shortcut menu.**


You may look at the graphical representation of the loaded sector map by starting **I/O Monitor**.

### Sector Map



### 3.11 Runtime Imaging

Runtime imaging is [image](#) creation for a drive object performed simultaneously with other data read operations from this drive. When **R-Studio** reads data from a certain area of the source (a drive, [partition](#), or region), it writes the data to the target which can be either a dedicated drive or an image file. When the data from this area is needed again, **R-Studio** reads it from the target rather than the source thus reducing access to the source. This is very important for faulty or unstable drives which health may be constantly deteriorating during data recovery operations.




**R-Studio** also creates a [sector map file](#) during runtime imaging.

**To start runtime imaging of an object,**  
*using a plain image file*

- 1 Select a drive object in the **R-Studio's Drives panel** and click the **Start Runtime Image** button, or right-click the object and select **Set Runtime Image** on the shortcut menu.



## Runtime imaging




Select **Plain** or [another image type](#) in the **Image type** field, specify the file name and path for the image and sector map files, and click the **OK** button. Don't select the **VMDK image file** unless you can disable writing to the drive later. Cloning to a physical drive is not recommended because Windows can write some data to the drive corrupting the imaged data when the image has been completed and runtime imaging is over.

**Plain image file** requires immediate allocation of disk space equal to the object size, whereas **VMDK image file** is growing gradually upon imaging progress.

### > R-Studio will turn on runtime imaging.

## Runtime imaging




Select the object and click the **Stop Runtime Imaging** button or item in the shortcut menu to turn runtime imaging off.

### using a physical drive

- 1 Select a drive object in the R-Studio's Drives panel and click the **Start Runtime Image** button, or right-click the object and select **Set Runtime Image** on the shortcut menu. 1



### Runtime imaging




Select **Physical drive** in the **Image type** field, specify the name and path for the sector map file, and click the **OK** button.

**Note:** all data on the drive will be destroyed.

- > **R-Studio will turn on runtime imaging.**


### Runtime imaging



Select the object and click the **Stop Runtime Imaging** button or select this item in the shortcut menu to turn runtime imaging off.

**R-Studio** stores the information about runtime configurations and asks the users whether they want to keep runtime imaging or discard it during its startup.

### Runtime imaging



This configuration will appear in **R-Studio**.

### Runtime imaging

Device/Disk	Label	FS	Start	Size
Local Computer				
KINGSTON SA400S37120G 03090005	50026877843A5618	#0 SATA2, SSD		111.79 GB
EFI system partition		FAT32	1 MB	100 MB
Microsoft reserved partition			101 MB	16 MB
C:	System	NTFS	117 MB	111.18 GB
Windows Recovery Partition		NTFS	111.29 GB	508 MB
Empty Space19			111.79 GB	1.44 MB
TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2, HDD		931.51 GB
D:	Data	NTFS	1 MB	931.51 GB
WDC WD1200BEVT-22ZCT0 11.01A11	WD-WXE808HN3826	#2 SATA2, HDD		111.79 GB
D:\Multipass\WDC WD1200BEVT-22ZCT0 11.01A11.vmdk				
E:	NTFS-Good	NTFS	1 MB	39.09 GB
F:	NTFS-Bad	NTFS	39.09 GB	72.70 GB

### Completing Runtime Image

You may complete the runtime image without browsing through the entire file system on the disk.

- 1 Select the object being imaged and click the **Complete Runtime Image** button, or right-click the object and select **Complete Runtime Image** on the shortcut menu.

### Runtime imaging

The screenshot shows the R-Studio Technician interface. The toolbar at the top contains various icons, with 'Complete Runtime Image' highlighted. The 'Device view' pane on the left shows a tree structure of disks and partitions. The selected disk is 'WDC WD1200BEVT-22ZCT0 11.01A11' with label 'WD-WXE808HN3826'. The right pane shows properties for the selected disk, including Name, Drive Type, OS Object, R-Studio Driver, Size, Logical Sector Size, Physical Sector Size, Partition Size, I/O Retries, Drive Control, and Physical Drive Geometry.

- > The Complete Runtime Imaging dialog box will appear.

### Runtime imaging


The screenshot shows the 'Complete Runtime Imaging' dialog box. The title bar reads 'Complete Runtime Imaging - WDC WD1200BEVT-22ZCT0 11.01A11.vmdk'. The dialog is divided into two sections: 'Bad sectors processing' and 'Multi-pass image creation'. Under 'Bad sectors processing', there is a checkbox for 'Perform reading in reverse order if possible' and a 'Drive sector map file' field. Under 'Multi-pass image creation', there are checkboxes for 'Minimum skip size', 'Maximum skip size', and 'Minimum I/O rate', each with a numeric input field. There is also a 'Number of retries (Retrying phase)' field. On the right side, there are checkboxes for 'Disable imaging phases' including 'Edges phase', 'Slow areas phase', 'Skipped blocks phase', 'Trimming phase', 'Scraping phase', and 'Retrying phase'. The 'Start' button is highlighted.

Select the necessary [parameters of multi-pass](#) imaging and select the **OK** button.

## > R-Studio will complete the creation of the runtime image.

If the runtime image has not been completed, you may resume it next time you start R-Studio.

### Runtime imaging




### Creating runtime image for individual files

You may create a runtime image containing only individual files rather than all data on the disk.


- 1 **Open the disk with the files, mark the files, and click the Save marked to runtime image button.** or right-click on the right pane, and select **Complete Runtime Image** on the shortcut menu.

### Runtime imaging



- > The Complete Runtime Imaging dialog box will appear.


### Runtime imaging



Select the necessary [parameters of multi-pass](#) imaging and select the **OK** button. You may Skip files with [bad sectors](#) if necessary.

- > R-Studio will complete the creation of the runtime image.  
You may open such images as regular ones.

### Runtime imaging



Such image contains information about the entire file system, but when a non-imaged file is opened, it'll contain only zeros.

## 3.12 Multi-pass Imaging

Multi-pass imaging is a process of [image](#) creation through several passes (phases). Each phase reads data from different areas of a hard drive, starting from areas with good sectors then going to slow sector areas and finishes with [bad sector](#) areas. This approach maximizes the amount of data that can be recovered from a failing drive and reduces it chances to fail during this process.

### ***Phase 1. Copying most good data from the drive***

In this phase, **R-Studio** reads data from drive by sector blocks, or groups of consecutive drive sectors read in one go. The phase is performed in several steps.

**Step 1. R-Studio** reads data from the drive until it runs into a block with bad or slow sector(s). Then it drops that block and jumps to another area until it finds a block with no bad or slow sectors. Then it continues reading data until it runs into another bad or slow block, and the process repeats. When this step is finished, most good data from the hard drive has been read, and **R-Studio** has detected the front blocks (edges) of bad and slow sector areas.

**Step 2. R-Studio** finds the rear edges of bad sector areas. It reads the skipped area from its rear end backwards until it runs into a block with a bad sector. Then **R-Studio** jumps to another bad sector area and the process is going on until all bad sector areas have been processed. When this step is finished, some good data from the hard drive has been read, and **R-Studio** has detected the rear edges of bad sector areas.

**Step 3. R-Studio** reads data from slow sector areas. It does that much the same way as for bad sector areas. When this step is finished, good data from slow sectors on the hard drive has been read, and **R-Studio** has detected the rear edges of slow sector areas.

**Step 4. R-Studio** finds the rear edges of bad sector areas in slow sector areas. When this step is finished, some new good data from slow sectors on the hard drive has been read, and **R-Studio** has detected the rear edges of all bad sectors within slow sector areas.

**Step 5. R-Studio** tries to read all skipped sector blocks. This is done without skipping bad sector blocks and checking read speed against minimum I/O rate.

When **Phase 1** is completed, **R-Studio** has read most of readable data and detected front and rear edges of all bad sector areas.

**R-Studio** tries to read the rest of data in the next phases, and does that sector by sector (rather than blocks).

### ***Phase 2. Trimming***

**R-Studio** detects the front and rear sectors of bad sector areas. When this step is finished, some new good data from bad sector areas has been read, and **R-Studio** has detected the front and rear sectors of all bad sector areas.

### ***Phase 3. Scraping***

**R-Studio** tries to read data from bad sector areas sector by sector.

### ***Phase 4. Retrying (mostly optional)***

**R-Studio** tries to read data from bad sectors through several attempts.

You may read more about this process in our article [Multi-pass imaging in R-Studio](#)

## **To create an image through multi-pass imaging,**

**1 Select an object in the R-Studio's Drives panel and click the Create Image button**

***Other ways to create the image***

- Select the object and select **Create Image** on the **Drive** menu




or

- Right-click the selected object and select **Create Image File** on the shortcut menu

## 2 Specify image options, a file name, and destination for the *image on the* Create Image dialog box and click the OK button

### Create Image (Bad sector processing) dialog box



### Bad sectors processing options

These parameters can be changed even while the process of image creation.	
Image filename	Specifies the name and path for the image file
Image type:	<p>Compressed image (R-Drive Image compatible): If this option is selected, <b>R-Studio</b> will create an image file which can be compressed, split into several parts, and password-protected. This image file is fully compatible with the images created by <b>R-Drive Image</b>, but incompatible with very old versions of <b>R-Studio</b>.</p> <p>Byte by byte image to a file: If this option is selected, <b>R-Studio</b> will create a simple exact copy of the object.</p> <p>Byte to byte image to a physical disk: <b>R-Studio</b> will create an exact copy of the disk on another hard drive. Data on the target drive will be overwritten. Available in the Corporate, Technician, and T80+ licenses.</p> <p>Some other image formats are also available in the Technician, and T80+ licenses. You may read more about these formats in the <a href="#">Supported Virtual Disk and Disk Image Formats</a> page.</p>
<a href="#">Drive sector map file</a>	A file with the sector map of the object to image. Optional for the RDI image type, mandatory for the byte-by-byte and VMDK image types.
Enable multi-pass image creation	Turns multi-pass imaging on and off.
Data to process	<p>All data: All data on the disk will be imaged.</p> <p>Existing files only (FS bitmap): Only the disk's area where existing files reside will be imaged.</p> <p>Unused clusters only: Only the disk's <a href="#">free space</a> will be imaged.</p> <p>You may image the existing files first and then unused clusters.</p>
Perform reading in reverse order if possible	Switches the direction of all phases/steps to reverse.
Minimum skip size	Minimum size of drive area to skip when a bad sector is encountered.

Maximum skip size	Maximum size of drive area to skip when a bad sector is encountered.
Number of retries (Retrying phase)	The number of read attempts in the Retrying phase.
Disable imaging phases	Multi-imaging phases that can be skipped. They can be skipped or added even during image creation
Start runtime imaging	Click this button to switch to <a href="#">runtime imaging</a> .

> **R-Studio will start creating the image, the Progress showing the progress.**

### Multi-pass imaging progress

The screenshot shows the R-Studio Technician interface during a multi-pass imaging process. The 'Device view' pane on the left lists the source disk (WDC WD1200BEVT-22ZCT0 11.01A11) and its partitions. The main window displays the progress of the image creation, including a progress bar and a detailed status window. The status window shows the following information:

- Time elapsed: 31m 41s, remaining: 46m 5s
- Creating image file of WDC WD1200BEVT-22ZCT0 11.0
- Multi-pass phase:
  - Rescued: 53.47 GB
  - Unprocessed left on device: 49.00 GB
  - Unprocessed for the operation: 49.00 GB
  - Skipped slow areas: 9.31 GB in 38149 blocks (block size: 256 KB)
  - Skipped bad areas: 14.12 MB in 59 blocks (block size: 256 KB)
  - Not yet trimmed: 768 KB in 6 blocks
  - Not yet scrapped: N/A
  - Bad sectors: N/A
  - Actual read speed: 44.26 MB/sec (average is 44.10 MB/sec)
  - Data processing speed: 28.79 MB/sec


The log window at the bottom shows several OS I/O error messages, indicating failed reads from the source disk.

You may change operation parameters during image creation. Click the **Options** button and change them accordingly.


### Drive Options tab

The screenshot shows the 'Options (Compressed drive image creation)' dialog box. The 'Drive Options' tab is selected, displaying the source disk path: WDC WD1200BEVT-22ZCT0 11.01A11 : WD-WXE808H-N3826. The 'Read retries count' is set to 'Default (0)'. The dialog has 'OK' and 'Cancel' buttons.

## Multi-pass imaging options tab




## Post Actions tab



When the imaging is over, **R-Studio** will show its results.

## Multi-pass imaging results



## 3.13 Reverse RAIDs

Reverse RAIDs is a technique that is reverse to creating virtual RAID. When creating a reverse RAID, the data from a real object is decomposed into virtual parents. Then data on those virtual parents can be processed like on real objects. They can be viewed, edited, imaged, copied to physical drives, etc.

### • [Reverse RAID of an Object](#)

This technique can be used to decompose data on a single volume into virtual parents. Then such virtual parents can be processed like on real objects. They can be viewed, edited, imaged, copied to physical drives, etc.



### • [Reverse RAID of a RAID](#)

This technique can be used to re-construct data on individual RAID drives when data on physical drives is corrupted, but can be recovered using RAID redundancy. A missing drive is an example of this case. Or if there are [bad sectors](#) scattered over the physical drives but the overall RAID integrity remains. Then the data can be copied to physical drives to create a healthy RAID.

**Note:** Many controllers write their own metadata to drives to recognize that the drives belong to certain RAIDs. Without that metadata they won't see those RAIDs. You have to write that metadata manually.

#### 3.13.1 Reverse RAID of an Object


This technique can be used to decompose data on a single object into virtual parents. Then such virtual parents can be processed like on real objects. They can be viewed, edited, imaged, copied to physical drives, etc.

Suppose you have an image of a former RAID 6 (Reed-Solomon) and you want to re-create data on individual drives from that RAID 6. You can do that by creating a reverse RAID of an [image](#).


**Note:** Many controllers write their own metadata to drives to recognize that the drives belong to certain RAIDs. Without that metadata they won't see those RAIDs. You have to write that metadata manually.

**To create a reverse RAID of a drive image (or other drive object),**


- 1 Right-click the drive object in the Drives panel and select **Create Reverse RAID** on the shortcut menu.



> The Reverse parents will appear in the Drives panel




Initially, the reverse RAID is set to its default values as RAID 5 on the Parents tab.



## 2 Adjust RAID parameters on the Parents tab, as necessary.

You need to add one reverse parent, change RAID type, and adjust RAID offset.



## > Process the appeared reverse parents in the Drives panel as real objects.

These parents can be imaged, viewed/edited, etc.

Device/Disk	Label	FS	Start	Size
Local Computer				
TOSHIBA DT01ACA100 MS20A...	44HSATLKS	#1 SAT...	0 Bytes	931.51 GB
Volume{3303cc57-3e4d-450...	Recovery	NTFS	1 MB	300 MB
EFI system partition		FAT32	301 MB	100 MB
Microsoft reserved partition			401 MB	128 MB
C:	System	NTFS	529 MB	292.01 GB
Volume{e0e573f2-14d5-404...	Data	NTFS	292.97 GB	638.54 GB
D:		NTFS	931.51 GB	1.69 MB
Empty Space25				
SAMSUNG SP0411N TW100...	S01JJ20XC75851	#2 AT...	0 Bytes	37.31 GB
Reverse RAID				18.65 GB
Reverse parent #A				18.65 GB
Reverse parent #B				18.65 GB
Reverse parent #C				18.65 GB
Reverse parent #D				18.65 GB
F:	NTFS-Test	NTFS	32 KB	6.76 GB
G:	FAT32-TEST	FAT32	6.76 GB	6.19 GB
H:	FAT-TEST	FAT16	12.95 GB	2.01 GB
Volume{c7a018fa-2f05-11e...	HFS-Test	HFS-	14.96 GB	6.67 GB
Harddisk\Volume25	Ext4FS-Test	Ext4	21.63 GB	6.52 GB
Empty Space31			28.15 GB	9.16 GB
Marvell SATA Config 1.01				
PIONEER DVD-RW DVR-219L 1.00				
E:				

### 3.13.2 Reverse RAID of a RAID

This technique can be used to re-construct data on individual RAID drives when data on physical drives is corrupted, but can be recovered using RAID redundancy.


Suppose you have a RAID 5 with one missing drive and you need to reconstruct data on that drive. You can do that by creating a reverse RAID for it and then copy data from that missing drive to a real one, or to an [image](#).

**Note:** Many controllers write their own metadata to drives to recognize that the drives belong to certain RAIDs. Without that metadata they won't see those RAIDs. You have to write that metadata manually.

### To create a reverse RAID of a RAID with a missing drive,

#### 1 Create a virtual RAID 5 of the existing drives or their images


Add a missing drive to the Parents tab.




If necessary, read the [Basic RAID 4 and RAID 5 Operations](#) and [Volumes Sets and RAIDs](#) help pages for details.

#### 2 Right-click the Virtual Block Raid in the Drives panel and select Create Reverse RAID on the shortcut menu.

> The Reverse parents will appear in the Drives panel



These parents may be processed as real objects, they can be imaged, viewed/edited. For your case the missing drive can be copied to a drive in the Drive Copy Wizard.



**Note:** The reverse parents contain the data that should be on the RAID parents, according to its layout, while RAID parents contain actual data, that may be corrupted.

### 3.14 Working with the Third-Party Hardware

The Technician/T80+ version of **R-Studio** can work together with [third-party hardware](#) developed for in-depth data recovery. Currently, the following devices are supported:

- [DeepSpar Disk Imager™](#)
- [DeepSpar USB Stabilizer](#)
- [DeepSpar RapidSpar](#)
- [PC-3000 UDMA hardware](#)

#### 3.14.1 DeepSpar Disk Imager™

**DeepSpar Disk Imager™ (DDI)** is an HDD imaging device specifically built for data recovery from drives with hardware issues. It greatly increases imaging speed, accuracy, and integrity of data retrieved from such drives.

The main features that **DDI** provides when working with drives are the following:

- Direct low-level access to a drive bypassing the computers BIOS.
- Disabling specific drive read/write heads.
- Disable SMART subsystem, Bad Sector Reallocation, and Read Look-Ahead
- Read sector timeout controlled by Software/Hardware/PHY drive reset commands
- Bit level analysis of corrupted data to filter out the read-write channel noise
- Fully customizable multi-pass imaging

And many more others an advanced drive imager must have. You may learn more about **DDI** on its vendor site: [DeepSpar Disk Imager™](#).


#### **DeepSpar Disk Imager™ basics**

The main idea of data recovery with **DDI** is to clone data from the source drive with a certain level of hardware malfunction to a clone drive and perform data recovery operations either from the clone drive or while data is being cloned. Such approach greatly reduces tear and wear of the source drive and reduces further deterioration of its state.

There are two modes in which **DDI** processes drives:


- **DDI** clones the entire source drive to the source one consequently, sector by sector. Any further data recovery will be made from the clone HDD.
- **DDI** clones those sectors of the source HDD which have been read during data recovery. Such readings are optimized to minimize the movement of the drive's head unit. All following reads from those sectors will be done from the clone drive. For example, if files are to be recovered from a [partition](#) on the drive, **DDI** will clone the boot record of the drive, the file table of the partition, and the sectors of the files. If the partition is scanned, the scanned sectors will be cloned, too. All consecutive operations, such as file preview, and so on, will be done from the clone drive. This greatly reduces the time necessary to perform the recovery operations and furthermore drive wear.

### DeepSpar Disk Imager™ board



Read the **DDI** documentation on how to install **DDI** connect the drives to **DDI** and start working with it.

The **DDI** board should be installed into a separate network computer (the **DDI computer**), and the source and clone drives should be connected to it. The **DDI** computer should be started using the boot USB stick supplied with the board. **R-Studio** running on another computer (the **R-Studio computer**) accesses the drive via the network. All data recovery operations will be done through this setup:



There may be several **DDI computers** on the network, **R-Studio** will connect to all of them. Such configuration may be useful for RAID recovery when several drives on the RAID have hardware problems.

### **Working with DDI**

To start working with **DDI**, its computer should be connected to **R-Studio**.

**To connect R-Studio to the DDI computer,**

- \* **Select Connect to DDI on the Drive menu**
- > **The drives connected to DDI will appear in the Drive pane.**

Device/Disk	Label	Interface/F	Start	Size
Local Computer				
> KINGSTON SA400S37120G 03090005	50026B77843A5618	#0 SATA2, SSD		111.79 GB
> TOSHIBA DT01ACA100 MS20A750	44H5ATLKS	#1 SATA2, HDD		931.51 GB
> ST380817AS 3.42	4MR29A6X	#2 SATA, HDD		74.53 GB
DDI Devices				
DDI-DS400521 - VProject#1	50026B77843A5618	DDI		111.79 GB
DDI-DS400522 - VProject#2	44H5ATLKS	DDI		931.51 GB
DDI-DS400523 - VProject#3	4MR29A6X	DDI		74.53 GB
Partition1	NTFS-Test	NTFS	512 KB	6.94 GB
Partition2	FAT32-TEST	FAT32	6.94 GB	36.23 GB
Partition3	FAT-TEST	FAT16	43.17 GB	2.01 GB
Empty Space32			45.18 GB	29.35 GB

Now it is possible to work with drives connected to **DDI** like all other drive objects in the **Drive** panel. For example, such drives may be included into [virtual RAIDs](#) and other compound objects.




### Viewing the drive map

A drive map shows the conditions for individual drive sectors. You may see which sectors are OK, bad, or unstable.

#### To view the drive map,

- \* Right-click the required drive/partition and select I/O Monitor on the shortcut menu, or  
select the object and select I/O Monitor on the Drive menu
- > The drive map will appear in the I/O Monitor window.

#### DDI I/O Monitor window




You may also [image individual files](#) and view [file maps](#).

R-Studio can also load and process [images](#) created with the **DeepSpar Disk Imager™**.

### Connecting to DeepSpar Disk Imager™ manually

If R-Studio cannot find **DeepSpar Disk Imager™**, the Select Interface dialog box will appear. Try to find the DDI interface manually.



### 3.14.2 DeepSpar USB Stabilizer

**This hardware works under Windows 10/11-64 bits**

**USB Stabilizer** is a device that allows any Windows software to reliably work with unstable/degraded USB storage devices providing a connection between the computer and source device. The storage devices can be hard drives, [SSD devices](#), USB memory sticks, memory cards connected through a special adapter, etc. Windows shows such device as if it was connected directly to the system providing access to it for **R-Studio**.



If any drive issue occurs, **USB Stabilizer** handles this issue preventing the system from freezes, crashes, or disconnecting the drive. Such handling may include various drive resets or even drive re-power without system losing the device.

You may learn more about **USB Stabilizer** on its vendor's [USB Stabilizer](#) or [our](#) sites.

#### Installing USB Stabilizer:

##### *USB Stabilizer Tech/Pro*

#### 1 Connect the **USB Stabilizer** to your computer and power it on

There should be no device connected.

The **USB STABILIZER** object should appear in the **Safely Remove Hardware** menu when **USB Stabilizer** is connected..

#### 2 Run **R-Studio**, locate the **DEEPSPAR NO DEVICE** object in the Device/Disk panel, and click the **Install driver button** on the **Properties** tab.


You may install the drivers either online or offline.

There should be no device connected.

The [USB STABILIZER](#) object should appear in the **Safely Remove Hardware** menu




## DeepSpar USB Stabilizer



R-Studio will start installing the drivers. You need to restart your system to complete installation.

- > The DEEPSPAR: POWER OFF object will appear in the the Device/Disk panel.

## DeepSpar USB Stabilizer



R-Studio is now ready for work with USB Stabilizer.

### USB Stabilizer Pro

- 1 Connect the USB Stabilizer to your computer and power it on

There should be no device connected.

The USB STABILIZER object should appear in the **Safely Remove Hardware** menu when **USB Stabilizer** is connected..

- 2 Run **USB Stabilizer Control Panel** that comes with **USB Stabilizer Pro** and click the **Install** button.

There should be no device connected.


## DeepSpar USB Stabilizer Pro



**Control Panel** will start installing the drivers. You need to restart your system to complete installation.

- > The **DEEPSPAR: POWER OFF** object will appear in the the Device/Disk panel.

## DeepSpar USB Tech Stabilizer




**R-Studio** is now ready for work with **USB Stabilizer**.

## Working with USB Stabilizer:


- 1 Connect the device for recovery to **USB Stabilizer** and click the **Power** button

### DeepSpar USB Stabilizer



- > R-Studio will show the **USB Stabilizer's drive**.

### DeepSpar USB Stabilizer




It may take quite a long time to turn the drive on depending on the drive conditions. **R-Studio** will show the **DEEPSPAR: DEVICE IS BUSY** line if there's not enough power for the hard drive to work. That may happen when computer's USB port cannot deliver enough power and the external power supply is disconnected.

**R-Studio** can now process the **USB Stabilizer drive** as it's a common drive connected to a USB port.

You may read about **USB Stabilizer** parameters in its manual.

You may change other parameters for **USB Stabilizer Pro** through its **Control Panel**.


### USB Control Panel Stabilizer



Read the **USB Stabilizer Pro** documentation for more details.


You may change these parameter during drive operations with **USB Stabilizer**.

### DeepSpar USB Stabilizer




You may also watch drive read operations in real time at the **I/O monitor**.

### .DeepSpar USB Stabilizer



You may specify the algorithm to process faulty drives. Click the **Edit algorithm** button and specify algorithm's parameters.

### .DeepSpar USB Stabilizer



### 3.14.3 DeepSpar RapidSpar™

**RapidSpar** is a specialized data recovery device from [DeepSpar](#) intended to extract data from problematic drives. Failing (source) and target drives are connected to the device, and it autonomously copies data from the source to the target in a way that maximizes the amount of successfully extracted data and minimizes possible damage to the source drive. The copy parameters can be quickly changed during this process directly on the device. Then the recovery software can read data from the target drive.

When connected to a PC, the specialized software (including **R-Studio**) can read (and clone) only those drive areas that contain the necessary files and folders to decrease time required for data recovery.

In addition, it's possible to perform some repair works with hard drives.

You may read more about **RapidSpar** on its [web site](#).



RapidSpar doesn't require any installed drivers.

### Working with RapidSpar:

- 1 Connect the source and target hard drives to RapidSpar and start the device. Refer to the **RapidSpar** manual for detailed instructions.

### DeepSpar RapidSpar

The screenshot shows the R-Studio Technician - Device view window. The left pane displays a tree view of the local computer's drives, with the DeepSpar RapidSpar Pro: DSR11 device selected. The right pane shows the properties for this device, including its name, drive type, and device identification details.

Device/Disk	Label	FS	Start	Size
WDC WDS500G2B0A-00SM50 40...	200619800287	#0 SAT...	0 Bytes	465.76 GB
Windows Recovery Partition	Recovery	NTFS	1 MB	499 MB
EFI system partition		FAT32	500 MB	100 MB
Microsoft reserved partition			600 MB	16 MB
C:		NTFS	616 MB	465.16 GB
DEEPSPAR: TOSHIBA MK8054GS...	49EFT1LYT	Local		
D:	RapidSpar	exFAT	64 KB	238.43 GB

**DeepSpar RapidSpar Pro: DSR11**

Clean device sector map:  Imaging strategy: Balanced

Name	Value
Drive Type	Physical Drive
Name	DEEPSPAR: TOSHIBA MK8054GSYF
RapidSpar Pro	DSR11755, Power off
<b>Drive Control</b>	
Maximum Transfer	8 MB
I/O Block Size	4 KB
Buffer Alignment	2 Bytes
<b>Device Identification</b>	
Vendor	TOSHIBA
Product	MK8054GSYF
Serial Number	49EFT1LYT
Bus Type	USBStabilizer


Log

Type	Date	Time	Text



> R-Studio will show the **RapidSpar** drive.

## DeepSpar RapidSpar




Read the **RapidSpar** documentation for the information about its parameters.

**R-Studio** can now process the **RapidSpar** drive as it's a common drive connected to a USB port.


You may change these parameter during drive operations with **RapidSpar**.

## DeepSpar RapidSpar



You may also watch drive read operations in real time at the I/O monitor.

## .DeepSpar RapidSpar



### 3.14.4 PC-3000 UDMA hardware

**PC-3000 UDMA** from [ACELab®](#) is a hardware-software solution for hard drive repair and data recovery. Its hardware part is a PCI-Express card that can work with both IDE and SATA hard drives providing access to hard drives with severe physical failures. Its software part is **Data Extractor UDMA** that performs actual data recovery. The **PC-3000 UDMA** card can be used alone for raw data extraction and drive repair.

**R-Studio** can work directly with the **PC-3000 UDMA** card as an alternative to data recovery software. Our article [Joint work of R-Studio and PC-3000 UDMA hardware](#) explains this in more detail.

### 3.15 Forensic Mode

**Note:** This feature is available for **R-Studio Technician/T80+** only!


When this mode is enabled, **R-Studio** will generate a [forensic](#) data collection audit log that can be presented at court hearings. This log includes information about a hardware configuration on which the forensic data collection takes place and MD5 for recovered files.

**Note:** A new log will be generated each time the hardware configuration is changed (a drive is connected/? disconnected, an external USB device is connected/?disconnected, etc)




**To enable this feature,**

- \* **Select Enable Forensic Mode on the Main tab of the [Settings](#) dialog box.**



The Forensic Log tab will appear on the Recover dialog box.

**Forensic Log tab**



Enter the required information on this tab and then go to the other tabs of the [Recovery](#) dialog box.

While file recovery, **R-Studio** will create forensic data collection audit log in the specified folder. Below is an example of such log.

```
***** Forensic Data Collection Audit Log
*****
```

R-Studio Technician

```
***** Drives Information
*****
```

```
- Drive Number 0 -----
* Drive Type [256 bytes]: Computer,Local Computer
* Name [30 bytes]: Local Computer
* OS [46 bytes]: Windows 10 Build 19044
* System [136 bytes]: 4 x Intel(R) Core(TM) i5-4570 CPU @ 3.20GHz, 3200 MHz, 16294
MB RAM

- Drive Number 4 -----
* Drive Type [256 bytes]: Physical Drive,Disk
```

```
* Name [62 bytes]: KINGSTON SA400S37120G 03090005
* OS Object [38 bytes]: \\.\PhysicalDrive0
* R-Studio Driver [44 bytes]: WinNT\Handle\Physical
* Size [8 bytes]: 111.7GB (234441648 sec)
* Sector Size [4 bytes]: 512B
* Partition Size [8 bytes]: 111.7GB (234441648 sec)
* GPT Disk GUID [74 bytes]: 69e6114c-6751-5e84-ed6d-8ece5d5616b4
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 4096
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 14593
  * Tracks Per Cylinder [4 bytes]: 255
  * Sectors Per Track [4 bytes]: 63
  * Sector Size [4 bytes]: 512B
# Partition Layout Sector Size [4 bytes]: 512B
+ Device Identification [8 bytes]:
  * Vendor [32 bytes]: KINGSTON
  * Product [64 bytes]: SA400S37120G
  * Firmware [16 bytes]: 03090005
  * Serial Number [32 bytes]: 50026B77843A5618
+ IDE Properties [8 bytes]:
  * Size [48 bytes]: 111.7GB (234441648 LBA)
  * Sector Size [8 bytes]: 512
  * Device Type [8 bytes]: SSD
  * Interface [38 bytes]: SATA 3.2, 6.0 Gb/s
  * Interface Speed [18 bytes]: 6.0 Gb/s
  * Standard [12 bytes]: ACS-3
  * Features [70 bytes]: S.M.A.R.T., APM-, LBA48, NCQ, TRIM
+ SCSI Address [8 bytes]:
  * Port Number [1 bytes]: 2
  * Path Id [1 bytes]: 0
  * Target Id [1 bytes]: 0
  * Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA-II

- Drive Number 5 -----
* Drive Type [256 bytes]: Physical Drive,Disk
* Name [56 bytes]: TOSHIBA DT01ACA100 MS20A750
* OS Object [38 bytes]: \\.\PhysicalDrive1
* R-Studio Driver [44 bytes]: WinNT\Handle\Physical
* Size [8 bytes]: 931.5GB (1953525168 sec)
* Sector Size [4 bytes]: 512B
* Partition Size [8 bytes]: 931.5GB (1953525168 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 4096
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 121601
```

```

* Tracks Per Cylinder [4 bytes]: 255
* Sectors Per Track [4 bytes]: 63
* Sector Size [4 bytes]: 512B
# Partition Layout Sector Size [4 bytes]: 512B
+ Device Identification [8 bytes]:
* Vendor [32 bytes]: TOSHIBA
* Product [64 bytes]: DT01ACA100
* Firmware [16 bytes]: MS20A750
* Serial Number [32 bytes]: 44H5ATLKS
+ IDE Properties [8 bytes]:
* Size [50 bytes]: 931.5GB (1953525168 LBA)
* Logical Sector Size [8 bytes]: 512
* Physical Sector Size [10 bytes]: 4096
* Device Type [36 bytes]: HDD 3.5" 7200 RPM
* Interface [38 bytes]: SATA 3.0, 6.0 Gb/s
* Interface Speed [18 bytes]: 6.0 Gb/s
* Standard [18 bytes]: ATA8-ACS
* Features [58 bytes]: S.M.A.R.T., APM-, LBA48, NCQ
+ SCSI Address [8 bytes]:
* Port Number [1 bytes]: 2
* Path Id [1 bytes]: 1
* Target Id [1 bytes]: 0
* Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA-II

- Drive Number 6 -----
* Drive Type [256 bytes]: Physical Drive,Disk
* Name [62 bytes]: WDC WD1200BEVT-22ZCT0 11.01A11
* OS Object [38 bytes]: \\.\PhysicalDrive2
* R-Studio Driver [44 bytes]: WinNT\Handle\Physical
* Size [8 bytes]: 111.7GB (234441648 sec)
* Sector Size [4 bytes]: 512B
* Partition Size [8 bytes]: 111.7GB (234441648 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
# Maximum Transfer [4 bytes]: 131072
# I/O Block Size [4 bytes]: 512
# Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
* Cylinders [8 bytes]: 14593
* Tracks Per Cylinder [4 bytes]: 255
* Sectors Per Track [4 bytes]: 63
* Sector Size [4 bytes]: 512B
# Partition Layout Sector Size [4 bytes]: 512B
+ Device Identification [8 bytes]:
* Vendor [32 bytes]: WDC
* Product [64 bytes]: WD1200BEVT-22ZCT0
* Firmware [16 bytes]: 11.01A11
* Serial Number [32 bytes]: WD-WXE808HN3826
+ IDE Properties [8 bytes]:
* Size [48 bytes]: 111.7GB (234441648 LBA)
* Sector Size [8 bytes]: 512
* Interface [38 bytes]: SATA 2.5, 3.0 Gb/s

```

```
* Standard [18 bytes]: ATA8-ACS
* Features [66 bytes]: S.M.A.R.T., APM, AAM, LBA48, NCQ
+ SCSI Address [8 bytes]:
* Port Number [1 bytes]: 2
* Path Id [1 bytes]: 4
* Target Id [1 bytes]: 0
* Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA-II

- Drive Number 7 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [6 bytes]: C:
* Mount Points [8 bytes]: C:\
* OS Object [98 bytes]: \\?\Volume{daf04b8f-aece-4176-9e12-25271c9682d5}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 111.1GB (233156718 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 117MB (239616 sec)
* Partition Size [8 bytes]: 111.1GB (233156718 sec)
* Partition Number [4 bytes]: 3
* GPT Partition GUID [74 bytes]: daf04b8f-aece-4176-9e12-25271c9682d5
* GPT Type GUID [256 bytes]: Data Partition, ebd0a0a2-b9e5-4433-87c0-68b6b72699c7
+ NTFS Information [8 bytes]:
* Cluster Size [4 bytes]: 4KB (8 sec)
* MFT Record Size [4 bytes]: 1KB
* MFT Position [8 bytes]: 3GB (6291456 sec)
* MFT Mirror Position [8 bytes]: 8KB (16 sec)
* Index Block Size [4 bytes]: 4KB
* Sector Size [4 bytes]: 512B
* Volume Size [8 bytes]: 111.1GB (233156717 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
# Maximum Transfer [4 bytes]: 131072
# I/O Block Size [4 bytes]: 512
# Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
* Cylinders [8 bytes]: 14593
* Tracks Per Cylinder [4 bytes]: 255
* Sectors Per Track [4 bytes]: 63
* Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
* Port Number [1 bytes]: 2
* Path Id [1 bytes]: 0
* Target Id [1 bytes]: 0
* Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 8 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [90 bytes]: Volume{06a81b86-6c2b-4a3c-9170-fff1161fb034}
* OS Object [98 bytes]: \\?\Volume{06a81b86-6c2b-4a3c-9170-fff1161fb034}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 508MB (1040384 sec)
```

```

* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 111.2GB (233398272 sec)
* Partition Size [8 bytes]: 508MB (1040384 sec)
* Partition Number [4 bytes]: 4
* GPT Partition GUID [74 bytes]: 06a81b86-6c2b-4a3c-9170-fff1161fb034
* GPT Type GUID [256 bytes]: Windows Recovery Partition, de94bba4-06d1-4d40-a16a-
bfd50179d6ac
* GPT Partition Attributes [256 bytes]: System, No automount (0x8000000000000001)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 169.3MB (346792 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 507.9MB (1040383 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 512
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 14593
  * Tracks Per Cylinder [4 bytes]: 255
  * Sectors Per Track [4 bytes]: 63
  * Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
  * Port Number [1 bytes]: 2
  * Path Id [1 bytes]: 0
  * Target Id [1 bytes]: 0
  * Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 9 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [6 bytes]: D:
* Mount Points [8 bytes]: D:\
* OS Object [98 bytes]: \\?\Volume{78addf5b-0000-0000-0000-100000000000}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 931.5GB (1953519616 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 1MB (2048 sec)
* Partition Size [8 bytes]: 931.5GB (1953519616 sec)
* Partition Number [4 bytes]: 1
* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 3GB (6291456 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 931.5GB (1953519615 sec)

```

```

# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 512
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 121601
  * Tracks Per Cylinder [4 bytes]: 255
  * Sectors Per Track [4 bytes]: 63
  * Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
  * Port Number [1 bytes]: 2
  * Path Id [1 bytes]: 1
  * Target Id [1 bytes]: 0
  * Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 10 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [90 bytes]: Volume{f6b7cc94-0000-0000-0000-100000000000}
* OS Object [98 bytes]: \\?\Volume{f6b7cc94-0000-0000-0000-100000000000}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 39GB (81972923 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 1MB (2048 sec)
* Partition Size [8 bytes]: 39GB (81972923 sec)
* Partition Number [4 bytes]: 1
* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 3GB (6291456 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 39GB (81972920 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 512
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 14593
  * Tracks Per Cylinder [4 bytes]: 255
  * Sectors Per Track [4 bytes]: 63
  * Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
  * Port Number [1 bytes]: 2
  * Path Id [1 bytes]: 4
  * Target Id [1 bytes]: 0
  * Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

```

```
- Drive Number 11 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [90 bytes]: Volume{f6b7cc94-0000-0000-0000-b0c509000000}
* OS Object [98 bytes]: \\?\Volume{f6b7cc94-0000-0000-0000-b0c509000000}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 72.6GB (152461312 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 39GB (81975296 sec)
* Partition Size [8 bytes]: 72.6GB (152461312 sec)
* Partition Number [4 bytes]: 2
* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 3GB (6291456 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 72.6GB (152461311 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
  # Maximum Transfer [4 bytes]: 131072
  # I/O Block Size [4 bytes]: 512
  # Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
  * Cylinders [8 bytes]: 14593
  * Tracks Per Cylinder [4 bytes]: 255
  * Sectors Per Track [4 bytes]: 63
  * Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
  * Port Number [1 bytes]: 2
  * Path Id [1 bytes]: 4
  * Target Id [1 bytes]: 0
  * Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 12 -----
* Drive Type [256 bytes]: Volume,Disk
* Name [90 bytes]: Volume{e7571fdc-fb5d-42cf-86fe-03807522d76d}
* OS Object [98 bytes]: \\?\Volume{e7571fdc-fb5d-42cf-86fe-03807522d76d}
* R-Studio Driver [42 bytes]: WinNT\Handle\Logical
* Size [8 bytes]: 100MB (204800 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 1MB (2048 sec)
* Partition Size [8 bytes]: 100MB (204800 sec)
* Partition Number [4 bytes]: 1
* GPT Partition GUID [74 bytes]: e7571fdc-fb5d-42cf-86fe-03807522d76d
* GPT Type GUID [256 bytes]: UEFI System Partition, c12a7328-f81f-11d2-ba4b-00a0c93ec93b
* GPT Partition Attributes [256 bytes]: No automount (0x8000000000000000)
+ FAT Information [8 bytes]:
  * FAT Bits (12,16,32) [4 bytes]: 32
  * Cluster Size [4 bytes]: 1KB (2 sec)
```

```

* First Cluster Offset [8 bytes]: 3.99MB (8188 sec)
* Root Directory Cluster [4 bytes]: 2
* First FAT Offset [8 bytes]: 3.24MB (6654 sec)
* Size of One FAT Table [8 bytes]: 384.5KB (769 sec)
* Number of FAT Copies [4 bytes]: 2
# Active FAT copy [4 bytes]: Auto
* Sector Size [4 bytes]: 512B
* Major Version [1 bytes]: 0
* Minor Version [1 bytes]: 0
* Volume Size [8 bytes]: 100MB (204800 sec)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
# Maximum Transfer [4 bytes]: 131072
# I/O Block Size [4 bytes]: 512
# Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
* Cylinders [8 bytes]: 14593
* Tracks Per Cylinder [4 bytes]: 255
* Sectors Per Track [4 bytes]: 63
* Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
* Port Number [1 bytes]: 2
* Path Id [1 bytes]: 0
* Target Id [1 bytes]: 0
* Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 13 -----
* Drive Type [256 bytes]: Volume
* Name [58 bytes]: Microsoft reserved partition
* OS Object [48 bytes]: \Device\HarddiskVolume2
* R-Studio Driver [42 bytes]: WinNT\Native\Logical
* Size [8 bytes]: 16MB (32768 sec)
* Sector Size [4 bytes]: 512B
* Partition Offset [8 bytes]: 101MB (206848 sec)
* Partition Size [8 bytes]: 16MB (32768 sec)
* Partition Number [4 bytes]: 2
* GPT Partition GUID [74 bytes]: ad153538-3269-4fe5-a229-0aa8afc25a2d
* GPT Type GUID [256 bytes]: System Reserved Partition, e3c9e316-0b5c-4db8-817d-f92df00215ae
* GPT Partition Attributes [256 bytes]: No automount (0x8000000000000000)
# I/O Retries [4 bytes]: Default
+ Drive Control [8 bytes]:
# Maximum Transfer [4 bytes]: 131072
# I/O Block Size [4 bytes]: 512
# Buffer Alignment [4 bytes]: 4
+ Physical Drive Geometry [8 bytes]:
* Cylinders [8 bytes]: 14593
* Tracks Per Cylinder [4 bytes]: 255
* Sectors Per Track [4 bytes]: 63
* Sector Size [4 bytes]: 512B
+ SCSI Address [8 bytes]:
* Port Number [1 bytes]: 2

```



```
* Path Id [1 bytes]: 0
* Target Id [1 bytes]: 0
* Lun [1 bytes]: 0
* Bus Type [4 bytes]: SerialATA

- Drive Number 14 -----
* Drive Type [256 bytes]: Partition
* Name [42 bytes]: EFI system partition
* Size [8 bytes]: 100MB (204800 sec)
* Partition Offset [8 bytes]: 1MB (2048 sec)
* Partition Size [8 bytes]: 100MB (204800 sec)
* Partition Number [4 bytes]: 1
* GPT Partition GUID [74 bytes]: e7571fdc-fbbd-42cf-86fe-03807522d76d
* GPT Type GUID [256 bytes]: UEFI System Partition, c12a7328-f81f-11d2-ba4b-00a0c93ec93b
* GPT Partition Attributes [256 bytes]: No automount (0x8000000000000000)
* GPT Partition Name [42 bytes]: EFI system partition
+ FAT Information [8 bytes]:
  * FAT Bits (12,16,32) [4 bytes]: 32
  * Cluster Size [4 bytes]: 1KB (2 sec)
  * First Cluster Offset [8 bytes]: 3.99MB (8188 sec)
  * Root Directory Cluster [4 bytes]: 2
  * First FAT Offset [8 bytes]: 3.24MB (6654 sec)
  * Size of One FAT Table [8 bytes]: 384.5KB (769 sec)
  * Number of FAT Copies [4 bytes]: 2
# Active FAT copy [4 bytes]: Auto
* Sector Size [4 bytes]: 512B
* Major Version [1 bytes]: 0
* Minor Version [1 bytes]: 0
* Volume Size [8 bytes]: 100MB (204800 sec)

- Drive Number 15 -----
* Drive Type [256 bytes]: Partition
* Name [58 bytes]: Microsoft reserved partition
* Size [8 bytes]: 16MB (32768 sec)
* Partition Offset [8 bytes]: 101MB (206848 sec)
* Partition Size [8 bytes]: 16MB (32768 sec)
* Partition Number [4 bytes]: 2
* GPT Partition GUID [74 bytes]: ad153538-3269-4fe5-a229-0aa8afc25a2d
* GPT Type GUID [256 bytes]: System Reserved Partition, e3c9e316-0b5c-4db8-817d-f92df00215ae
* GPT Partition Attributes [256 bytes]: No automount (0x8000000000000000)
* GPT Partition Name [58 bytes]: Microsoft reserved partition

- Drive Number 16 -----
* Drive Type [256 bytes]: Partition
* Name [42 bytes]: Basic data partition
* Mount Points [8 bytes]: C:\
* Size [8 bytes]: 111.1GB (233156718 sec)
* Partition Offset [8 bytes]: 117MB (239616 sec)
* Partition Size [8 bytes]: 111.1GB (233156718 sec)
* Partition Number [4 bytes]: 3
* GPT Partition GUID [74 bytes]: daf04b8f-aece-4176-9e12-25271c9682d5
```

```
* GPT Type GUID [256 bytes]: Data Partition, ebd0a0a2-b9e5-4433-87c0-68b6b72699c7
* GPT Partition Name [42 bytes]: Basic data partition
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 3GB (6291456 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 111.1GB (233156717 sec)

- Drive Number 17 -----
* Drive Type [256 bytes]: Partition
* Name [54 bytes]: Windows Recovery Partition
* Size [8 bytes]: 508MB (1040384 sec)
* Partition Offset [8 bytes]: 111.2GB (233398272 sec)
* Partition Size [8 bytes]: 508MB (1040384 sec)
* Partition Number [4 bytes]: 4
* GPT Partition GUID [74 bytes]: 06a81b86-6c2b-4a3c-9170-fff1161fb034
* GPT Type GUID [256 bytes]: Windows Recovery Partition, de94bba4-06d1-4d40-a16a-
bfd50179d6ac
* GPT Partition Attributes [256 bytes]: System, No automount (0x8000000000000001)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 169.3MB (346792 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
  * Sector Size [4 bytes]: 512B
  * Volume Size [8 bytes]: 507.9MB (1040383 sec)

- Drive Number 18 -----
* Drive Type [256 bytes]: Empty Space
* Name [28 bytes]: Empty Space18
* Size [8 bytes]: 1.44MB (2959 sec)
* Partition Offset [8 bytes]: 111.7GB (234438656 sec)
* Partition Size [8 bytes]: 1.44MB (2959 sec)

- Drive Number 19 -----
* Drive Type [256 bytes]: Partition,Primary
* Name [22 bytes]: Partition1
* Mount Points [8 bytes]: D:\
* Size [8 bytes]: 931.5GB (1953519616 sec)
* Partition Offset [8 bytes]: 1MB (2048 sec)
* Partition Size [8 bytes]: 931.5GB (1953519616 sec)
* Partition Number [4 bytes]: 1
* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)
+ NTFS Information [8 bytes]:
  * Cluster Size [4 bytes]: 4KB (8 sec)
  * MFT Record Size [4 bytes]: 1KB
  * MFT Position [8 bytes]: 3GB (6291456 sec)
  * MFT Mirror Position [8 bytes]: 8KB (16 sec)
  * Index Block Size [4 bytes]: 4KB
```

\* Sector Size [4 bytes]: 512B  
 \* Volume Size [8 bytes]: 931.5GB (1953519615 sec)

- Drive Number 20 -----  
 \* Drive Type [256 bytes]: Partition,Primary  
 \* Name [22 bytes]: Partition1  
 \* Size [8 bytes]: 39GB (81972923 sec)  
 \* Partition Offset [8 bytes]: 1MB (2048 sec)  
 \* Partition Size [8 bytes]: 39GB (81972923 sec)  
 \* Partition Number [4 bytes]: 1  
 \* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)  
 + NTFS Information [8 bytes]:  
 \* Cluster Size [4 bytes]: 4KB (8 sec)  
 \* MFT Record Size [4 bytes]: 1KB  
 \* MFT Position [8 bytes]: 3GB (6291456 sec)  
 \* MFT Mirror Position [8 bytes]: 8KB (16 sec)  
 \* Index Block Size [4 bytes]: 4KB  
 \* Sector Size [4 bytes]: 512B  
 \* Volume Size [8 bytes]: 39GB (81972920 sec)

- Drive Number 21 -----  
 \* Drive Type [256 bytes]: Partition,Primary  
 \* Name [22 bytes]: Partition2  
 \* Size [8 bytes]: 72.6GB (152461312 sec)  
 \* Partition Offset [8 bytes]: 39GB (81975296 sec)  
 \* Partition Size [8 bytes]: 72.6GB (152461312 sec)  
 \* Partition Number [4 bytes]: 2  
 \* Partition Type [256 bytes]: NTFS/HPFS/exFAT (0x7)  
 + NTFS Information [8 bytes]:  
 \* Cluster Size [4 bytes]: 4KB (8 sec)  
 \* MFT Record Size [4 bytes]: 1KB  
 \* MFT Position [8 bytes]: 3GB (6291456 sec)  
 \* MFT Mirror Position [8 bytes]: 8KB (16 sec)  
 \* Index Block Size [4 bytes]: 4KB  
 \* Sector Size [4 bytes]: 512B  
 \* Volume Size [8 bytes]: 72.6GB (152461311 sec)

\*\*\*\*\*  
 \*\*\*\*\*

----- Session 1  
 -----

START Date / Time of Collection: 2022-07-05 03:56:48

Case Name: Stiven v. Christofer  
 Case Number: 28-S-0205-CR85763  
 Operator / Investigator Name: J.F. Lewson

Source drive:Sector	Modification Date	MD5
SHA-1		SHA-256
	File Name	
20	2021-11-15 11:18:41	Partition1/Root
\$I30: INDEX_ALLOC (Non-Resident)		

```

288-295
20          2022-04-14 10:07:42      Partition1/Root/$RECYCLE.BIN
20          2022-04-14 10:07:42      Partition1/Root/$RECYCLE.BIN/S-1-5-
21-1491398347-2858144638-2526585153-1002
20          2022-04-14 10:07:42      a526b9e7c716b3489d8cc062fbce4005
      2df502a944ff721241be20a9e449d2acd07e0312
elb9ce9b57957b1a0607a72a057d6b7a9b34ea60f3f8aa8f38a3af979bd23066
Partition1/Root/$RECYCLE.BIN/S-1-5-21-1491398347-2858144638-2526585153-
1002/desktop.ini
20          2021-11-15 11:18:41      Partition1/Root/$RECYCLE.BIN/S-1-5-
21-3229151806-1869599629-3662833694-1001
20          2021-11-15 11:18:41      a526b9e7c716b3489d8cc062fbce4005
      2df502a944ff721241be20a9e449d2acd07e0312
elb9ce9b57957b1a0607a72a057d6b7a9b34ea60f3f8aa8f38a3af979bd23066
Partition1/Root/$RECYCLE.BIN/S-1-5-21-3229151806-1869599629-3662833694-
1001/desktop.ini
20          2021-11-15 10:47:20      Partition1/Root/Documents
      $I30: INDEX_ALLOC (Non-Resident)
      99920-99927
20          2021-11-15 10:47:19
Partition1/Root/Documents/OpenOffice-files
20          2021-11-15 10:47:18
Partition1/Root/Documents/OpenOffice-files/Calc-files
20          2021-11-15 10:47:18
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-files
20          2020-04-06 16:21:52      b1eb4cc9101bcb86c0042231f898f0ae
      8e5da7978ebe26604b5f556ec2d20a4cell176ff1
4d226d7f3c0e1c874f0aaf772f9a5cf9bed2c7d982906a4a0314c206cbc4bb35
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-files/.DS_Store
      DATA: DATA (Non-Resident)
      99960-99975
20          2020-04-06 16:18:30      eab006354c7cf4e1fd3772afd0643672
      bfc7b3368a46a640c3145646b0dfad10bb89f096
4709af13b6dbaf11feab0750bc2a3734eab9a94e184bd7f736805adcb02ac368
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-
files/file_example_ods_10.ods
      DATA: DATA (Non-Resident)
      99976-100007
20          2020-04-06 16:20:50      94790aeb545e806ea9cf161f6ae2697f
      152a13f940c2dfa4530b1b022897cb3dbd0cb45b
edb79e7965f6b61722f1c6427200e4ba44692e573b2f2f8cd210f356aed7f3c9
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-
files/file_example_ods_1000.ods
      DATA: DATA (Non-Resident)
      100008-100111
20          2020-04-06 16:19:47      000389561d71032e79411613d73f01f5
      3e9fdd1b26eed17f40e98a0f8d13af11decdf951
b668e04c130d51d023531482c8067b5232284decdf54760c6ae431e3718388c3
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-
files/file_example_ods_50.ods
      DATA: DATA (Non-Resident)
      100112-100143

```

20 2020-04-06 16:21:44 28aa35b07f4a28f4f001e28f277dd1be  
f9dfcaf3e9b6c1c15a949ab9150b8e7d599f1d6  
069ad480df6dba6de101188dc126f688127206932d98f02149eb390b6e8f2928  
Partition1/Root/Documents/OpenOffice-files/Calc-files/ods-  
files/file\_example\_ods\_5000.ods  
DATA: DATA (Non-Resident)  
100144-100519

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-files

20 2020-04-06 16:31:06 c763a032a1999d42934abebc25fc6a83  
07c1d02aa03ae7768dfb88445bff68e9c32c2264  
208fef9240237b668cbb927255a8f204e6ab808a68701ffe72bf3ca85e4d13e1  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-files/.DS\_Store  
DATA: DATA (Non-Resident)  
100520-100535

20 2020-04-06 16:25:50 f893b7290b96905f0776e0e1cb4b91c4  
d80a4175a6a2767b61fe8e2b33774bd211b6a934  
ab82e943104f1edfa17b58595b4221c02ddf93aa4056fa630473de192f85d1fe  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-  
files/file\_example\_OXLSX\_10.xlsx  
DATA: DATA (Non-Resident)  
100536-100551

20 2020-04-06 16:30:27 be99eeaa2e2aa77ecb4d7b9eef44cb4  
1aad45945f99a02383e168e339a20d38999491b6  
cd6583c0aa16dde7342c4dc5483987edf173d7378ce946ded7383bbf4b5990ba  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-  
files/file\_example\_OXLSX\_100.xlsx  
DATA: DATA (Non-Resident)  
100552-100575

20 2020-04-06 16:30:10 2280cba8bea0ded6bf9c428939f9cb32  
4aee4fe0add47392f508fef28af3f5c02a9eb4a2  
59da4d0e97a54c462fcf34268b14a4214ef324da368712a0a32678c976e89484  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-  
files/file\_example\_OXLSX\_50.xlsx  
DATA: DATA (Non-Resident)  
100576-100591

20 2020-04-06 16:30:42 980e7a175ea67333379753a788d331e5  
c90c1841006b8da26e69636596c7a8e5fcc26ec6  
0d66f10f1b76f620d69e4054eeab6669f2e64b0b2fa5e3365101027aa5b657e7  
Partition1/Root/Documents/OpenOffice-files/Calc-files/oxlsx-  
files/file\_example\_OXLSX\_5000.xlsx  
DATA: DATA (Non-Resident)  
54912-55287

20 2020-04-06 16:23:13 db42bc048678d194bda93124fcc1e359  
9f7137c6703b51cd78a797b56b5f2a2e7c8b83ea  
433476459c23ba979ab467ce4c310e29a40e3b9a8d68dd63467b503ddc4cdf23  
Partition1/Root/Documents/OpenOffice-files/Calc-files/.DS\_Store  
DATA: DATA (Non-Resident)  
99944-99959

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files

```
20                2021-11-15 10:47:19
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-files
  $I30: INDEX_ALLOC (Non-Resident)
    101296-101303

20                2020-04-06 16:13:48      7901a6038143aa293bff65c1dcc564a9
    13c30d142999708f8b0f3b71bce35c1c91304032
ad75eff3191cbb4e3215b25ce1733f062f474ff6aa242db82de391eada0f114e
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-files/
.DS_Store
  DATA: DATA (Non-Resident)
    101008-101023

20                2018-10-19 11:12:18      01a42d82b4e2e143876cc0afea4883ed
    3cc9264c3a5569c08abfb9ee343dbalbfb96f1b3d
be198ae04df0476e6a8153e4b396da05c9badef729f87f1abbb626f8bfae8491
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-
files/file_example_XLS_10.xls
  DATA: DATA (Non-Resident)
    100928-100967

20                2018-10-19 11:14:00      efc6e746de385a6ba15f9e697503f4c
    96451e09d24aacaab7c00292316020ecd8090dbf
8562df19f14cb945b769a0812fblafd5acd9e349f0cdd71150282202d71319ee
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-
files/file_example_XLS_100.xls
  DATA: DATA (Non-Resident)
    6944-7015

20                2018-10-19 11:14:56      f9773bf0bd611c8a9107140956b3881f
    7a538e2ca18bb7cb0c2fb0130767012f7acd9019
d3107cae4af0231540887be840135ec03763d83926c2900fb76aead0226787ca
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-
files/file_example_XLS_1000.xls
  DATA: DATA (Non-Resident)
    4992-5295

20                2018-10-19 11:13:23      b3df6dd6764416491f51415c4ccflaaf
    eealbebb11f6beab8f38bc2b1705dbf598bcbfaf6
a7beba6217ffa60c9e79f0310d024a74cbaf363d7b884d214178e413e758b68e
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-
files/file_example_XLS_50.xls
  DATA: DATA (Non-Resident)
    100872-100927

20                2018-10-19 11:15:24      ecb548b885ec5cf6f6e38ece80fa5f2e
    5ddffe520563c9b9c26a7c297c99b2e896e891d0
bc8d33d7033eb858dd63ae4882d4381fb9fe85c0740fd41efb9a309fca9e366f
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xls-
files/file_example_XLS_5000.xls
  DATA: DATA (Non-Resident)
    101496-102863

20                2021-11-15 10:47:19
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-files
  $I30: INDEX_ALLOC (Non-Resident)
    55288-55295
```

20 2020-04-06 16:16:33 8f9765363a3610383bbafb7ed7e8928c  
075e8f3a721f3d733c20e897c3e9db0c907322b7  
9320252c62acfa865ebd315c1597d767f9ebc16ea410bff7e3d2e479bdcde088  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-files/  
.DS\_Store  
DATA: DATA (Non-Resident)  
101280-101295

20 2018-10-19 11:16:15 bd5ec17de931c601b3231fdb4eac6db6  
2a647da6430913fa47cfd7874721f0832bb91f52  
584bd2879378c518796f4422f8ed41c971798e76c5ee58c307fc3d40adb03eaa  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-  
files/file\_example\_XLSX\_10.xlsx  
DATA: DATA (Non-Resident)  
101112-101135

20 2018-10-19 11:17:58 43cb8b1c3ede97eae779d0bc7d03710  
41360a2a5d2f8a2aaacd2ae503ea754fc33d93f4  
97e004974d26f04bf7bf960d5b4e33f2f59a81d79e95526804f5b570f819eacb  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-  
files/file\_example\_XLSX\_100.xlsx  
DATA: DATA (Non-Resident)  
100840-100871

20 2018-10-19 11:18:45 513e4fac7ff88720001864d1a350ed1c  
87e9c39ea24c1949cca6f68ff42cdb8208c32a13  
14fed5fcf63206d7f5bd275058b7d79184ce187b062fcdab5d9ff77b4ea19502  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-  
files/file\_example\_XLSX\_1000.xlsx  
DATA: DATA (Non-Resident)  
9720-9831

20 2018-10-19 11:16:44 775654d96ef34c95cela60e9606977e9  
1954ba25e67edc407955203d21aeb8c3a99d272f  
e40aeadfebe57e3be87ac46260ad09e1c4c030b95eef2af767382d0fe79198a  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-  
files/file\_example\_XLSX\_50.xlsx  
DATA: DATA (Non-Resident)  
101088-101111

20 2018-10-19 11:19:09 ea38c0c454aa508b5909161bd8260918  
e566e8c34a723ad44431cc3f0fdbf3bcel8410e5  
acbd5c728f2738a70f59c245c961eb8122d59aa07b7debd7d348efe472b650b  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/xlsx-  
files/file\_example\_XLSX\_5000.xlsx  
DATA: DATA (Non-Resident)  
103080-103551

20 2020-04-06 16:31:14 52d71be9d0971685678823c546b72eff  
1930f5ed939a35965802a508afb3865810e7e0af  
8ffc5293b616b558264fdb2277fb6a8d032ebecaf6b678b491ddcfdef1a3f9f2  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Excel-files/.DS\_Store  
DATA: DATA (Non-Resident)  
100984-101007

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-files

```
20          2020-04-06 16:12:41      34b20ad44b5d33cc3401b0calc9c55ad
    236a6271d535ea5149eca9fe73e939900968c019
9cc166b17367418d3af128bd74ae79c7b0a20c0a1fd19c4d458c1834897905db
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-files/
.DS_Store
    DATA: DATA (Non-Resident)
    101056-101071
20          2018-10-19 11:10:23      759cbcd3d7c574ec4de97222bc407665
    1308c158c06c9050ffa3f0f5898a5ccf4a94c8c7
3fbfda0b36c4edc4b4d48ec5c0425ced04ed15c6e3891495201a7289533a2ce2
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-
files/DOCFile_500kb.doc
    DATA: DATA (Non-Resident)
    103592-104599
20          2018-10-19 11:20:26      35176f9b7f521954445100e5df74dee9
    5aee31c3f490b421e75548ea713a6755818980db
f907aad6b6b9b38c8e19eaf44aa11796051eeac35d0d2115246449da98f1137f7
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-
files/file-sample-doc_100kB.doc
    DATA: DATA (Non-Resident)
    102864-103071
20          2018-10-19 11:19:59      bb8c0ad499fc64837a45154a27e07734
    1e09acf84e23e9eddb152f812354785e2f7cd159
2bcd9c011678a8aa7045a6485bef7872c4295fbb6c2467cc29135ffcc769457b
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-
files/file-sample-doc_1MB.doc
    DATA: DATA (Non-Resident)
    104808-106823
20          2018-10-19 11:21:18      e16fb51cef336edf2c19d065ef49a662
    15bfff84aea3602cd0ec81bd7ac9789a969c3528
41f65cf10d9b0b42d12307a46b66ae632e6d883e067db5959969822780823d7a
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Doc-
files/file-sample-doc_500kB.doc
    DATA: DATA (Non-Resident)
    106824-107807
20          2021-11-15 10:47:19
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-files
20          2020-04-06 16:12:41      0717f9af8c983c9af7d5fb9d311ab163
    0celf83b661658d58caee54b75ede278a30e0927
359246310af6c9ff8c7192b637ae949a8c388f1c9b684d46clea013d4fcafffb
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-files/
.DS_Store
    DATA: DATA (Non-Resident)
    101040-101055
20          2018-10-19 11:11:20      96d043aabc6bdad1046db4c47aa7a3a8
    7705c94a188ecebd1be2f68f70687b1ef7360d21
9383ce8098236174683cefab77cbddfe8cc17d8656b4e87281e783ce55b76d52
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-
files/DOCXFile_500kb.docx
    DATA: DATA (Non-Resident)
    107824-108511
```



20 2018-10-19 11:22:33 0815c2eb26ab3ad59fab1ccba9d18fd0  
20898f28011ae05f5062e09690b292ed13fbbf20  
acd7fe4a7ee20c77b48489be5b9dbad8a850a2b29af721c912f6993e238b5471  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-  
files/file-sample-docx\_100kB.docx  
DATA: DATA (Non-Resident)  
108512-108759

20 2018-10-19 11:21:55 9a1485d3bca8dd88cb67f248c0144d0b  
0dcff5af4a39b3d57e964ead8a004636c3a276f4  
98983b17e3562d015aclc1a6f9d9971090303c04d0d70d6729416d376385eb2b  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-  
files/file-sample-docx\_1MB.docx  
DATA: DATA (Non-Resident)  
108760-110847

20 2018-10-19 11:23:09 183a5dc1a099e3c8c0b54c6aa52d64b7  
1266501c54bdea72f239925138a61a62a9f8b2ba  
ff010e8d024e80c14901ea9ac618f253862667e7a69f69b070002cbc74df9f58  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/Docx-  
files/file-sample-docx\_500kB.docx  
DATA: DATA (Non-Resident)  
110848-111983

20 2020-04-06 16:44:01 8b1836fc208a9ab78cb95bc0d00b6256  
c6f205d3920442756681d4bc1c3091dae0b69466  
5dba5fad9c2bf25ea40190fb34594641a66e44d4fd40a7cabf9ea11862e6246a  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/Word-files/.DS\_Store  
DATA: DATA (Non-Resident)  
101072-101087

20 2020-04-06 16:44:31 b6e071bf10615607b95d544a2022d187  
199662a8e3916924b81b13ac8ae705f3c581cec9  
c988d303b52f36214ce9464a07df2dbf114b6820971eddd987668e89bb0167a6  
Partition1/Root/Documents/OpenOffice-files/Microsoft-files/.DS\_Store  
DATA: DATA (Non-Resident)  
100968-100983

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Writer-files

20 2021-11-15 10:47:19  
Partition1/Root/Documents/OpenOffice-files/Writer-files/odocx-files

20 2020-04-06 16:33:22 70b4b7f69342042902032114b234fa03  
79bfe4ccde5838e150a0f236b9c7478104b9cd09  
2dd6ea9aef467ef368f7024e22ae3ea03d3e4f73949c0elee7cb055779c596a7  
Partition1/Root/Documents/OpenOffice-files/Writer-files/odocx-files/file-sample-  
odocx\_100kB.docx  
DATA: DATA (Non-Resident)  
101136-101279

20 2020-04-06 16:36:02 e579cd58blac23749e4251835bc0f610  
e8d59c3b4ea9f4c08c4e59031736a578d728dff6  
1c0f9edf45a390e0d279ald10da038e374b515cef3e5c077c8bae99e3dd4a5cc  
Partition1/Root/Documents/OpenOffice-files/Writer-files/odocx-files/file-sample-  
odocx\_1MB.docx  
DATA: DATA (Non-Resident)  
112144-114047

```
20          2020-04-06 16:36:58      0a64c077c83153e159aa45906220ff3e
    ca27738f86b01900b3b94e19bd99003fb47a5c80
05100d4633bff3a8809b8b075ecbb7e9dd22f94148307faabad972ee8c8307d7
Partition1/Root/Documents/OpenOffice-files/Writer-files/odocx-files/file-sample-
odocx_500kB.docx
    DATA: DATA (Non-Resident)
    114048-114951
20          2020-04-06 16:34:45      fldbf4f7ad95d39ccc0f877d9b887afa
    c6b1149ecbd1303d75868e19643e61c60a822808
fb723512f7f3f166cb0013f3160d98b648719f08bc6dcde7db5043277cb1ca85
Partition1/Root/Documents/OpenOffice-files/Writer-files/odocx-
files/ODOCXFile_500kb.docx
    DATA: DATA (Non-Resident)
    114952-115823
20          2021-11-15 10:47:19
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files
20          2020-04-06 16:43:34      d4c494a030d81983196866482a5597fe
    46aa85342a8d01ae27ea91965ce088813a4410ed
8fcb878c093e2f4652b632bb347b3f69db28ece431801b9651b3809b47ff16e4
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files/.DS_Store
    DATA: DATA (Non-Resident)
    9832-9847
20          2020-04-06 16:40:21      c3e2b9d976977ec25d6347ed02673120
    c913470ca428305f83c37c34a17cdf79903a3248
455b56ea7a3bd759f917b8e3a3d16b567f10ada93c8202ddee8945db150bf810
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files/file-sample-
odt_100kB.odt
    DATA: DATA (Non-Resident)
    100592-100839
20          2020-04-06 16:42:33      5f1e8dfdac3fc3133511a75f26001854
    7a26c32e318fa96d08c4515122c197e7bf7397ba
23a5d871d288d0b5bd3a65747e2dc6bba4689a9c67ccf8e609e8d8ce9af74336
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files/file-sample-
odt_1MB.odt
    DATA: DATA (Non-Resident)
    116088-118183
20          2020-04-06 16:41:23      324dd4fe1e621090a5dfe7e0c7680050
    c070a68cce81d1058838a5438a91c3a6bff11fa5
de09f89e254cc5ecc388ba278cf2f224067e9fbc9c64ae3009adf565fcc798c6
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files/file-sample-
odt_500kB.odt
    DATA: DATA (Non-Resident)
    118184-119319
20          2020-04-06 16:43:29      b45be240cb18dda2cd78caee72891837
    06bb21bd6fffd5eae59034e4cf9533076ccb68bb5
ed39112cdf37ddc805e39b9edb033fd97dcel179831c1392a2a59e46f85a0796
Partition1/Root/Documents/OpenOffice-files/Writer-files/odt-files/ODTFile_500kb.odt
    DATA: DATA (Non-Resident)
    54392-54911
20          2020-04-06 16:37:14      14a0ca21163393f57c739e278f95dfde
    cc80e712df7b497601fb5ab86c23f4d6ebd8db0c
b4c09d792b41a04e369df0ccdd202eba89a11c9f1530a62be60183379cd85335
Partition1/Root/Documents/OpenOffice-files/Writer-files/.DS_Store
```

DATA: DATA (Non-Resident)  
101024-101039

20 2020-04-06 16:34:59 229601a0b29ad34773e4891161a14e2b  
e0a791be31e35348bac1d6840e27e8e47c730f98  
2c6a0a942b9466457708117adfecb2408b24b214cd595fd00a850a8cca2a8d26  
Partition1/Root/Documents/OpenOffice-files/.DS\_Store

DATA: DATA (Non-Resident)  
99928-99943

20 2021-11-15 10:47:20 Partition1/Root/Documents/pdf  
20 2018-10-19 11:31:09 cafaa4fe6206c58f5dec13c3ea9d0371  
7ed087345df3071191fbb455470a4ae8e4b423e7  
2a42cd96488ebc2e8fd807008726dee7ab1709c007fa9abe8affbc5843591bb0  
Partition1/Root/Documents/pdf/file-sample-pdf\_100kB.pdf

DATA: DATA (Non-Resident)  
6424-6943

20 2018-10-19 11:28:32 f75c9215162661abdd9cd1aa11d792e6  
06dcbad6d7184b39925fb0a19f55b4a9ce3f297b  
0da983da280865ec4ef11497f7ae9a3322d36b88a12b419e90109774ae50d40f  
Partition1/Root/Documents/pdf/file-sample-pdf\_1MB.pdf

DATA: DATA (Non-Resident)  
120360-122727

20 2018-10-19 11:30:08 23d2d7627d3edbc66586726cbd4225b1  
34d580da967fbc3balbc54e59da11b7183afffb6  
0dce6c42b677f621d5f8ac8abbfad0ed7d69e7e18e1f328c9276453e2b57680b  
Partition1/Root/Documents/pdf/file-sample-pdf\_500kB.pdf

DATA: DATA (Non-Resident)  
122728-124143

20 2018-10-19 12:05:41 2cea8c95dc5f5db6065f704068292867  
6628857689d03f6e0b52cdaef20c9be4f17d0f79  
5e147079d557fe26de3dbdf0c5c7aab4ac18ec13d4e31bea320d1167475dae0c  
Partition1/Root/Documents/pdf/large\_pdf.pdf

DATA: DATA (Non-Resident)  
124144-154039

20 2018-10-19 11:49:27 4bfa34445fe5e92cee0d4belc4b6afbd  
4c166dd5ad455053664bb095fbed5238f5a17a68  
1284a8bd83fa65802aa0ee0d7ca77a008c6db18cbd288f1b1f1319aae703fa4a  
Partition1/Root/Documents/pdf/PDFFile\_500kb.pdf

DATA: DATA (Non-Resident)  
154040-156631

20 2018-06-22 11:08:57 b05a97e064cc54b99daba53bde958d58  
31249aec7b1e9dd55828b296f3626c5654071860  
b0e8e10fc34b366dfa1709719cd737745581fb277a82509a60518cb5e6c8ddf  
Partition1/Root/Documents/easychair.docx

DATA: DATA (Non-Resident)  
55296-59767

20 2013-06-26 08:00:33 0a4ffa384ae31d33a801acc0e1746e65  
f09aedad237560fe3fc2d255d39520923cab91f2  
6387b9576f369e587e7c810df976b29ededf8c4f7e3f1d6662b7ccd78dc4a521  
Partition1/Root/Documents/Mac\_mini\_Early2009\_UG.pdf

DATA: DATA (Non-Resident)  
59768-66015

```

20          2013-06-26 07:58:08      12ab314eb73a4a938bed3d6550da0ff2
    22b0141246f4f5c7cf20171645c0f8de596cb35a
eada5fecc16cb98c28c54b080319ff79eb20b62a313ed4b6ba5c254a4a3ede7e
Partition1/Root/Documents/Mac_mini_Intel-based_Mid2007_UserGuide.pdf
    DATA: DATA (Non-Resident)
    66016-67767

20          2013-06-26 07:56:33      bcb1278d0441dd482bc9aafb57abe8a6
    790de86e64018a72d48b97ed9281d9bbe036d728
b9aa929d68b88288d49fa4850143e18120c67d55c81c8733e605a639637cdb7c
Partition1/Root/Documents/Mac_mini_Intel_User_Guide.pdf
    DATA: DATA (Non-Resident)
    67768-72199

20          2018-10-19 12:04:44      9bc47b9f8c3ddc76f98b888d29d58dc8
    ca2d122f689a98ca752fdbe0414e6296dcff8c68
18ca6866a60efd06455338739bed02ed3a60bbe8e9cd5e8688b7877aa2a11ef6
Partition1/Root/Documents/MyDoc1.docx
    DATA: DATA (Non-Resident)
    72200-99919

20          2016-08-09 06:43:29      cbe35c8518717402622e37fe748e08b3
    028f8ea45432e9b87e45693847d0b6c068b3096d
4868c01d946e0ab0fb2af3bb186ead65ff41d82817f8cc210e254cb115f494a
Partition1/Root/Documents/Test_Arch.zip
    DATA: DATA (Non-Resident)
    156632-163591

20          2021-11-15 10:47:28      Partition1/Root/Music
    $I30: INDEX_ALLOC (Non-Resident)
    296-303

20          2021-11-15 10:47:25      Partition1/Root/Music/Andre_Rieu
    $I30: INDEX_ALLOC (Non-Resident)
    4968-4991

20          2016-06-05 06:40:09      a44be999d6682d18644da916cc3a5569
    545dca6e41229c13c8ea51930b809c1155balae8
1ca04432f8cc56e7e11d13f9a4a930dda67d2756c68040bd280bbc6307854b2a
Partition1/Root/Music/Andre_Rieu/Andr_Rieu-
Air_On_A_G_String_Johann_Sebastian_Bach_(mp3.cc).mp3
    DATA: DATA (Non-Resident)
    508840-521647

20          2016-06-05 06:39:14      babfb3a12071e9207803c707f0ea4da9
    19c0fc620469b9f709a9e5f41358cc9f77935133
9a61b7a900bce729eab4c964ebfdac730e656e0b4206741d09f8blea9ce0d34a
Partition1/Root/Music/Andre_Rieu/Andr_Rieu-Ballade_Pour_Elise_(mp3.cc).mp3
    DATA: DATA (Non-Resident)
    521648-529695

20          2016-06-05 06:39:10      d4d8f39e2b3c8df8c62b363284524e7c
    3eea72aa9277fee3f8af60fbc7b47929339190c
aa0def648856d03145be5428ef6e00461ceab3b93c56c33d4559e98c46a4971f
Partition1/Root/Music/Andre_Rieu/Andr_Rieu-Barbero_de_Sevilla_F_garo_-
_Largo_Al_Fact_tum_(mp3.cc).mp3
    DATA: DATA (Non-Resident)
    529696-544487

```

20 2016-06-05 06:39:14 0f83a6b9df6c1c8768ff7a5466789eb2  
77dd488fc42dce156f172e9e5557c2f4ed51cc83  
88ff016fb6208004ad2b77d58c0b58ca54fcaald76a0c58c9030bc554977496a  
Partition1/Root/Music/Andre\_Rieu/Andr\_Rieu-Clavelitos\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
544488-551535

20 2016-06-05 06:40:02 e76773c030362550b84955ddb47bc7db  
bfd4ac01e34c51d4bd852ff38b63c2001e8fd151  
3e7e0a37558c0578d8333b6f4e10f09d0518065a12065f22d11a91ef388b9abf  
Partition1/Root/Music/Andre\_Rieu/Andr\_Rieu-  
Funiculi\_Funicula\_isp.\_Mario\_Lanza\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
551536-558855

20 2016-06-05 06:39:51 36f69d719447f30f50290692aelba58a  
cf6c96a7051dbc35fd6c67239e94db3f657082db  
2d5f4b5ab667f46ceda5d6ecde00da34928f393b601d23d43dd661437db76a23  
Partition1/Root/Music/Andre\_Rieu/Andr\_Rieu-Greensleeves\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
558864-573031

20 2016-06-05 06:39:14 f33002bfcfdff30eca4937b2fa02e7b4  
2913a18636137a730ee80459472f1890342bfac1  
2fdbac3252e9b287a4db3441b4f0cd6ec55dcf26f1488c37bc17c69cbd0a417d  
Partition1/Root/Music/Andre\_Rieu/Andr\_Rieu-  
Romantic\_Paradise\_Live\_in\_Italy\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
573032-574559

20 2016-06-05 06:40:24 afd9b6627e3ee2a87027fe4037b684a  
9c63c3b09f44b182b4cc95980b2e4c06429a0a33  
d7d259fb9aea96c6016bd0a2cce50a63a84344d5ca87ea98df496b4d697fbc60  
Partition1/Root/Music/Andre\_Rieu/Andr\_Rieu-  
Suite\_for\_Jazz\_Orchestra\_No.\_2\_Vals\_No.\_2\_Dmitry\_Shostakovich\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
574560-583311

20 2016-06-05 06:39:45 95412d5402c21407a4f1fedf4976a019  
a5e5dac46a0e6669836e8f74fb36f19e7dab4167  
6d0a3e7cef78acd51b5fd4402aa8d2f9e691e1666e154a58fda31050874f9a38  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
All\_Men\_Shall\_Be\_Brothers\_From\_Beethoven\_s\_9th\_Symphony\_Live\_In\_Dublin\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
167896-177111

20 2016-06-05 06:40:08 a0c6ca644336e199bdd47941f90273cb  
76d44494e624dd4740115081c055bf9e471b6aa4  
f68153eaec5a9d70b3902d84d7ade66266a3495b125a8805d4ef4f0ec44fdf61  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Andante\_-\_Piano\_Concerto\_No.\_21\_-  
\_Elvira\_Madigan\_Mozart\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
177112-204839

20 2016-06-05 06:39:23 1349bee844c598e63840776a8672c7b9  
45c0ec96e6a7ea035e011a76e6efcd9b749c43f5  
e8ec4dac74ef09da945f22715ad4de103374e725961d0ad36f4f5db42d6f6444  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Bella\_Tarantella\_Love\_inVenice\_2014\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)

204840-217055  
20 2016-06-05 06:39:12 7d8c170fdef0f9be95ebb3eb8ff5c351  
872e0e6c8c382dda836901f58d666e2e07895a15  
27649a6813d82823912829120b9225f81cae99c3152fa545b074f53fb76aad33  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
C.Orff.\_Fortuna\_imperatrix\_mundi\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
217064-227039

20 2016-06-05 06:40:13 b2d52b23a778f12d5ecd3dd17cefac21  
f03a5694e19238f4a6d361b700f958ff62e69f64  
e631522504fa6d6f73809bfbe7a6218a55b7ccec7bb17676785a1b8d17b09583  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Carnival\_of\_Venice\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
227040-248655

20 2016-06-05 06:39:28 6ed3f80daa58010724c6522a1c8599b8  
6f81fa64c5902341f43c2937f0df73f5fc436d56  
2d5575b49ef97e53966ebd96bccbb3373cb397d6a25faa306b0a294cfc830ef8  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Cielito\_Lindo\_Meksikanskaya\_narodnaya\_pesnya\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
248656-253143

20 2016-06-05 06:39:33 5df7c88018a4a90877e37f5146b64ba4  
bf1e81b6e750a7e0209fd50b8b63df0d118e8c1f  
0c86737d7209b8b3591b18ce125f04eed7e2ad356909a9eab72e6c79b951d5c5  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Concierto\_De\_Aranjuez\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
253144-264287

20 2016-06-05 06:39:10 e1469291b0a0383d587c8783a206679b  
606a92c5f170a172c0bdeac2bdb07170e3a680d7  
abebd5f9a4c397e6ea404e8b2a2bb002a6f89b45403e6af7d456d275b1c59f28  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Einzug\_der\_Gladiatoren\_nemeckij\_marsh\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
275504-285607

20 2016-06-05 06:39:25 24edae723208ebb53fa9a70c6235d174  
7cae4dc4e4c21b5ccc9feacf63ce1e50007abe55  
6b957574e65f2f23369e4c57affcc6bc8afbc0bef486c9cbfcb4ae82d0f3c78d  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Einzugsmarsch\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
264288-275503

20 2016-06-05 06:39:16 4214e0582e22356faa3006f593c31521  
648429f6f343f3b6fal5befdlfa17eldbd359e6  
0ca50844f96980e2ebc420da7319dbalb399a562a57b19436c40ea64906f5fcc  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Francuzskij\_kankan\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
285608-291711

20 2016-06-05 06:39:30 6f867a4b657fcb11eb1590b93f6121af  
2a44513002d45228f4b477c0a6fd8b7011d14006  
2407979c0e2c55845565cfce09b5141e0c00df7e7355e7ae29b063d7df9064cd  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Heigh-Ho\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
291712-294151

20 2016-06-05 06:39:12 9da23d67db029b0a2aba65a902977ee7  
f4427b8ce2d37fe2d94726a760b55565e0060beb  
b955ebef0f774c7cab342a71e978b20767797fffbc8fb6ebc9a223eee81e6e  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-I\_Hear\_The\_Sound\_Of\_Cymbals\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
294152-306983

20 2016-06-05 06:40:19 04f2d1fdff801d2ebe6df0f29a18e619  
ae5ef67f8fdee64c69cdfbcb53367450e2525201  
234ef05b32baaed3d91a60f77b5c3728eed21fff34c5c8110c5d07a57f38247a  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Jackety\_Sax\_Benny\_Hill\_Theme\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
306984-313959

20 2016-06-05 06:40:19 3a8b983d9b22d2cf58714f94272085a2  
d8888d6e7698e19dd06f88ae0c52132e808322c9  
7eae251302dfbec1381e645c1feb6fb81a3bfb40dd378c835fd7082be83b227e  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Kalinka\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
313960-325439

20 2016-06-05 06:40:05 ed26972ec518840247f114119e032cb9  
954750d662eec3f4f7469c7dc86dfb6caac47852  
43ce97cle7f4358484b18cbfcbf5046e4a9fff92378f63603a4d4d1251a3c8c25  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Main\_Title\_The\_Godfather\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
325440-334727

20 2016-06-05 06:39:44 90d6ced1e8a5012ba917d1049cb86d83  
c8563a0a974c53b5a410522f68392c92230997fc  
9fele61c05e2c3815df1a7b4f2933b8fd3d8fac85f21cee97bb890259c2268cb  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Marche\_De\_Radetzky\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
334728-343527

20 2016-06-05 06:40:22 16c30e0592019ff78261b8ace757d93c  
26c8510995f161358ca9a623cc6830ec0f3bb7f0  
0926727b89c24ec0837ec080a9fcd6dca7977568a0c4cdae2f0bdfdde21588ce  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Moonriver\_from\_Breakfast\_At\_Tiffany\_s\_Henry\_Mancini\_violin\_cover\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
352904-362279

20 2016-06-05 06:40:21 16c30e0592019ff78261b8ace757d93c  
26c8510995f161358ca9a623cc6830ec0f3bb7f0  
0926727b89c24ec0837ec080a9fcd6dca7977568a0c4cdae2f0bdfdde21588ce  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-  
Moonriver\_from\_Breakfast\_At\_Tiffany\_s\_Henry\_Mancini\_violin\_cover\_(mp3.cc) (1).mp3  
DATA: DATA (Non-Resident)  
343528-352903

20 2016-06-05 06:39:22 9f2fa86941e53af861f58a20fe4ca3a0  
048dae683de9566f2444750ce4e18a59b2f14b39  
3adba60be7fc3f52ff992361feb663af28ab74f5ff475616368b6d69ba4605b4  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-O\_Sole\_Mio\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
362280-377447

20 2016-06-05 06:39:08 7a4d0e64b2e59713d8372bc8c33a413f  
6eb557504149913d0642d0a355fb57c2a168af78  
650857fblcbacbe2984478823d857c4c49055302e375039a389112f314ce28bf  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Sabre\_Dance\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
377448-384543

20 2016-06-05 06:40:26 85af6129badd4d015270a811c686b5ed  
fa8560286a78c9fb2476223d241dabfc080ac585  
72454419c59109188499bf8f20f94988ab0f6feec1ef0b083cf0b3d481919e0f  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Second\_Waltz\_Shostakovich\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
384544-394927

20 2016-06-05 06:39:37 d8f4430b58e89bfbc7e04d9c8c1ae85  
ed606770fb935d2c7da8cec4634ae25cf6251bc0  
258c0d8334a22f8cfe48cfa4f407faa4911a86e6dc0159eed3943989efc5aeb2  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-The\_Blue\_Danube\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
394936-417087

20 2016-06-05 06:39:33 526ac06ad6e99e345c605e8ee5308765  
a26404f1a20c22fb35c1f2e1a789689e16503f05  
3f19694235113ab6393a3e3b9e7a7c0bff2c34de5f5a23b1946f19dbc44b2522  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-The\_Gypsy\_Baron\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
417088-437583

20 2016-06-05 06:39:41 5e069942912410b0a2b9a07393c5bca8  
1d9a975521d5841a4096be46b52cea589a3b996a  
d3ed442842ec32249c32fd65368878ald3fffb0b6796c5a7fe23ba072c9b13792  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-The\_Stars\_And\_Stripes\_Forever\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
437584-448295

20 2016-06-05 06:39:30 620bf7a865780b1d6f5357af14d91ad5  
7634bcf96204d17693e4616ae29abad6499624b6  
6a06815b8af9bfb97b6f6363c4f818439b69b22dd25dfd77fee199125fe00c79  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Thunder\_And\_Lightning\_Polka\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
448296-460503

20 2016-06-05 06:39:16 c9cf9053c04806485687e3cc0c26fef2  
56258d0bc0e87ebea17ec4f918166e2387711f1e  
350efbb5f6dd944682942dd6e88bfbd4cflc60104bcd95a172067ac32e9538c6  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Tiritomba\_Love\_inVenice\_2014\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
460504-470655

20 2016-06-05 06:39:18 e9f2e7b7ec1b375bf8409bbb63c0c1d3  
516710c7d6977e5654ba350b12e3619d2272ad3b  
61bleled2daec5f1244624145ccd81aba6efal6a5f38bcf150ddbalc78deff21  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Valse\_Neige\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
470656-481119



20 2016-06-05 06:40:01 5f5e765df138f0d8695d567bd6ba7ebf  
4a7d04e3579fcd2a5a95d890264fa507b1de62cb  
9940e93f8931702e4f68baea39708e3b3a7f2fa3e7fef0060d60ca2158616b8c  
Partition1/Root/Music/Andre\_Rieu/Andre\_Rieu-Viennese\_Waltz\_(mp3.cc).mp3  
DATA: DATA (Non-Resident)  
481120-508839

20 2021-11-15 10:47:26 Partition1/Root/Music/Barry\_Sisters  
\$I30: INDEX\_ALLOC (Non-Resident)  
7016-7023

20 2013-10-18 13:58:26 ca8ecbaf0d6dc35e2633236cdd4fd3a3  
7bd6f803814c58ef522cd3ff8a894ed0ca154bfa  
0ff94b864e65320d8059654c503843df15f2edc91768e6d5821c557c845215e5  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters-Ketsele\_Baroyges.mp3  
DATA: DATA (Non-Resident)  
583312-588871

20 2013-10-18 13:25:14 2cac595c471dbc63b18f64d7402e5a47  
48db9c5251b72973949dcf6cc0696bb3e42bc916  
b1518592e55d37fd09cb91b3d1a9e66b49dc0b72cc673f189b5ad18ee75f664a  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters-L'Chaim.mp3  
DATA: DATA (Non-Resident)  
588872-595495

20 2013-10-18 13:14:20 ab3e597a143beb7cca18afabe6b2cf05  
0bea492a98c11c131dcae40348a47e2fb68d33d3  
b81c2fbc0e859c621194bcf7a25cffb4726452e5d0c8ca864e03f00188e71c96  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters-Tum\_Balalaika.mp3  
DATA: DATA (Non-Resident)  
595496-602071

20 2013-10-18 14:14:54 93faf50fbbb3852820fd0af9304d981e  
dc99e2890538319da9a264eb59a0400b7e4faa6b  
4bb557581d0a2209c20e156357e008fad23b9c22307941c4d2304cb481a28c66  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters-Vaybele\_a\_Tsnie.mp3  
DATA: DATA (Non-Resident)  
602072-608455

20 2013-10-18 13:51:52 665e256b848c6932d601ba9c7a69d71a  
b7d4ce6579d8ecd957ff0c14651de2bdf2292796  
e98e2fe701aadbb80ac154396492411124619eae88ded655d8d1f77bfb575116  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters-Yidl\_Mitn\_Fidl.mp3  
DATA: DATA (Non-Resident)  
608456-625383

20 2013-10-18 13:06:18 ebc7efe7222437cea77bbb756ae20b66  
09241e9a275c0c2d05ea04fb984fe05af985d8ec  
920841b083ac3a3783c057428cf447576d9b2eda5bf0a20efee56e70c30d2e4f  
Partition1/Root/Music/Barry\_Sisters/Barry\_Sisters\_Chiribim\_Chiribom.mp3  
DATA: DATA (Non-Resident)  
625392-631599

20 2013-10-18 14:20:22 d835c7abf97c3739e3ad3a2943e3bbe5  
011f89ba643ce150000bf5db3d5f1d25d93f0293  
f9eda23a76b4fe6ad41117ae5fbb18e914fc400fa01533c39bleeele7ff2409b  
Partition1/Root/Music/Barry\_Sisters/Bublitski\_Barry\_Sisters.mp3  
DATA: DATA (Non-Resident)  
631600-641023

```

20          2013-10-18 13:28:36      d8cdf8cfd4419fbb70c7f5df347f6890
    1fe23a26be467f59c14703cbeeb580ed5de3a5c9
bc0052be54f9175bb0e590aac8ecf1dcf4ba7587c263cf9fca6bc8ccc0feb3dc
Partition1/Root/Music/Barry_Sisters/Hava_Nagila-Barry_Sisters.mp3
    DATA: DATA (Non-Resident)
    641024-648903

20          2013-10-18 13:41:54      675c2e035c953df83bc6dd245966ff8e
    30d3a38b8b4f55bd67a82035c42d0a304c1db394
f16175bc9c26f9fe3fc8d8b8a497eef3d29f6642372a9472cf33e805cf4c8882
Partition1/Root/Music/Barry_Sisters/Hevenu_Shalom_Aleihem-Barry_Sisters.mp3
    DATA: DATA (Non-Resident)
    648904-656031

20          2013-10-19 02:03:04      8cff6cb8a834d5a0e00366853c2ed8bd
    494933f834d9c170f0a3aff602c2093a8e62ae13
bd0271ca25d8f9c6c58bb13c6bb8b7dd478bc1255da5cb427e3ald836dc11db4
Partition1/Root/Music/Barry_Sisters/Papirosn-Barry_Sisters.mp3
    DATA: DATA (Non-Resident)
    656032-665879

20          2013-10-18 13:37:44      c928185e9da6fd4bb10b64b5b578552f
    32fcebb494330a3fff73fdc9675c4c8057f3cd00
3e8a99fala7f6e3eabf64d155ble57f3006a9f7847f21e798642b3a445339a93
Partition1/Root/Music/Barry_Sisters/Vi_iz_dus_geseleh-Barry_Sisters.mp3
    DATA: DATA (Non-Resident)
    665880-682359

20          2021-11-15 10:47:26
Partition1/Root/Music/Electric_Lgcht_Orchestra
20          2021-11-15 10:47:27
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981
    $I30: INDEX_ALLOC (Non-Resident)
    54296-54303

20          2005-04-07 03:11:40      e56b81d6e95ba198ba13f55a6c94d9d6
    1f7b7dd059fe88dd1373c218ca3fdcd549f32758
348646f1fa7fd3f99d595b68a33c90f2ec43d0a439d1bbb2768c06f47ffae21a
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981/01. PROLOGUE .mp3
    DATA: DATA (Non-Resident)
    50824-54295

20          2005-04-07 03:11:40      e183a3f026acbfaf8e4c8c9997c03721
    8bb96b64b57214247bc90c129cf363ac14f29a3b
f7d0d08f9116c4279f07c753763b89aa4415afd102b3235ab4e8f3caaadc55e7
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981/02. TWILIGHT .mp3
    DATA: DATA (Non-Resident)
    700776-708375

20          2005-04-07 03:11:40      e71574ae3bdb6a6d39a777b63f98c261
    ea5a27d3abbe6dad451b8d5fcab8e2ed20916918
6f1ae25b46b334a0814a39f0176879857d32beca920d546573e80f60a89d3b1d
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981/03. YOURS TRULY, 2095.mp3
    DATA: DATA (Non-Resident)
    708376-720199

20          2005-04-07 03:11:40      1a5112f377cacd6d35e093d47c52fcc0
    7b5b697381584a2cb6e6c32199d563c7807019ef
9be8d830897a6e8ed2bfd9f4f3196e8a5c32862667cfc049ccel96aa7fcb0561
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981/04. TICKET TO THE MOON .mp3
    DATA: DATA (Non-Resident)

```

720200-731799  
20 2005-04-07 03:11:40 f9d68c6e0468aed135415687d65e41a6  
bd2292b32c41c9d04b8c64e80162c37a14377986  
32f769043c203cd172d4595c79e043e650b48b218e0c7187c7c53576272d98e9  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/05. THE WAY LIFE'S MEANT TO  
BE .mp3  
DATA: DATA (Non-Resident)  
731800-744895

20 2005-04-07 03:11:40 75d6f8ea67e56aff2c37a7355c311c81  
55a5fea075d9c791b07109450e3f80f3c36ad700  
dec7a546e447a06e821bfae76d56842886a66e524a49e27126593b9c0fb806dc  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/06. ANOTHER HEART BREAKS  
.mp3  
DATA: DATA (Non-Resident)  
744896-755583

20 2005-04-07 03:11:40 f20ca468c271d565a9cf8a2b5dc00064  
ff4c2759b70f49cbe7926aaccf1da736f3dc5c6  
644040723alcd11e09a7bf8e4d8cd88cd30716b9679ae9884af9583dd6744e44  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/07. RAIN IS FALLING.m3  
DATA: DATA (Non-Resident)  
755584-766583

20 2005-04-07 03:11:40 9f71d12c63e3c3df2a343ad6f7949e1e  
7517b6d91b71bf3e4a52ac33ca78ea99951f1d76  
2ce95099a194b20d8e64d8ed79ab4e61ecbc784b6695e3af431a7e9dcd92bad7  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/08. FROM THE END OF THE  
WORLD .mp3  
DATA: DATA (Non-Resident)  
766584-775807

20 2005-04-07 03:11:40 13521f054f7d59ba7cab3df7da45257e  
ca176095f3b9164be65daba5f2a97f695f40dd07  
0a943aaa8f0318db5db96170499523f8890de0a788885943adba75efd7db8af6  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/09. THE LIGHTS GO DOWN .mp3  
DATA: DATA (Non-Resident)  
775808-785815

20 2005-04-07 03:11:40 c05d2969d001899b4a175a4e68c2fecb  
9294e29e1f30e28f23922416b5a908a3109bb9d5  
1790a250729eb139b25d588de3f53834b8f2f7cd2928125784b0df8aeb3a892b  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/10. HERE IS THE NEWS .mp3  
DATA: DATA (Non-Resident)  
785816-796343

20 2005-04-07 03:11:40 4a6ac89638420964737bcd597e12f667  
ca4fbdc19d85bb999c0bc1299f57f25a690ae3a4  
4a47e924470a26a57ebb89b947cfdc9eb96477838050fea459aaa01544a8aa8d  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/11. 21ST CENTURY MAN .mp3  
DATA: DATA (Non-Resident)  
796344-808063

20 2005-04-07 03:11:40 1b3bb20062656046700d2356c66978e6  
e985fc4780e2f3ce001ba44e6cadaff8df4b4bab  
0089088cb3062cbfa50f8d414ecb68c5c94f9d9aec77966fae55a154553f7f5c  
Partition1/Root/Music/Electric\_Lgcht\_Orchestra/Time\_1981/12. HOLD ON TIGHT.m3  
DATA: DATA (Non-Resident)  
808064-816815

```

20          2005-04-07 03:11:40          6553cefc73c2eb9c974d65d9e100ce63
    a63cf43e4e070796ale0f5636585ef855e647226
5b78807b8012ed28af78845c00244a3ae6575e8afaf280d0c3184de600d55541
Partition1/Root/Music/Electric_Lgcht_Orchestra/Time_1981/13. EPILOGUE.mp3
    DATA: DATA (Non-Resident)
          816816-821127

20          2021-11-15 10:47:28          Partition1/Root/Music/Ennio
Morricone
    $I30: INDEX_ALLOC (Non-Resident)
          54304-54311

20          2001-08-16 14:00:00          e9d6556f18f45fcc506d99d17ca3010d
    885bdba70b153885ad660dd3f87f0ecbcc7d21d4
554c109bf97dcfca8d5bbc27d255dc2e963ca7430056105fc3538529ccdaed38
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-A Gun for Ringo.mp3
    DATA: DATA (Non-Resident)
          821128-825511

20          2001-08-16 14:00:00          4b2bcfafa655751e0be9aad58d32df98
    a8183fbb98ddca996fd50fdc7437c5bdfef48540
f54573a8c38b12641a9a9db40ba85ddfa0ec67103e3967d5f45e7f97fe9971f7
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-C'Era Una Volta Il Trenino.mp3
    DATA: DATA (Non-Resident)
          825512-832503

20          2001-08-16 14:00:00          cc03b5901e0950ed7f6fce239c53f387
    97a6202ed8a5a7613a5d92b8670654fef60c802f
d77bd85c9a96cc1ba4a3f091499a725910552ad4a2b7df1ee78412d09f5d0934
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Chi Mai.mp3
    DATA: DATA (Non-Resident)
          832504-840895

20          2001-08-16 14:00:00          8242372bc075979a755f5ebc64b1c0f0
    bd4b071c45c321ae859e6falbc29a8c6408982a2
d92f7501ae994e95527fdd1e6e3d721c206466f1271e6a27alb0a0196b23b14c
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Cockey'S Song.mp3
    DATA: DATA (Non-Resident)
          840896-848991

20          2001-08-16 14:00:00          167926ceb7f39e1707f1514fb44ac9b8
    bb942a68678bf29a9e0d847e5e644bfe43471a96
7cc3f790f6f420158a51bfc20c7b23e468259b9b09d664f6effa116b242112ca
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Farewell to Cheyenne.mp3
    DATA: DATA (Non-Resident)
          848992-853927

20          2001-08-16 14:00:00          9ce646a5049fdd19bee62c84eabebd5a
    95d1260f50f41efb91474471f0111428979bbf41
ec42a38484cc6fd4fc83eee6471d01115db77bf174c586d8b4edca7b06b8a387
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-For A Few Dollar.mp3
    DATA: DATA (Non-Resident)
          853928-858559

20          2001-08-16 14:00:00          6704adff61e44c1f7daa9ce2baabbab0
    051a4ae5d60171a60c6074a2fb36621fcaef211
d4b43c1f5371386e9f1b7dae44f7deldbe8d9ad78da0b2a9ad6a85da6a8c02f7
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Goodbye Colone.mp3
    DATA: DATA (Non-Resident)
          858560-861895

```

20 2001-08-16 14:00:00 df47b2ebadac3343ef63ba820f567d55  
21c4de7b3fb30bd0093cab0c8f19d7aeea3cf10a  
c24c1a09c7dda361b870b14634ae7d73ee8d8032ed9edf9dc11335ecce8ef580  
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Le Vent, Le Cri.mp3  
DATA: DATA (Non-Resident)  
861896-876823

20 2001-08-16 14:00:00 dd654b0d7aadbd4ed5aa2f07f601d54d  
db453dc07334b16e5cd0dec60alc2fc89ffa30df  
54bde5e91c19478763fd4a20947a573ffda7a217832e596849967eeb7bfddeb8  
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-March of the macgregors.mp3  
DATA: DATA (Non-Resident)  
876824-881551

20 2001-08-16 14:00:00 f2857800c13a4eb3d2c196093921f56b  
bfcc6fbcef98f95d5ec1c0774157de3b20335f0c  
9c2c7fa2afebd245606977bfb5b47dcf966099fee8edada864245eba72655468  
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Once Upon A Time In  
America.mp3  
DATA: DATA (Non-Resident)  
881552-888727

20 2001-08-16 14:00:00 66ead755183f910d14aeb071b1b0a906  
250c0430cad1a773f2bc950312ce2447109827e6  
5f6e0777093692d2c79dd756154fccd87de7216cdfa745376ceeldfad28cb49d  
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Once Upon A Time In The  
West.mp3  
DATA: DATA (Non-Resident)  
888728-895631

20 2001-08-16 14:00:00 f8c04ca99abc731f691dac5d1258c623  
50a4f21dc3daa70a9d5474bca6cbd1b2fcc5069e  
cd81f63dba683d5a7be2a10a67a5c953a67ceb62f4f5c60972103fae64924410  
Partition1/Root/Music/Ennio Morricone/Ennio Morricone-Overture a fistful of  
dollars.mp3  
DATA: DATA (Non-Resident)  
895632-901135

20 2016-04-28 14:51:04 678be5fa10fd689690b47a63b8091549  
8a196fde7b67298c6f65f44b17a74a318218c748  
c0fba9eb8cd60edf592efde7a94c273083a20f55fa5e7349781bbae8605025d3  
Partition1/Root/Music/ CONFEDERATE\_SONG\_TO\_ARMS\_IN\_DIXIE.mp3  
DATA: DATA (Non-Resident)  
163592-167895

20 2016-04-28 15:12:33 cb2a01e7a4de030627a8bd11330853a4  
55d40b7ca48373cc59e03b2614a0005731d5de62  
605c872d2891b98875f39782521e108538dc511464535a89a76b786b48348c81  
Partition1/Root/Music/derek-warfield-the-southern-wagon.mp3  
DATA: DATA (Non-Resident)  
682360-690663

20 2016-04-28 15:14:01 d09612ad1b02eb2f89ce0f7cb54687b0  
72d986512c390254a289a02ea36c1a6b10ff7cd8  
9c783ba314837f59174f2a3713327f92fdc0cb4de41643bd23ab8717a3887989  
Partition1/Root/Music/derek-warfield-the-wearing-of-the-grey.mp3  
DATA: DATA (Non-Resident)  
690664-700767

20 2016-04-28 14:46:58 31cce7cada7d6e1250024562038f851f  
d7bbdle78ad71bb930cc00b809ea08ae7d3f8c06  
48ef762818c7e36088ed5ca27c8d0f725ee0ea16860cae92cc810b5161495de0  
Partition1/Root/Music/Im\_a\_good\_old\_rebel.mp3  
DATA: DATA (Non-Resident)  
901136-915415

20 2016-04-28 14:36:43 698ab247141b7ee08376ca4bdc107614  
324362db1940e541cb85932aabba5335b6d39051  
2c23952b20f4187c39d0fd1a78ff32d49c6d217d49eb3f60d45d2643a24121a7  
Partition1/Root/Music/johnny-cash-cry-cry-cry.mp3  
DATA: DATA (Non-Resident)  
915416-922327

20 2016-04-28 14:32:14 24d2f32b70c8720297b4683e45526d53  
e0dd254f7b546f3e11ccele9a09f58570c361dd19  
7adc7fe757bc7cdef0fe354b0bb8d78a22c192f8c4a52c177d9a025297e213a5  
Partition1/Root/Music/johnny-cash-san-quentin.mp3  
DATA: DATA (Non-Resident)  
922328-929727

20 2016-04-28 14:38:27 ea34e906ad80d8c007b228d64f43325d  
61c9e3055c945058176152d9e3173f90a9f4c37b  
fd4d14e4c536ced737fddd3c9503c4d6fe2fa2b15a797bffce2a822b6edbdb01  
Partition1/Root/Music/Johnny\_Cash-I\_Got\_Stripes.mp3  
DATA: DATA (Non-Resident)  
929728-935607

20 2016-04-28 14:29:20 012ff60673c13ee257122f7c89ccc8a1  
3bc32eb8195628611ebbl1ecfe891b5ec974d3e5  
63c6eb80644401b50f6056ccfa6bba2b28acd50354de27ab94ec7b2bb3838a35  
Partition1/Root/Music/Johnny\_Cash-Man\_in\_Black.mp3  
DATA: DATA (Non-Resident)  
935608-949151

20 2016-04-28 14:22:18 59d71c51254e6a34ec2b56bd24215f0e  
ae45fd4e2ae3f49d99703e42ab4098eb971d2454  
1c48623249bf89e918b06169d6e6ff08f5d9902ec744762dd99d040f690348c1  
Partition1/Root/Music/Johnny\_Cash-THE\_GENERAL\_LEE.mp3  
DATA: DATA (Non-Resident)  
949152-956031

20 2016-04-28 14:35:10 59f3006e9f2f718ab75f7373e92bbd12  
bffb06aa970738517061f1358e318e5cc78273c6  
5f7d1a6b32d4f316ac05b41e91b6a2752a860338cb7c09850c5d92a3ce897472  
Partition1/Root/Music/johnny\_cash\_ghost\_riders\_in\_the\_sky.mp3  
DATA: DATA (Non-Resident)  
956032-963071

20 2016-04-28 14:44:03 5286083472934c6997889b1384dd750a  
f3eb5f4e78bfcala1e4718c83ale3b7a8efa946f  
e02aa2f29274a73d1d4580cb00f5bc6f4166ca87427e0d8a4558ffea3e7fc1bf  
Partition1/Root/Music/Stonewall\_Jacksons\_Way.mp3  
DATA: DATA (Non-Resident)  
963072-967495

20 2016-04-28 14:58:37 aec6b3e9c714bdb1472d21aad613006a  
e0c8ab1280482e428a65286e156a3287274fdb3e  
d3b8e261c2afb6b0989e6a2d83205ea06603345ad3b336447d68ace48e697af7  
Partition1/Root/Music/The\_Bonnie\_Blue\_Flag.mp3  
DATA: DATA (Non-Resident)

978264-988463  
20 2016-04-28 14:16:20 85c29de2ac785e0f2453e0b86334ef54  
d5b2bc5822e324b4e943e076e6075aab8314cb56  
a9070f9bc811a4174461542046a71870a99a84c5d05dee4452bcb1ce24f72a91  
Partition1/Root/Music/THE\_BONNIE\_BLUE\_FLAG-1861.mp3  
DATA: DATA (Non-Resident)  
967496-978263

20 2016-04-28 14:17:10 6cb3521e4ab602c95a09a61348545cfe  
3bdeb449dc5dbf5508e097b41a91d85c8a02df3f  
c56dbe344b96a59932a0049378a6c591d19d189948ea0fd1e3b33dfd2ff6e7d4  
Partition1/Root/Music/Yankee\_Doodle.mp3  
DATA: DATA (Non-Resident)  
988464-993359

20 2021-11-15 10:47:35 Partition1/Root/Photos  
\$I30: INDEX\_ALLOC (Non-Resident)  
54320-54327

20 2021-11-15 10:47:29 Partition1/Root/Photos/Diving  
20 2009-04-29 02:52:42 1be9257a5f5816119alee7932f277709  
b164610273e1684806c4cfdfb087dd6bb9c45ae4  
de7eee26d1a8ef8b8f7098ca323d635bc2f2e2ec3260a8e7cdb9afee41d679aa  
Partition1/Root/Photos/Diving/MyPhoto1.jpg  
DATA: DATA (Non-Resident)  
993360-998599

20 2009-04-29 02:53:22 96d4bd523d897cb9b71d81b9703e7361  
d4688bb699075afc0892b2a044eb42367c934c3e  
7c0cb8fc34246a7711cf0e0ea56589fafdc204a911d20fe60ec23f516ca6a859  
Partition1/Root/Photos/Diving/MyPhoto2.jpg  
DATA: DATA (Non-Resident)  
998600-1002175

20 2009-04-29 02:53:58 bb6bbeaad2b8ef9c9abe4648de3a5999  
cdfcfb3779a3a208af1f7643914dce53632588c4  
6030e056aa02221686bf6e6a32cfa7abff8a1401c28b43d57eab23a2aa1fc5f2  
Partition1/Root/Photos/Diving/MyPhoto3.jpg  
DATA: DATA (Non-Resident)  
1002176-1005727

20 2009-04-29 02:54:20 beb944c66d0c83a708felc69011a5d42  
4a9ebcece6a0c3a780f6e9852e065f2ce7d625a0  
2b6598767763c096alec8161fd98ad00c878a514e91224e74598774e1285d00e  
Partition1/Root/Photos/Diving/MyPhoto4.JPG  
DATA: DATA (Non-Resident)  
1005728-1007495

20 2009-04-29 03:13:38 55bef019410f8bcd10731a46fa250909  
35fa0050b34ec540b6f9facd24d01d31094f8bc4  
c343fee6083774eeabe36c0e4496de4af942ec99ac3f454c675cef28cf6f9552  
Partition1/Root/Photos/Diving/MyPhoto5.jpg  
DATA: DATA (Non-Resident)  
1007496-1013919

20 2021-11-15 10:47:30 Partition1/Root/Photos/Helsinki  
\$I30: INDEX\_ALLOC (Non-Resident)  
54312-54319

```
20          2007-07-25 00:14:30      28b5e80d00c5c1e44547e944319f2fc4
    6cffe5d309990d77989a119859d4f353f0e0169a
2622f7b32f509b200ac78787efd194133f8d36000fc739d22f0dad47a606e7b4
Partition1/Root/Photos/Helsinki/Helsinki 005.jpg
    DATA: DATA (Non-Resident)
    1013920-1016151
20          2007-07-25 00:14:35      0985e9acf3eed9f6efdc54f6444a890c
    8409c041c31a8eb3023994ed1b8f49781abf32cd
477aa2e3af10f4bc3715b20d37e89e52692450827b65563ff2223cc54d763287
Partition1/Root/Photos/Helsinki/Helsinki 007.jpg
    DATA: DATA (Non-Resident)
    1016152-1018815
20          2007-07-25 00:14:37      6c0f93298d0e48ba408f661bfc2236e6
    6fa4cc63ea595337398e2edb7f070860cd510b03
8cfc04cb423aa7bfdaac2580107e4dc2a5d05544848ea3de7c8c2fd22519390f
Partition1/Root/Photos/Helsinki/Helsinki 008.jpg
    DATA: DATA (Non-Resident)
    1018816-1021879
20          2007-07-25 00:14:39      eb17a6b5efad44800ce7d7d83c69eff6
    ea0ca44a349338d6c4776c6a96fb7829316d9041
b83b385bf8de8d8457ffa0b8ae5e6adb625fc9153ffab29bae8afda438cb516c
Partition1/Root/Photos/Helsinki/Helsinki 009.jpg
    DATA: DATA (Non-Resident)
    1021880-1024591
20          2007-07-25 00:14:54      52a5aadcbfcacaf383d1a0297bac0fb533
    7faad9d693e98fad561813e6d4257fc34ef214fb
77cfcae9196c54e0a33116bfc6659e33835bae5ade4aa19a71f3a64fdd943b04
Partition1/Root/Photos/Helsinki/Helsinki 014.jpg
    DATA: DATA (Non-Resident)
    1024592-1027959
20          2007-07-25 00:14:56      ff01a8fcc0828e06a441d6da9d971b25
    aelfd253e25c59f3825809fc18055c7a84dde7ff
78dd23b664150bbfcedb1a8146c8b6db6e00b6839ba9f3e7b5c064d61740fe77
Partition1/Root/Photos/Helsinki/Helsinki 015.jpg
    DATA: DATA (Non-Resident)
    1027960-1031215
20          2007-07-25 00:14:59      b7fd46830da4a1c74c0dca5be70fcdfd
    b550ecd95a731e7fe45cf52b43676883409773c9
08447b4529b38472248673ee2ebb2e9f24958cbd662bf53680fe5bb43f647846
Partition1/Root/Photos/Helsinki/Helsinki 016.jpg
    DATA: DATA (Non-Resident)
    1031216-1034159
20          2007-07-25 00:15:14      42cd2c12e0f30c16eaa5e32791ea2865
    e6d0da7d265e116f8a7988070b2a8296798f2d91
df4725a0326e39af256d3a49cc83e4d4d435f121ac79ala26eb1177060031040
Partition1/Root/Photos/Helsinki/Helsinki 020.jpg
    DATA: DATA (Non-Resident)
    1034160-1039799
20          2007-07-25 00:15:55      8364499c7c8615c153efece95eb08384
    2465309940f8a58182b4ed088bef7665d6b35159
84c973bf92e484c4f56575d929df42fb4ffffa275d9d1558a57d5618eec4a3be
Partition1/Root/Photos/Helsinki/Helsinki 036.jpg
    DATA: DATA (Non-Resident)
```



1039800-1042735  
20 2007-07-25 00:15:57 21f868c3943b06282bb955cd9acf182b  
7957e9ea9347cb656f160cb053034817a52d803a  
5716a3e5ee831b4df017e0eccd9df6a4b082c330d23ed134ca8859cbff65e00c  
Partition1/Root/Photos/Helsinki/Helsinki 037.jpg  
DATA: DATA (Non-Resident)  
1042736-1045207

20 2007-07-25 00:16:04 5e0825fd4b9ea941bc183b07ee53b30b  
10f84ba2a8812560d8b9f840046c1228cc47482a  
34c4ad4320904766be78eb8a5c6041ad0dd63a8c6796730ac99f6e6d7ff375c1  
Partition1/Root/Photos/Helsinki/Helsinki 039.jpg  
DATA: DATA (Non-Resident)  
1045208-1048895

20 2007-07-25 00:16:26 f60112a20189a34ded555d744fc995cd  
2031d955a59fb5bbeaac6c5d02f34e55134791be  
9fde08acebe4cb7e8dc5708a7d088791a25530418c9a35c9117da43c03a3013e  
Partition1/Root/Photos/Helsinki/Helsinki 046.jpg  
DATA: DATA (Non-Resident)  
1048896-1052791

20 2007-07-25 00:16:53 6bdc1d3560757979d5a8c74499703fca  
d3734dd78b1dc1d7aa80e7a37c052a64e90b7161  
86abc31897dd528e0d2bfbe7adbe0cf13c750f0a335cff560bd9809ee30200ec  
Partition1/Root/Photos/Helsinki/Helsinki 055.jpg  
DATA: DATA (Non-Resident)  
1052792-1056847

20 2007-07-25 00:16:57 eab027d27180b03de7e2545824918f50  
a7840875a34c7b006c79a13f2cf4c97a8db83f84  
587323db9e818f483b1f6dff3720e3c94db08a508d93473ac6c82f43dd2448d9  
Partition1/Root/Photos/Helsinki/Helsinki 056.jpg  
DATA: DATA (Non-Resident)  
1056848-1062087

20 2007-07-25 00:17:39 fe959fdcae31e90b0fdb0a3982e59b79  
74a2b387cd3326b645d66c1219ab2104d4f10d25  
7d23a5b29e990elf4310f53f432e73dd89001a511fa0a8672214e7ab2ab86bb8  
Partition1/Root/Photos/Helsinki/Helsinki 068.jpg  
DATA: DATA (Non-Resident)  
1062088-1066479

20 2007-07-25 00:17:51 048ac817b294fcbd35226d924dd6403e  
136b336c3532deca6c127d208732db730c3632d4  
7b835006d4c1d9f5785f1a784cb86d2be8f47cef5e697df057dd918070c417db  
Partition1/Root/Photos/Helsinki/Helsinki 072.jpg  
DATA: DATA (Non-Resident)  
1066480-1069903

20 2007-07-25 00:17:53 2b62227eb196f862d1cf457a5ddac5cc  
347e84f14e2e129a591d2d522e81297d4d4c7522  
779fc6198aab07b47c7164961b9fe7fd337e52d4ef113689abaa1f31c264albb  
Partition1/Root/Photos/Helsinki/Helsinki 073.jpg  
DATA: DATA (Non-Resident)  
1069904-1072775

20 2007-07-25 00:17:56 890e90a5a7abb2d1a27392229808b4c2  
5acbac453876602bcb7faaba6914248a0d872608  
36274f507db46efa766e15f0a461fe5a28ed10826a281b4b96e9df0711564baf  
Partition1/Root/Photos/Helsinki/Helsinki 074.jpg

```
DATA: DATA (Non-Resident)
1072776-1075887
20      2007-07-25 00:18:01      d39d9a42c01b2108540103ce2f788520
21dfc2b20479ee49c336da51cf587e72012b5bcf
495dd2dc8a6d2604529975e79572ae86d42014b3e05ce342606fcfb234afa2f6
Partition1/Root/Photos/Helsinki/Helsinki 076.jpg
DATA: DATA (Non-Resident)
1075888-1079175
20      2007-07-25 00:18:04      8e8492d1199d9009f051056b7e87f6d0
7a03c9c26fac9c90861e698647b473f0a2a1b0dc
68029f074e36d150bec089850c56c82d5e372763c6cebedf3f471d637a92aa68
Partition1/Root/Photos/Helsinki/Helsinki 077.jpg
DATA: DATA (Non-Resident)
1079176-1082087
20      2007-07-25 00:18:06      883494b431679f7f9d39ea7d1ceb157c
50bc8c009c7c51b4616d27a1617facb6fe328fd1
5928276ed054d2e97359345c2ba204ce53felcae4357100ef71dfelaa3a023ca
Partition1/Root/Photos/Helsinki/Helsinki 078.jpg
DATA: DATA (Non-Resident)
1082088-1084655
20      2007-07-25 00:18:08      f47cd4b931c58d5c6afd085467ceed91
b08393e2e176e342a02d3faa0ddd920cad62c021
d4169e76e48b21e828783e426a4fe722ee4be7070ee164802fe941b43819e2bf
Partition1/Root/Photos/Helsinki/Helsinki 079.jpg
DATA: DATA (Non-Resident)
1084656-1087415
20      2007-07-25 00:18:11      6d75cc9c722568437c5e8794412248b6
13fa2483785d35170cc086691f4394650f91a418
ca5a0e3e2d3e675605bf3eaf97c2bfaa7aa543f26b21f168275aa41eb6411580
Partition1/Root/Photos/Helsinki/Helsinki 080.jpg
DATA: DATA (Non-Resident)
1087416-1090207
20      2007-07-25 00:18:13      9796e28ed4fala498fb0d4a88d54271a
597df2450fcb9a316a6ff38d73019d7d3a61fefc
e368ca4f127fadca31ca967bbc4e0c053b545155864d65fdb12172ccdbc041d1
Partition1/Root/Photos/Helsinki/Helsinki 081.jpg
DATA: DATA (Non-Resident)
1090208-1092983
20      2007-07-25 00:18:31      4c313faa0ef5e45095fbbfb9df12ba3b
701e94358467ab51eeb285128eab7b14c5a991e4
a113063e2a5139328035dfb08ale90ele28a547ce3d4596eld1d2ade4a8018a3
Partition1/Root/Photos/Helsinki/Helsinki 087.jpg
DATA: DATA (Non-Resident)
1092984-1095375
20      2007-07-25 00:18:33      2b19644cde41ead9a90607ddefbd9baf
bdd733f02ffa868959fd0211032d6743924ca0a0
f2e739d955a2257d9b5cee24b3748e28ab6303ae314c5ebd5007426f3cdef87f
Partition1/Root/Photos/Helsinki/Helsinki 088.jpg
DATA: DATA (Non-Resident)
1095376-1097783
```

20 2007-07-25 00:18:35 726690c9daec4197326eefalc43aeea9  
029b8a8f3e152b12ad93fc24d007dbd0c4e4795b  
9ba48d14266e1e0b3e0ef70e5784a948729ead0873ea22487a97a4d4107c24df  
Partition1/Root/Photos/Helsinki/Helsinki 089.jpg  
DATA: DATA (Non-Resident)  
1097784-1100831

20 2007-07-25 00:18:37 0c72be139e24115e6c158746f68cc331  
10b55785fbb2dd271d493be3602a5f5547b252f4  
a4e27da775a445947ae3609332aa8685a67de31c62d8057cc9499e26bd70d1d2  
Partition1/Root/Photos/Helsinki/Helsinki 090.jpg  
DATA: DATA (Non-Resident)  
1100832-1103079

20 2007-07-25 00:18:39 f85c8796fa3172ddb8bdaa6cccb10a53  
1567805661f1d053fa4d53957d6d9893e1efd7ab  
246697b1731a42e45c1526217fd9aac2ba85cc0d29970c6179e94a87f7ed03ae  
Partition1/Root/Photos/Helsinki/Helsinki 091.jpg  
DATA: DATA (Non-Resident)  
1103080-1105343

20 2021-11-15 10:47:30 Partition1/Root/Photos/NY  
\$I30: INDEX\_ALLOC (Non-Resident)  
54328-54335

20 2009-05-24 07:43:16 77b5b122cd1b05c2af50cd0836f9b985  
31a3271a5d1b054dc69992580d32f26a8adb9383  
47fa5a2e0ef322ddc7018a13324c80ea39dfda762d844de8de680b358b088044  
Partition1/Root/Photos/NY/IMG\_0201.JPG  
DATA: DATA (Non-Resident)  
1118136-1124855

20 2009-05-24 08:25:48 a09054f3acefb09a45ca4478b43640e  
05311785bee82da2d04a7b83d8fa4108d48a7f84  
401d1499cd59ec7ffc8e215baeffea2c1d752a60df93783a6c328dc3373b1a4  
Partition1/Root/Photos/NY/IMG\_0211.JPG  
DATA: DATA (Non-Resident)  
1124856-1133791

20 2009-05-24 09:58:56 a343458fad6b045f9d77c6fb646f71ce  
dd2b11785bee82da2d04a7b83d8fa4108d48a7f84  
860249189d3d69279458b6b3f41b2839fde01df255c81ceaf3c2ce13a4104a2c  
Partition1/Root/Photos/NY/IMG\_0250.JPG  
DATA: DATA (Non-Resident)  
1133792-1142863

20 2009-05-24 14:21:14 c29ac1f58994cb46c53a56f46fdde5b5  
a8f5e6e7eafcl146e3e868eaadf38cc9f0c28ebfe  
d97b2373efdab0df6877c8637749310b0c11310081e1830eac7e630232a21b8c  
Partition1/Root/Photos/NY/IMG\_0283.JPG  
DATA: DATA (Non-Resident)  
1142864-1151551

20 2009-05-25 11:07:46 f8d65215fe542da63bdee82868e0fe9a  
f9eabae61c6d18clad3c5dc2d45b1a0a01e6d09a  
fc3leadca0b68f19c6ba0be9c8ec51ec87e2fb0e718dc2ace60e257883a6162b  
Partition1/Root/Photos/NY/IMG\_0389.JPG  
DATA: DATA (Non-Resident)  
1151552-1159343

20 2009-05-25 11:15:24 f145c400d3ed9e69557851c522320a56  
3f56ea39f77f1fd9b18dc2041f51baa61504103f  
7b4c77c6dad37857ec7fd82e960db64e4c842d05cfc72115b7d439942f8d051f  
Partition1/Root/Photos/NY/IMG\_0390.JPG  
DATA: DATA (Non-Resident)  
1159344-1167087

20 2009-05-25 11:15:32 b603d9b3aff85c5f62a9e8091f2dc916  
b496ea7f8aa7ed6e5b4c893225ae3912fc8a0970  
1028b54e45ac0d610863a8e8a3448c7a428518e96b517ba9170aa5eea7cfd0eb  
Partition1/Root/Photos/NY/IMG\_0391.JPG  
DATA: DATA (Non-Resident)  
1167088-1175415

20 2009-06-06 12:01:08 94ca44fd6bcad151e18159393fc0e71c  
0b9a0d4d357d9236ac8dbc2d09b3e4792c934a14  
c8a4056f1e11d6d4041bf97db5cb37c102f9117e36009a723881f809cb84c881  
Partition1/Root/Photos/NY/IMG\_3694.JPG  
DATA: DATA (Non-Resident)  
1175416-1187271

20 2009-06-06 12:11:32 35df6163f8b1154b535bb185aced2d56  
01f1be100762c5d175ec75eb8333079551f29c00  
fc71d8ebcc188ba26d3e07a28da5ddf89078606d20d84f4922412ef8a5aac283  
Partition1/Root/Photos/NY/IMG\_3699.JPG  
DATA: DATA (Non-Resident)  
1187272-1197455

20 2021-11-15 10:47:34 Partition1/Root/Photos/PNG  
\$I30: INDEX\_ALLOC (Non-Resident)  
54336-54351

20 2016-08-09 06:29:55 0e20c4014a80419756af6b3618d894d4  
dfeb1486ddb64d89b56426847dc945d40a7413fe  
7392ae31589eeb672798620f5fa6f5776a67c7aa7494c455e509df324e915a09  
Partition1/Root/Photos/PNG/DSC00398.png  
DATA: DATA (Non-Resident)  
1197456-1204095

20 2016-08-09 06:29:55 50a39ae6bdde09570419e04899e861ca  
7d9a673c484ae32fa631bc03bdf3f3c5c670524f  
957f4fa27af2dbbc6b4d5156a8151a6222093e8dad15a7c53559c118fe8443ef  
Partition1/Root/Photos/PNG/DSC00400.png  
DATA: DATA (Non-Resident)  
1204096-1208903

20 2016-08-09 06:29:56 07a975f0d121d5710e9e0678c9f08a5d  
d15beaa4483bda7879642f452a76a5f9d0e5a2ec  
aabc57174e53dd3af315c336720dfef22fdae6ece52bfc59a8e36ed09cd31a6  
Partition1/Root/Photos/PNG/DSC00401.png  
DATA: DATA (Non-Resident)  
1208904-1214455

20 2016-08-09 06:29:56 1cfeal6f1e3b86b9d85ec43a1c146405  
c78d1c40f4579c7c8a98d9cd6629083a48c42a03  
51415fb98f758a51ec6fd914cf6b57b9d34fd3564f61b05a57df7376f038b536  
Partition1/Root/Photos/PNG/DSC00402.png  
DATA: DATA (Non-Resident)  
1214456-1219775

20 2016-08-09 06:29:57 f39301a4119a7e8b83f8bb9573675cb7  
1bd0dc7373246658aa02cd49846f51b9cb4baa85  
f5cc938586b14de903d81f20d3948c41ceb47ccbb4bc8062899f750371d5ff85  
Partition1/Root/Photos/PNG/DSC00403.png  
DATA: DATA (Non-Resident)  
1219776-1230831

20 2016-08-09 06:29:57 2b6dd7410024c29335480e4b01ecf6bf  
8b76cfdcf2c4bc8ccfef9bfa859e0a7d798bdc25  
elef35ccca901231062b8d831a77e703819a931a5e63e0c23761754798e3e44b  
Partition1/Root/Photos/PNG/DSC00409.png  
DATA: DATA (Non-Resident)  
1230832-1236839

20 2016-08-09 06:29:57 831472853caf70e4279eb9b10fb95502  
946d4e88d33b732e7ebf9e4a76ba8eac5d5efbab  
3f124d3163afa23b01b70667de6c4eb8ae56763bca0def60a74f24f7c9eb434c  
Partition1/Root/Photos/PNG/DSC00410.png  
DATA: DATA (Non-Resident)  
1236840-1243119

20 2016-08-09 06:29:58 554ec19309cce9e77234673957d843a6  
4487afbe76ff4de2a255a2cflb3c428c46ac0fel  
lada79bc031064a27353aea69860a3edd9bcfc6eadbcc9af2c115cad419cc275  
Partition1/Root/Photos/PNG/DSC00411.png  
DATA: DATA (Non-Resident)  
1243120-1249863

20 2016-08-09 06:29:58 bbbfalafbe6caf6d20727636eca423c6  
11b5983ecb84b0fd177be00e6319d2598d0e577e  
9374fb21b2c7126dfc5f7101471baffff849998d9eb42796a280c448ba95ba68  
Partition1/Root/Photos/PNG/DSC00412.png  
DATA: DATA (Non-Resident)  
1249864-1256839

20 2016-08-09 06:29:58 d6596d9f439081baed836fa0c8a28a8e  
15c0b00e68f538c8d5ef69b2bc27e9362a8dd439  
4cdcf050e903d1daa38d87b04855c7419e44409165d2ea41381c7cb122d3b257  
Partition1/Root/Photos/PNG/DSC00413.png  
DATA: DATA (Non-Resident)  
1256840-1264383

20 2016-08-09 06:29:59 3980b368079e048f6f8eed6d218f1456  
97d2ce7c74dfd4a07f6b162b69b822945e50413d  
073a2f3e47a5092e8877a46b441a3f95eaa73dle7558c746ca833b87dad1013  
Partition1/Root/Photos/PNG/DSCN0108.png  
DATA: DATA (Non-Resident)  
1264384-1278247

20 2016-08-09 06:29:59 3af85c982fdae46f578fcec569f037e  
36a556ffd3c56988dcec87a15b61c0a916132be3  
c412553bcb7e21e6cf15e377873ee80738a6b6f9990b4e84fd7fa9b1db44a95f  
Partition1/Root/Photos/PNG/DSCN0109.png  
DATA: DATA (Non-Resident)  
1278248-1288871

20 2016-08-09 06:30:00 clac17a6c98f27fbeat401359f14b515  
e6b6186c29e38ea7dbda9ba4b8c242732d4b2241  
3bb72a8e56f4f4f36760fd9256a366690650f54f8202d789bde31af8535fad46  
Partition1/Root/Photos/PNG/DSCN0113.png  
DATA: DATA (Non-Resident)

```
1288872-1299927
20      2016-08-09 06:30:01      03d72084aa58d9ce060595bcfe0257a7
973a861c8388d4caac711f847005e944edb50d13
b2ce7f5ec69b5418bc723a160f4cc8780a9d3184efb2d3de220d0cb848cb6c33
Partition1/Root/Photos/PNG/DSCN0116.png
DATA: DATA (Non-Resident)
1299928-1311911
20      2016-08-09 06:30:01      a066c510d6c6ae3227d4f675abe5b0f1
b2ae56bbcbdl1962ba46802878e67b96dcf384673
1344199eda7438278493240159d4547186da9e9f485480bf7b435f4184a12835
Partition1/Root/Photos/PNG/DSCN0117.png
DATA: DATA (Non-Resident)
1311912-1323551
20      2016-08-09 06:30:02      d5dfe820657d381ad10740edc4536a67
6b7e5f77db5bbacb5a5516ab6bbe20e19b928d48
3bd8b74067d514bd306318489cbbfd056aaa25a7cdf19e888198e35e56259e37
Partition1/Root/Photos/PNG/DSCN0121.png
DATA: DATA (Non-Resident)
1323552-1343399
20      2016-08-09 06:30:02      9a667f59d860a11fb4a0bda9f6fdf0d6
9a6cc2c151aae01c03fe955fa44b5e1e482d5ce7
7759c44a7b384eb1c5bd0e351bfd91a7a839f1ac4bfa7ab813ae5c48514a2bc3
Partition1/Root/Photos/PNG/DSCN0124.png
DATA: DATA (Non-Resident)
1343400-1347279
20      2016-08-09 06:30:03      2c08bc733d7461eeac2b1a9af2b9f360
dc4fe2772c7392aa184a9f83fd9a34114024f5ef
af0c4ab532fca75fa8f84b80a0d7fd6b3d9593f531ea989ba84b8b7f94d6a3b7
Partition1/Root/Photos/PNG/DSCN0125.png
DATA: DATA (Non-Resident)
1347280-1357855
20      2016-08-09 06:30:03      0a5e03889a84d667baabdd3094e61025
ec6077f5b83a2f683c82a7279511a6478fe98f91
f85747e4ca8289fd1ef0c96fddd7aaddf70b3733c2a91054f762968ce8ee6942
Partition1/Root/Photos/PNG/DSCN0129.png
DATA: DATA (Non-Resident)
1357856-1367767
20      2016-08-09 06:30:04      5ee9282489f0903303703bb5d77d439a
d5da1618ec1281d2e48e8f74fdce2eleab40576e
b5be34d6680d6ea87ae54801dbb57cb720b2bd872dcfc527a8550c895c03727b
Partition1/Root/Photos/PNG/DSCN0131.png
DATA: DATA (Non-Resident)
1367768-1379495
20      2016-08-09 06:30:05      9e953995ca786148098b427656a60e35
090f7c89de46092ea19b3b0a0f8b93300bbf0dc6
46d66ae03cdb2566c5893391e2c8cdd3f8402914bdd635cc9def0d46c7bfb23d
Partition1/Root/Photos/PNG/DSCN0132.png
DATA: DATA (Non-Resident)
1379496-1384247
20      2016-08-09 06:30:05      cfe7fe275b90861aa58433e1aaada445
84afbdceb6f06bc5fd4ef5ae58a7417357d2b5fb
5edfd80300f07e45c8484d52c005afe83c00b56df1e56f3387ae2047120c4729
Partition1/Root/Photos/PNG/DSCN0133.png
```

DATA: DATA (Non-Resident)  
1384248-1402263  
20 2016-08-09 06:30:06 ca234fe6fa2fc56916c1450e9fcc891a  
f62c36132b14d9afa36d1a2927cb4c5f2bba9705  
7462ead43cbfbee4df6e1673ccc2d08800641de9b32f905f0f85dd7196a916f6  
Partition1/Root/Photos/PNG/DSCN0135.png  
DATA: DATA (Non-Resident)  
1402264-1413071  
20 2016-08-09 06:30:06 2c386dda664658d66050e7cfd9d869fd  
7ca02cbaab88968b2b30e34b2d1e81cd9fe0b8a4  
d219ab0e123d60887b31202dae8c68045518346d90511b86d3c908c763b58b2a  
Partition1/Root/Photos/PNG/DSCN0136.png  
DATA: DATA (Non-Resident)  
1413072-1425783  
20 2016-08-09 06:30:07 b2b1be511998f2e630475d164efa0c3d  
1482b7550f5f958eb62e5c3a77a13b594d33695f  
7d580fccd6dfb31cca059dfd4032ec4793de0acba9c3ba89ac63fc3724f5b4fc  
Partition1/Root/Photos/PNG/DSCN0138.png  
DATA: DATA (Non-Resident)  
1425784-1432047  
20 2016-08-09 06:30:09 28c3d52822bcd0eb7123a20f9d0f71a0  
0add9ad208f1878ee29f26f74746591c81377934  
ae8696cbc2e7427fa257d6760471a8aa8255f6c17e5ade05c8c83874e8c765da  
Partition1/Root/Photos/PNG/IMG\_0301.png  
DATA: DATA (Non-Resident)  
1432048-1460183  
20 2016-08-09 06:30:10 f5e5a8ad113cf60301cc3038738018df  
db903a727602dca3f285d4c837bb7b04591dd260  
229324830ef256de4a568105244876dc6cb38c7fc883b23d1ceb599c10d529  
Partition1/Root/Photos/PNG/P1000075.png  
DATA: DATA (Non-Resident)  
1460184-1482863  
20 2016-08-09 06:30:11 dbc0c95df4c2b4a16fd5d653a03e3a03  
3fde4c2902804033cfc33f70292b5e840b649917  
f257c37d5437b8f38c33d97f2df239fb07990af33080676d5721a798c3fcd268  
Partition1/Root/Photos/PNG/P1000076.png  
DATA: DATA (Non-Resident)  
1482864-1500847  
20 2016-08-09 06:30:12 a3df8bed38651d33eac4b21dd6a001e5  
20c969a51774ada67c4488028b73fe5db1883ef7  
9475b205dded40cc9b42d5c9a5ac75021fba4c068f4elaa5f984e4b42930alb5  
Partition1/Root/Photos/PNG/P1000077.png  
DATA: DATA (Non-Resident)  
1500848-1522703  
20 2016-08-09 06:30:13 7262d86f98a816ac5aa19d5000fdaa38  
ca5a2244d3bdea722af50db79459d4f56ac29aea  
19265744bc50cc6ebdb7dd30c358d350d589827ce088da6b12a73d7bcc6b8415  
Partition1/Root/Photos/PNG/P1000078.png  
DATA: DATA (Non-Resident)  
1522704-1544367

20 2016-08-09 06:30:14 20f2266bc91a926c0af8fb8890b39cdd  
a3d919d08dfae21239593898960b415f4fcad938  
c8fa689c01b91841af197ff442ba4aefb5673021bdcc4e9cfd9e40504ac381df  
Partition1/Root/Photos/PNG/P1000079.png  
DATA: DATA (Non-Resident)  
1544368-1566127

20 2016-08-09 06:30:15 b3943271dec5e1d6f8f98ce41195a573  
9fa3da99f4a4ca7c1370f8c91d4789e3d6de658d  
60bacec13cd11f0b094df945f9024bff7b916d8491cb3219085c7d1e22322bfc  
Partition1/Root/Photos/PNG/P1000080.png  
DATA: DATA (Non-Resident)  
1566128-1587527

20 2016-08-09 06:30:16 399f7ca061e54f792c0842ddb75abe08  
f70bd20e4ae6d08da136889d32d066f6fdf17089  
fe0f4d8b2cb268cd92235375fcb5df2445c27498c663ee64f3e84a5d97931246  
Partition1/Root/Photos/PNG/P1000081.png  
DATA: DATA (Non-Resident)  
1587528-1609207

20 2016-08-09 06:30:17 badbc4166c959a41bc77820f2c1aa5ac  
24d11bd0f46e9598a4a5a09e7c2c250f4c0190f1  
fb9a16f920b54863194096ebdc384445f0fb82d3cdbf1224607fa46b6f72a6f2  
Partition1/Root/Photos/PNG/P1010289.png  
DATA: DATA (Non-Resident)  
1609208-1631775

20 2016-08-09 06:30:18 3699a09b4d90e3e0466d2e025ac71f38  
db77c0005f5554eeb928a28e642c20b1c1c19459  
424a8ae233c30ce4931ef37b5d76c6c335261af36b76af9bcb2e82e2e67a4c7a  
Partition1/Root/Photos/PNG/P1010292.png  
DATA: DATA (Non-Resident)  
1631776-1645127

20 2016-08-09 06:30:19 9c8dfa6629ca4056b66ba70df36b6155  
3014b48f9d129411703968c62347a6741bde31da  
397078f5d412f0dadf993efbbc6fc986e107bbef03a8e88a59f26d62ee629833  
Partition1/Root/Photos/PNG/P1010296.png  
DATA: DATA (Non-Resident)  
1645128-1663407

20 2016-08-09 06:30:20 449a39e60fb73cd06792eb33702e3fd2  
7aa3459012435f09a2abfe5d2aaee35beea20e8b  
70c8b6f17dfe2770bd089fc1c837863743d638b991eaf382713adb536cd14338  
Partition1/Root/Photos/PNG/P1010299.png  
DATA: DATA (Non-Resident)  
1663408-1680375

20 2016-08-09 06:30:21 ee784f441db80e795a4f50a5ed06bc31  
f544a576568271f1a70995fe83bdc6926351b954  
9d17e3ea583d57ca7d2b2abaa7b0f676a098d0e2e8508085eee3dd0df639f32e  
Partition1/Root/Photos/PNG/P1010302.png  
DATA: DATA (Non-Resident)  
1680376-1692727

20 2016-08-09 06:30:22 9b2ee5928e602ec7610cad42538a2ea7  
c8a6797e0898840a416b40a71facdc991badd151  
b3520b16941b9a6a82db76978bad29faed5bd1af715f9f8d0a9511e830e51c39  
Partition1/Root/Photos/PNG/P1010304.png  
DATA: DATA (Non-Resident)



```
1692728-1704823
20          2016-08-09 06:30:23          1bfbd10558bb2dd12cadfd3032b78572
          fec0d4502b9ff0d5b892e00edb5f8a7a391f79f2
af314883ec48e419f8dfdf653c212beldd9664af4f1fce7dd6bd56becf925ble
Partition1/Root/Photos/PNG/P1010316.png
DATA: DATA (Non-Resident)
          1704824-1726783
20          2021-11-15 10:47:35          Partition1/Root/Photos/SF
          $I30: INDEX_ALLOC (Non-Resident)
          54352-54359
20          2009-05-30 10:13:46          be7dba7a3fff3748f1f438b728b279a4
          3cc2043ed0f732f71cf92f505fafb9e8282925e2
9249d50a8d9054d2bc182f1504f085621c8db30e7fd3081b5dfd83f5d9890c3a
Partition1/Root/Photos/SF/IMG_0869.JPG
DATA: DATA (Non-Resident)
          1726784-1734007
20          2009-05-30 10:15:56          999611c3e27def28c94708e9b6203db8
          34b2fda8e0db1bdee804c403574e0e067e07cb13
71f3335d6e50b888d6f80b57c2408921466623ef90d1a6f33b6c5e8a775573d1
Partition1/Root/Photos/SF/IMG_0873.JPG
DATA: DATA (Non-Resident)
          1734008-1745495
20          2009-05-30 10:47:26          ca72b6c55f22a45908b24cbd8bf29a56
          4a6f4ab37a9caa41balb8f5b97d81b4c157d9d20
84b973d5bafd5fa96a9c62130536c457d0f67e77db155e41f819a83d13867d52
Partition1/Root/Photos/SF/IMG_0890.JPG
DATA: DATA (Non-Resident)
          1745496-1756559
20          2009-06-03 09:59:04          bfa7e431bf44e036bd8c6f77179e7543
          c501d565c9570983c7be391ad6c4175c23d8e077
e77e31291d871816c80055edee4ad8c650617c58f4dcd55b9492b8e5a07742ca
Partition1/Root/Photos/SF/IMG_1739.JPG
DATA: DATA (Non-Resident)
          1756560-1764895
20          2009-06-05 16:58:08          1854c9f44cc66810600f955e7e57bdb1
          4f878ac70788a0b2942afe7449bb2b13adac23f5
e4503c9868e27b7a333e69624fe3b7d62e2ca932e1990fd96d0fc22102111c4d
Partition1/Root/Photos/SF/IMG_3460.JPG
DATA: DATA (Non-Resident)
          1764896-1773871
20          2009-06-05 16:58:26          6f2ac54948b5b30ce16e477c66e111ce
          6fc0971621d0185a8364b15518eceb79d39b4d9e
acafd581b254a3c004a962a13f4cf37197819770b7b8b45d12315d7f74f8f243
Partition1/Root/Photos/SF/IMG_3461.JPG
DATA: DATA (Non-Resident)
          1773872-1781887
20          2009-06-05 17:02:50          2a052e493fbcdd7cdd55a850a611cc445
          442be0bacc541cfd913bfd9322b6fd453359f39d
da4c8a85efc46392dba681825a0a4eecd9a6a3d1d0f33b233638d89ea5ff981a
Partition1/Root/Photos/SF/IMG_3476.JPG
DATA: DATA (Non-Resident)
          1781888-1789927
```

20 2009-06-05 17:03:22 44652638deef4f478e07706566550c61  
b4393152bedf73c7c5df083b42ff7843d4602f67  
b5e555ca283d8ed1b765f12312f87c3c311ef157dd8bfbbe6f1392dabbb770f1  
Partition1/Root/Photos/SF/IMG\_3478.JPG  
DATA: DATA (Non-Resident)  
1789928-1799639

20 2009-06-05 17:03:42 3872c8067f88768007a636d612c3650e  
d32f3acf3b3deeb86916106fa7d9c4537979d9eb  
e9af47c22716eld660cf85cb51b096a331f74f6f630fda53e941e3fb61000e96  
Partition1/Root/Photos/SF/IMG\_3479.JPG  
DATA: DATA (Non-Resident)  
1799640-1808399

20 2009-06-05 17:03:48 035c6628e8d5bbed6287bb85cf6022b2  
aa888343c7b2cc0b633cec47a12ac1b984f7ea99  
17475eae12901a87325a745dd90adae4565f5de89f122c72a6bb64bf6de96304  
Partition1/Root/Photos/SF/IMG\_3480.JPG  
DATA: DATA (Non-Resident)  
1808400-1817175

20 2009-06-20 11:00:56 e41f63dcb998da55a02dd60fa505bcd  
a0abbb34ddd702d6497978d1f48c92aff7f7cf31  
02f936f3ba9a24f0fce9c3fa840780d36bf7eb6b01671312c085aa4c54b43ddb  
Partition1/Root/Photos/SF/IMG\_3481.JPG  
DATA: DATA (Non-Resident)  
1817176-1824095

20 2009-06-05 18:50:22 22e77e0803b18803256074b4c252bd88  
6f562ec7317481dff469c03a3e6390f9c370f00d  
036c2c5dd5e4b22b3894b3a45dd6bec0da5ca5330b3d0031c40a4e32af2634de  
Partition1/Root/Photos/SF/IMG\_3493.JPG  
DATA: DATA (Non-Resident)  
1824096-1833839

20 2009-06-05 18:55:56 1300d583c82fe612dd57d3ad910a9486  
0e57692faeabc7845441bd30ac282f2cb83f29f1  
6f6f10a14c50635a84a63fefcc97845831f0dbd5f78d54e6b16589462f825926  
Partition1/Root/Photos/SF/IMG\_3535.JPG  
DATA: DATA (Non-Resident)  
1833840-1841103

20 2009-06-05 18:57:38 8b1353ff9495552a19b0bfeec5394247  
1f4fe5885358892353a875c06b616c9cfe14d81b  
69b90255a3a0f893a3e7565c69f0cec869ed2bcel43fda09e4c1ffc99a6c00f6  
Partition1/Root/Photos/SF/IMG\_3542.JPG  
DATA: DATA (Non-Resident)  
1841104-1849135

20 2009-06-05 18:59:32 cefa4e580592809baf1c00cefacd93f0  
7c871f52b0f04cd6ceb2e6bce43164157eef6234  
965587104c3492b03b42fca3c7f84ddadcf789462f1b0d46bb972b3d6466bba0  
Partition1/Root/Photos/SF/IMG\_3579.JPG  
DATA: DATA (Non-Resident)  
1849136-1857167

20 2009-06-05 18:59:40 9143872d4928619a667153c4ed3a303c  
11cdcf422af6bfda3857dfa92b38eb9095c9d242  
4e8e53a15940b4c9aa50be4bb088aabfe42734e5b31259f750d0faldb4f0ble7  
Partition1/Root/Photos/SF/IMG\_3580.JPG  
DATA: DATA (Non-Resident)

1857168-1864031  
20 2009-06-05 18:59:48 a545a740177ead5214943f35115e2d84  
1897045c018a11183ab3acf9e4ba123e666508f1  
6fed1d2964c18f82e7d5ea8f5d3077c09a56d8536359cdd81147299abce60b47  
Partition1/Root/Photos/SF/IMG\_3581.JPG  
DATA: DATA (Non-Resident)  
1864032-1872407

20 2009-06-05 19:00:18 74896797a5afc74f9d257c087a2d7637  
407583fd0347dfa12f33662d334d230facd3b02d  
4a825f744198f83421b6a61bb96e5bce642f3256bfc16178e674e3ddb5a42eed  
Partition1/Root/Photos/SF/IMG\_3589.JPG  
DATA: DATA (Non-Resident)  
1872408-1881495

20 2009-06-05 19:00:22 191bf4eac6e4bec6779e857609448a0c  
1f9531e936ae6efdf1328c4b55e22640860e2f98  
e872c99ba38c4110b6175cd3cfl5e7fd7efbb7ce3062d96ab6c5eaa140323ab  
Partition1/Root/Photos/SF/IMG\_3590.JPG  
DATA: DATA (Non-Resident)  
1881496-1891071

20 2009-06-05 19:00:22 d8b25a6d107fa25e67c01fd1691a840a  
ea92863dc37bf6d1c9d2c8f29f16424c4f768bf6  
18a4871a2a3fbadb0d29653d8588b4fb32e41b9a3c6637279279384675f12dd7  
Partition1/Root/Photos/SF/IMG\_3591.JPG  
DATA: DATA (Non-Resident)  
1891072-1899431

20 2009-06-05 19:00:22 be2a41a0f6c956b0a9105cbc81366a86  
6f62e8ea9a06e82a63f796eb532be7ecdeebfd49  
b68f3bad91756a3e13652c6195c2884b7867f2a13cab485ce2cb779ac36f7754  
Partition1/Root/Photos/SF/IMG\_3592.JPG  
DATA: DATA (Non-Resident)  
1899432-1909759

20 2009-06-05 19:00:26 482bfbcb2665903526f3bb328d70bcc68  
61deca50b2413161e868a249afd24fa696f4cb33  
fafd55132f1cc69b75470ea0c745d694240e7184b46af5c4896a0bd741f28c60  
Partition1/Root/Photos/SF/IMG\_3593.JPG  
DATA: DATA (Non-Resident)  
1909760-1919471

20 2009-06-05 19:00:30 157a7a625ea640ff216ef35c01b20740  
69d556d9d0b24e42803719f268abacb8a9b13312  
428284f5eb2a1955514beaff192dc352276b4ff2630f8c45418a361be6194c9d  
Partition1/Root/Photos/SF/IMG\_3594.JPG  
DATA: DATA (Non-Resident)  
1919472-1929079

20 2009-06-05 19:00:32 b36d08d7fddeae5a02bf023c82f6ce6a  
9e42ca16ed3796bf4e5999a2984a0b02b16e0c11  
3f26880ee0c4a655f47b60537967f1c4343884a8641c21ccb6f217a51298b4e9  
Partition1/Root/Photos/SF/IMG\_3595.JPG  
DATA: DATA (Non-Resident)  
1929080-1939511

20 2009-06-05 19:00:34 298393890a37472a688a82e7bbc13ec7  
03c15b242f3f0b7c82bae05898db3ad4bcd912cb  
84a890dd1d913c5daccd41689890c1156ab5d45f36e34563f0c018bd145579b1  
Partition1/Root/Photos/SF/IMG\_3596.JPG

```
DATA: DATA (Non-Resident)
1939512-1949623
20          2009-06-05 19:01:28      af118fa168b1e768805bab011ed79ec3
9b25a5144660578d6cc32f6ea8c363460cf3f683
f0f404ce95f1b8b1e78ald396f3bcaebb675663ealf1456delfd929580a5f4a1
Partition1/Root/Photos/SF/IMG_3608.JPG
DATA: DATA (Non-Resident)
1949624-1959895
20          2009-06-05 19:02:36      84013837a9cd3be6cd35dd5afb77099b
946ed167cd548dcf48f35ee0990010941789cece
dd15a8d44aae3e54207f8cb5f0f4f214f0676b882f596d41009a03f2f6a72546
Partition1/Root/Photos/SF/IMG_3627.JPG
DATA: DATA (Non-Resident)
1959896-1967031
20          2021-11-15 10:47:36      Partition1/Root/Photos/Vegas
$I30: INDEX_ALLOC (Non-Resident)
54360-54367
20          2009-05-27 20:46:20      0f5cb6b4dc609659f4ce7e5alc4c01aa
fca842cc27792bel149e0186d246d9d9c40c28ecf
5b38b41aaa5e3ecf533862027673b0d4179cbcc3fdfd44e99aa2d701b4025a6e
Partition1/Root/Photos/Vegas/IMG_0510.JPG
DATA: DATA (Non-Resident)
1967032-1975471
20          2009-06-20 02:42:41      c5497d040ee9ca74aacbla627584620b
5b0a9e275afe04aee280915acb838038dbc72eab
1cfb5f3818b7930f31a8e63762a5652badd4ale58977f5954e2bac8507d1d71b
Partition1/Root/Photos/Vegas/IMG_0516.JPG
DATA: DATA (Non-Resident)
1975472-1983991
20          2009-05-27 20:55:54      be3c022f27e9b50f54fde9ed2926716d
e9blad5e0e40903ed58448dbf90701db4ff4f4bc
0ee032b760e54100eb1fc9db986ef972a23094fb7b94edd1907f94d52a0ca3b5
Partition1/Root/Photos/Vegas/IMG_0525.JPG
DATA: DATA (Non-Resident)
1983992-1991639
20          2009-05-27 20:59:50      0d30cbcb374dc62be046953738a90523
df8f55969022328fb652f8141b41321bf855deb3
c57233f22715b0a50cbd90e2b48acda7aaab245a8c31bc9a45aaff16373d9675
Partition1/Root/Photos/Vegas/IMG_0539.JPG
DATA: DATA (Non-Resident)
1991640-2000143
20          2009-05-27 21:00:44      277f3865011837bc68612c72eb9a2691
b6e63a75c77639cdade2a42ca29d8eebble5023f
613c9c7ee324ae96857260ba9e56ald3145de5ab368331035854a555c7cefa5e
Partition1/Root/Photos/Vegas/IMG_0541.JPG
DATA: DATA (Non-Resident)
2000144-2007823
20          2009-05-27 21:04:54      77acf0f1d75d65cbb59329f3253e4030
6a4fd9123679ffcfdf3e0aa00a8ab81946bcba8f
6fa349225b5fd265133ff2bd8b5d780154bfe47bdlee00c754181fe10dbd90fa
Partition1/Root/Photos/Vegas/IMG_0542.JPG
DATA: DATA (Non-Resident)
2007824-2015527
```

20 2009-05-27 21:05:02 960983bce3dfa5e34935b215f0e018ce  
31a3b17c2f0b01d6924ca2c0bb82c25flaa76de3  
b52a36769aa422b741ef739e8f8bc5fe7b820e31bbc0954f5a07f028c4c8973b  
Partition1/Root/Photos/Vegas/IMG\_0543.JPG  
DATA: DATA (Non-Resident)  
2015528-2022495

20 2009-06-20 02:42:23 06ce765c697ea92ab4782b4696174512  
f3dcfcfc2e2ddd9a76ac0d172clee07c62beec8a  
b2b195f7a62c89e5b1f9b45c3016a5e53b90b3cb8e4d6ad517d1c05b5750d0fe  
Partition1/Root/Photos/Vegas/IMG\_0545.JPG  
DATA: DATA (Non-Resident)  
2022496-2030367

20 2009-06-20 02:42:17 b2f292f1694c9d12f2b100abec8e252d  
039efc71f61ac6816f7d53f0cecabf6a64b8122d  
c10eecef25e4a6d7650e4c239df01192e5c700b24b8bf275768bb8de3d881cae  
Partition1/Root/Photos/Vegas/IMG\_0547.JPG  
DATA: DATA (Non-Resident)  
2030368-2036887

20 2009-05-27 21:09:00 f7960866200a1f52ee74a46ebcd9761e  
f09b4b253fdaa5bdcf8b425111492dlece716488  
3184ac48cc4db4822d2df1ef5539e413473705fa478aal467eb0fcd21ee182c  
Partition1/Root/Photos/Vegas/IMG\_0550.JPG  
DATA: DATA (Non-Resident)  
2036888-2044927

20 2009-05-27 21:09:10 4ac853b049966e9cee7e7cdf9894eb9c  
30e71ec78c93e590083c26222afecfcb377766d6  
5043a207a823a52d556a2532bd92e3c104941793efble7cbc417baa2451b72ab  
Partition1/Root/Photos/Vegas/IMG\_0551.JPG  
DATA: DATA (Non-Resident)  
2044928-2051983

20 2009-04-29 02:54:46 3feacbf5dd9afc05143f12a55f0536f0  
acf18fc7824c46e2107113e28438ala7f3d5364c  
501d7f5876228466260bcf200bed3e71fbf362f9f7f5601cf45ff8b7e3dd792e  
Partition1/Root/Photos/MyPhoto6.JPG  
DATA: DATA (Non-Resident)  
1105344-1107543

20 2009-04-29 02:55:06 22bf64446fcd3a630ab17bf839de6e7d  
6e023a946c407fb59b2b96216f46b6d0e7f4081d  
d317be69a99418cd6c1aa628837db02537b04cd2c0549099e2f5edc7f4361c40  
Partition1/Root/Photos/MyPhoto7.JPG  
DATA: DATA (Non-Resident)  
1107544-1109231

20 2009-04-29 02:55:30 cb4bed7e6405a90b65cd80ccbec04928  
6581e5cc10659704ea5d98b81a7a326ab9640a26  
94f3d3b0877947b05a4e4a6be15f9caa590ff9a9dbc3984b65bf5ea9760758d8  
Partition1/Root/Photos/MyPhoto8.JPG  
DATA: DATA (Non-Resident)  
1109232-1111231

20 2009-04-29 02:56:50 2abc60a295d7e3eaa91cb7ad92efc788  
52de9551e8710d6978e525194b8e9cd3a44ea992  
20141717c1bfbf42901603843fdd360a56ed64af6865fdc61197ec48fc89807b  
Partition1/Root/Photos/MyPhoto9.JPG  
DATA: DATA (Non-Resident)

```

1111232-1118135
20 2021-11-16 09:38:58 Partition1/Root/System Volume
Information
20 2021-11-16 09:38:58 9a9e2941af363372e78db223793602c9
172678454aa1776e9a7e71ecacb3b5a57f388c75
2ac9b80907e81185d3479e340ed6123a4063cf0fd1305cd6b66227cf30a74647
Partition1/Root/System Volume Information/IndexerVolumeGuid
20 2021-11-16 09:39:01 1e7a6c21c279de2ce269b029a0e2c472
c5d14bce2dc6fd037e4ecf41a0b8ff864c0d1baf
ad4f52a33fa3d312a93a946a3c8dd4bc5826046f2e570f1c93b3c97246c6e5ec
Partition1/Root/System Volume Information/tracking.log
DATA: DATA (Non-Resident)
4912-4951
20 2021-11-15 10:46:45 69921f526526f76d9f2ecce1e61a4408
72f60bff40c69e35d3c3ce6e00d72a2b132c28b0
5a88103911c673be8f0b86345b0c0c7a275b6312a7b666f75de78409b3cb2f48
Partition1/Root/System Volume Information/WPSettings.dat
20 2021-11-15 10:50:33 Partition1/Root/Video
$I30: INDEX_ALLOC (Non-Resident)
54384-54391
20 2021-11-15 10:47:43 Partition1/Root/Video/Avi
$I30: INDEX_ALLOC (Non-Resident)
54368-54375
20 2021-11-15 10:48:51
Partition1/Root/Video/Avi/Cops_Season_24_HDTV
$I30: INDEX_ALLOC (Non-Resident)
54376-54383
20 2016-06-05 22:18:26 7f0357f25d88e1369c8dc1acd0aed663
317dd884a8bc77e96e7fd1656e4aed35d077b0da
a48313a5f5756abd792ba5falda6e92f9caf0a7511435e2f5dcfce5250bea41a
Partition1/Root/Video/Avi/Cops_Season_24_HDTV/Cops.S24E01.HDTV.XviD.avi
DATA: DATA (Non-Resident)
3870016-4228031
20 2016-06-05 22:19:24 8dd47bbfb3420f7ff4b0b101e8cad36b
1fd74b806f952314abfecea3fbd56b0560ebb315
72a952dc62b83d078327a25c5e0d81e6027e684238c7b1bcf02c1c29e8f097ef
Partition1/Root/Video/Avi/Cops_Season_24_HDTV/Cops.S24E02.HDTV.XviD.avi
DATA: DATA (Non-Resident)
4228032-4585423
20 2016-06-05 22:19:41 e389377f24ca35cc802aa90d821a246d
3f4c33408ad18287d5f1dca0b474c208748c7002
8622c265f0c0533bd756b0b45fdbf661c23370c093c8a708b14a503238a2ad9f
Partition1/Root/Video/Avi/Cops_Season_24_HDTV/Cops.S24E03.HDTV.XviD.avi
DATA: DATA (Non-Resident)
4585424-4943447
20 2016-06-05 22:12:38 5e828eea4a7d198d5d029eb6a5fd8a97
5f696a6568215a658415bbf736098166253c7bd2
ce10df567443f9c8211655bf9c62071d636dd5106f334efbbf22d57b62e0a256
Partition1/Root/Video/Avi/Cops_Season_24_HDTV/Cops.S24E04.HDTV.XviD.avi
DATA: DATA (Non-Resident)
4943448-5301583

```

20 2016-06-05 22:17:43 409e0f6332db4c12da861cd3cab5ae14  
6d21926f26bd26e3730274b37ad69731219c29f5  
e8b357b3f488e04276a2f1dfd9147e8f1b73e4a5a4ad7854abebble6a83fc379  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E05.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
5301584-5659415

20 2016-06-05 22:18:57 b55ee3db70b62f883db5573a5746e4d1  
08c309ee65b69c1a937f447b9b45e95055ad422e  
e39d39283cd4fbec2a5e4e59dba6751c4b2be36eedfaf0ad4d2b3e904867dd9d  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E06.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
5659416-6017039

20 2016-06-05 22:17:05 1febb45222f9f114e88c533c36f8f29b  
b1656a3eb4766af43e31b46defb3827be551bfde  
42513d7f9738dd06077f8e2636cdb6852aa852bc67316cbbc45b6bec5cff69c9  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E07.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
6701312-7058527

20 2016-06-05 22:16:17 0ecf424d46e619cd1d09bce2dae5b570  
a15b481e4083022254c0ff9aa85f369782a7c87b  
7240d9aed4d0129139f9d817bd1beb140f2c46b226e77570f083387e54a04ebd  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E08.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
7058528-7416287

20 2016-06-05 22:17:14 88b3f03a9e20f9b2310dde6cd0296fca  
b839c39d53c22c5e8a46cda745f0c90ac86ac38d  
2b61dad5b94d79f8b0e202db5dc30f5a581f1093b588a16354701419aaeb6ebb  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E09.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
7416288-7774255

20 2016-06-05 22:19:17 delcf8808dff26c1b4398220a8913dd1  
139ad01952126d3294c49e4f2258168462f4b61d  
3a70dfd2993d0ae572855aa7a20847d58a0e8823fba77e0e136a9a2a92b0bb6e  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E10.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
7774256-8132167

20 2016-06-05 22:16:49 216bdd9f74a00a7a9b4383e2e655ef58  
47bdb9493dc69f0aff6c38536f3100cca3c6c3f3  
ed4d42a3c4162a16da28f21d85a2dfb53b0f07fe005b9012e573717fef70af59  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E11.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
8132168-8489975

20 2016-06-05 22:17:34 51bf22c8ed46f23cd1efde24952d305e  
a090ee7373d093cf91ee3afa42decbbdf5f43d6a  
72d917ebda33cc238falbcada877f7949ff460105e7467d2c314a63fd1224740  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E12.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
8489976-8847887

20 2016-06-05 22:19:31 ac81e8b5472ca54054c8e57b6e69b1b0  
bdb5963313cflcdcbd9d7ae2e66daf8b669000d6  
eae261da6d61b544dc42c8843ab4752496fb4869fcbff869baa9f62ea47b9ee7  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E13.HDTV.XviD.avi  
DATA: DATA (Non-Resident)

8847888-9206559  
20 2016-06-05 22:16:28 8d99cfc73a09a48825a276375bfad763  
735aa03db094173277fb702ef0c7d96bdc8e11c2  
052e121628b631a3154d04a2b30774340fdaf0e4593b9b751187f867b2c433e3  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E14.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
9206560-9565823

20 2016-06-05 22:18:51 6c498108cd539cb1b05c813b8e91893d  
843e634c0def9751870c8bbe5087be478211d62b  
42d916b97a81a2147ef5e03a9e07dab0e6db4d6b148693492644f539ebbf1cdc  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E15.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
9565824-9923519

20 2016-06-05 22:18:10 0e418b50264b2bb748f031e1250de762  
b6a7edd6909b1fff6e5d6e85b6cd3734a8ddff4ef  
9286b40a34a4fae19a24117c179cca4f4493f54341dc66fa2255e49eb209clab  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E16.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
9923520-10281511

20 2016-06-05 22:19:07 65fe333f28d8c5f27d21a2445d95fa91  
f6ed23e660b1f8559e5f7151ee16cd583e3fc353  
344d36ce2ecefeld3676197f247dca485e37be2282a469aa2fb2a219907d737e  
Partition1/Root/Video/Avi/Cops\_Season\_24\_HDTV/Cops.S24E17.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
10281512-10639959

20 2016-06-05 22:18:17 514b0659f98a3c45202f1cc8a125fe61  
1ba85643445ac825a4d4a5281020d6f82b5bc69a  
b99c92603b97699ed7aa10a4e7f21fbd92a4cd8688a4083e33e8a4c54049aaba  
Partition1/Root/Video/Avi/Cops.S24E18.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
2051984-2410095

20 2016-06-05 22:18:12 0e6f2a5dea0e8a1e4dd33ad2c99395cb  
9a0b653b3820ba4dd0d78ae94d0da524ff62567a  
133cccd202e162aa8f52cbf289351dcb3414d78cfb82945ae49233b4d245d907  
Partition1/Root/Video/Avi/Cops.S24E19.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
2410096-2765911

20 2016-06-05 22:18:38 f3704970997f2eb8af3fb9dd2691f7d0  
580ca470463e58d4b29eba6471081910b7b4ebfc  
3544a68251c3b273675eae72431be23a3971057c6c18292bf69f71cd5b42590f  
Partition1/Root/Video/Avi/Cops.S24E20.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
2765912-3124295

20 2016-06-05 22:18:47 ba81e0c6597f2e3898535fb78ffa0ccb  
7f537260ad18099950dcc69964de66ceb45fe176  
3797d035d4b503fal8b05153790ed1371394b7d549589219955d75c77abedbd  
Partition1/Root/Video/Avi/Cops.S24E21.HDTV.XviD.avi  
DATA: DATA (Non-Resident)  
3124296-3481199

20 2016-06-05 22:19:37 f61d04146b1f1e8404b1a16e9adfab5e  
306ebaddaa2d57688f4e5888cf5363da207e3f28  
ad0d94c09fb496f2f2177c0d6de71ac3d8f2188c1631676ed713acd251b3f406  
Partition1/Root/Video/Avi/Cops.S24E22.HDTV.x264.mp4



```

DATA: DATA (Non-Resident)
  3481200-3870015
20          2021-11-15 10:48:56      Partition1/Root/Video/Flv
20          2010-01-05 14:11:42      d2ef7350396693de9389e8b39774b4d7
  31920aa00dc386e8d2e1889f80c7b170560d349c
38a0753248b06cfca4ceeb4bc67198214216bdd2313e0d8cc3ee641471054766
Partition1/Root/Video/Flv/Better_than_me_flv.flv
DATA: DATA (Non-Resident)
  6017040-6033135
20          2021-11-15 10:48:56      Partition1/Root/Video/M4V
20          2012-08-22 07:36:44      968139c8f965b32be629b5eddac23382
  3d4ab462a46e985f61e55d3d293598ae658179e9
d84d38f3792764ab30e3d735da22c5977920c92a0339d46055d5710b40e008bc
Partition1/Root/Video/M4V/general_hospital_fall_2008_promo_(hq)_m4v.m4v
DATA: DATA (Non-Resident)
  6033136-6035127
20          2021-11-15 10:49:34      Partition1/Root/Video/Mov
20          2015-10-11 07:33:14      53bd8bd63f73df2e647b20ac336b5184
  3847624df92163b5857177e06fccfc01f09655c6
4b5af7cael0bd584f7ffcf7c6a690a8df6f12bf4a5d54e83fdceec6d44d6ae8d
Partition1/Root/Video/Mov/FILE0031.MOV
DATA: DATA (Non-Resident)
  10639960-13303647
20          2015-10-11 07:48:14      4d0737f26d565e7ade41cleeff0e7cae
  9a11b89381fc546c638eb8cbdfb1a1f4b892348e
0afc907c0ae3aa8f6ee9a35ec2f863650872a30f9dcc3cb72391f856b7124370
Partition1/Root/Video/Mov/FILE0032.MOV
DATA: DATA (Non-Resident)
  13303648-15967559
20          2021-11-15 10:50:25      Partition1/Root/Video/MP4
20          2010-11-30 10:58:19      3e3661d0dc6f16a5d416791614623e9e
  3d41e5063b1c5b1a4f659c669a2016873578c3c2
553fcee0ff4df6eefc45024c334ff2ddda887031c2d2ce75d64f8a0cc28365f1
Partition1/Root/Video/MP4/mp4
Haiti_can_succeed,_but_not_without_your_help_(Former_US_president_Bill_Clinton).mp4
DATA: DATA (Non-Resident)
  15967560-16143863
20          2015-09-18 17:52:23      f9d18db99b4d4f3d5d8f7ecda07a283a
  3f30923a876e075e0c5735d095fafc71798a5a8f
d055ab546e6c24517aeaadc8217b3a56443baf902230c7a41235f6402770e4c0
Partition1/Root/Video/MP4/VID_20150918_215223.mp4
DATA: DATA (Non-Resident)
  16143864-16348887
20          2015-09-18 18:00:20      b970ad6b6fc339a639a747d43279fc24
  226dd51746a2765ebfeb7e58a61d5f43ee8cfcf3
0e2d63dc86db96e93cb84e61724699bce08aalf68ca17216e98355800ead5038
Partition1/Root/Video/MP4/VID_20150918_220020.mp4
DATA: DATA (Non-Resident)
  16348888-16685327
20          2015-09-20 08:31:20      050863ea63873886856c1850f89b2872
  15e1a4f4ed00ae657cc4892959e2d161d011b84f
64e86ce37f11c639c102721be53d58f6f42302056fc183a701c7cbd6696a0f38
Partition1/Root/Video/MP4/VID_20150920_123120.mp4

```

```

DATA: DATA (Non-Resident)
    16685328-16938367
20                2021-11-15 10:50:29      Partition1/Root/Video/MPEG
20                2016-08-06 11:50:22      8661e7edc04aa49accced6da2520decc
    0b7c023cd7f19445e78f11a5d3d4c2058196e307
63a8045b7ee6345adec7079e0e18fe89656e0cb188eb34712614e9b539f89740
Partition1/Root/Video/MPEG/Mpeg_Video.mpeg
DATA: DATA (Non-Resident)
    6035128-6119063
20                2021-11-15 10:50:33      Partition1/Root/Video/MTS
20                2015-08-05 03:44:42      28264a21f4babe4c26fd9422ecce8066
    ddd8c7b7717e0c0374d50af851a499b9ec11e428
fdaf9826c0bb27005d60b611857f6ac4d81191cfcdd63519343f7d4192208491
Partition1/Root/Video/MTS/00026.MTS
DATA: DATA (Non-Resident)
    16938368-17128831
20                2013-03-20 07:16:48      c8813d64f8e33e4e41c773d188ce6f62
    cd6dae3c9a31db7f02d18bfa8fa493d85b64e64b
1cfbb5d3d93c7725f06a388d93490e112427c640db705dfe90036c98c6db4820
Partition1/Root/Video/MTS/00140.MTS
DATA: DATA (Non-Resident)
    6119064-6132695
20                2013-03-20 07:16:20      40566a6585ba0440175eed119a32a32a
    95776ef4d52ea51062c472ce744delef075bdf2f
34cf55b950cbce275ddclecad2e9fc0821e4b664d23eeb3270059b3e6e8d0c4e
Partition1/Root/Video/MTS/00168.MTS
DATA: DATA (Non-Resident)
    6132696-6148823
20                2013-03-20 07:15:22      90b17b9d8b04d14b2a72aala7ea2c6c8
    19ddc6147e3f8d9c628c83cf33525cc859423c00
fbf55ea6c3b86c666c79caaf5c1386eebede4f02b8b70c7c91610effaf874ddc
Partition1/Root/Video/MTS/00346.MTS
DATA: DATA (Non-Resident)
    17128832-17145343
20                2016-06-05 09:36:07      d6b0ce497e569371b94e19fea48355cd
    37fbac48c80859f47024f2382d9880be633477b
b08522bb8e9d63c86c290a8c7032f3097fc78db704eald54eaaa75934c29de46
Partition1/Root/Video/The.Lincoln.Lawyer.2011.1080p.BluRay.x264.DTS-FGT.mkv
DATA: DATA (Non-Resident)
    17145344-33576271
20                2012-11-03 10:10:07      9565cf6684e2858bda872890a32cc671
    da8c56c8b989ed9c2b42057ac657257520cfe661
beedd667813a9279426cfa769cb39f53156080fe78e73803dcb3206978985b04
Partition1/Root/Blue Skies (1946) 104 min.Fred Astaire.Bing Crosby.Irving
Berlin.Musical.avi
DATA: DATA (Non-Resident)
    33576272-36340295
20                2013-06-26 07:58:08      12ab314eb73a4a938bed3d6550da0ff2
    22b0141246f4f5c7cf20171645c0f8de596cb35a
eada5fecc16cb98c28c54b080319ff79eb20b62a313ed4b6ba5c254a4a3ede7e
Partition1/Root/Mac_mini_Intel-based_Mid2007_UserGuide.pdf
DATA: DATA (Non-Resident)
    6148824-6150575

```

```
20          2005-08-06 06:04:54      59262f761288b9fd5f1306a80aa25ddb
          95f732edc568a3563de4f2fa4410b4b488a9778e
d1205b011a0139b8a9c8fcc15ca227a72c7ef575828ff99d747021ebbab04fca
Partition1/Root/P1000075.JPG
DATA: DATA (Non-Resident)
      36340296-36344487

20          2005-08-06 06:06:04      33e7439162b60fc39c701fe1d40cdde7
          fef0d28922959512f5766b22867100583a83ea27
7645c7b66336c420372c6f4e4b8f3c1d9cf14cff36d6599b54587b8f8a8827e8
Partition1/Root/P1000076.JPG
DATA: DATA (Non-Resident)
      36344488-36348455

20          2013-12-12 08:31:39      bf2a0fb0328c20ab65a1d9485d9748c4
          e3c3e84fc05f16d09edce676ff52a24812f15a1f
1fb743fa827fe7569bb93232555389aa596398997b7e4946fba2f9141f78b26c
Partition1/Root/TestVHDGPT.vhd
DATA: DATA (Non-Resident)
      36348456-38445615
```

END Date / Time of Collection: 2022-07-05 04:02:59

-----

-----

## IV Text/hexadecimal Editor

Any object visible to **R-Studio** can be viewed and edited in the **Text/hexadecimal editor**. It is also able to parse the data and represent data according to various data patterns. You may also create your own patterns to parse data.

**Note:** Data alteration is available on the **Technician/T80+** and **Corporate** versions only.

You may turn [numerical indexes](#) for objects to distinguish them better.

- [Viewing and Editing Objects](#)
- [Navigating through an Object](#)
- [Data Copy](#)
- [Files and Sectors](#)
- [Creating Custom Patterns](#)
- [Pattern Example I](#)
- [Pattern Example II](#)

[R-Studio Features](#)

[Contact Information and Technical Support](#)

[Data Recovery Using R-Studio](#)

[Basic File Recovery](#)

[Advanced Data Recovery](#)

[Mass File Recovery](#)

[Volume Sets and RAIDs](#)

[Data Recovery over Network](#)  
[Technical Information and Troubleshooting](#)  
[R-Studio Emergency](#)  
[R-Studio Agent Emergency](#)

## 4.1 Viewing and Editing Objects

**YOU MUST BE ABSOLUTELY SURE OF WHAT AND WHERE YOU ARE WRITING!  
Or you may completely lose all your data.**

Before you can physically write anything on a drive, you need to enable writing.

**To enable writing,**

- 1 In the **R-Studio** main panel, select the **Tools** menu, then **Settings**, and select **Enable Write** on the [Settings](#) dialog box.
- > **The Editable:** status will change to **Yes** from **Read Only**.  
Now the object can be edited.

### Locking and unlocking objects

It is possible to manually lock an object being edited in **Text/Hexadecimal Editor**.

When an object is locked, **Text/Hexadecimal Editor** has an exclusive access to it, and no other programs or Windows can make any changes on it. **Text/Hexadecimal Editor** itself always locks the object itself before writing anything on the drive and then unlocks it. But sometimes locking/unlocking may take quite a lot of time, up to several seconds. That is why sometimes it is a good practice to lock an object while editing it in **Text/Hexadecimal Editor**. This can be done by selecting **Lock** on the **Tools** menu.

When considering locking an object in **Text/Hexadecimal Editor**, keep in mind the following:

- Starting from Windows 7, it is impossible to change data if it resides on a [logical disk](#) without locking the drive. If the data is on a place outside of any logical disk (on an unmounted [partition](#) or empty space), such lock is not necessary. Windows Vista, XP, or below do not have such restrictions.
- The **Lock** command tries to lock all logical disks on which the object being edited is placed. For a drive, those are all its logical disks, for a file that is a logical disk where it resides. And if a RAID is created from logical disks and a file is opened on that RAID, **Text/Hexadecimal Editor** blocks all logical disks on which the file resides.

Moreover:

- If a logical disk is opened in **Text/Hexadecimal Editor**, the **Lock** command locks the drive if there is no files opened by some other programs.
- If a drive is opened in **Text/Hexadecimal Editor**, the **Lock** command locks the drive if all its logical disks can be locked. That may cause problems is one of the logical disks is a system one.

**To view/edit an object,**

- 1 **Right-click the object and select View/Edit on the shortcut menu**
  - ☐ **Other ways to view/edit the object**
    - Select the object and select **View/Edit** on the **File** menu
    - or
    - Select the object and press the **Ctrl+E** keys

> A Text/hexadecimal Editor panel will appear

R-Studio Text/hexadecimal editor

The screenshot shows the R-Studio Text/hexadecimal editor interface. The main window displays a hex editor view of a sector (Sector 6010844) with columns for Offset, Binary data, and ANSI. The left sidebar contains a Templates panel with a selected 'Boot sector NTFS' template, a Properties panel showing details for the selected sector, and a Find Results panel showing search results for '0x1af54d200'. The status bar at the bottom indicates 'Ready' and provides details about the current sector: 'Size 7340032000 Offset 0x0b76fb800 = 3077552128 Sector 6010844 Editable: Binary data: Unaltered'.

Data Parsed According to the Selected Pattern Object Properties

The image shows two panels displaying parsed data for a selected pattern object. The left panel is the 'Templates' window, showing the 'Boot sector NTFS' template selected, with a table of properties and values. The right panel is the 'Properties' window, showing a table of properties and values for the selected sector.

Property	Value
Name	F: -> SAMSUNG SP0411N T...
Size	7340032000
Sector size	512
Offset	0x0b76fb800
Sector	6010844
Position in sector	0
Parent	SAMSUNG SP0411N TW100-11

Property	Value
Name	F: -> SAMSUNG SP0411N TW100-11: S01J20XC75851
Size	7340032000
Sector size	512
Offset	0x0b76fb800
Sector	6010844
Position in sector	328
Parent	SAMSUNG SP0411N TW100-11
Size	40060403712
Offset	0x0b77fb948
Sector	6012892

### Object Sector Mapping

Sector	Parent Sector
6010842	6012890
6010843	6012891
6010844	6012892
6010845	6012893
6010846	6012894
6010847	6012895

### Data Shown as Various Digits

Name	Value
8 bit binary	00110000
ANSI character	0
OEM character	0
<b>Little Endian</b>	
UTF8 character	0
UTF16 character	(E)
8 bit hexadecimal number	0x30
8 bit octal number	060
8 bit unsigned decimal num...	48
8 bit signed decimal num...	48
16 bit hexadecimal num...	0x3230
16 bit octal number	031060
16 bit unsigned decimal ...	12848
16 bit signed decimal num...	12848
32 bit hexadecimal num...	0x62773230
32 bit octal number	014235631060
32 bit unsigned decimal ...	1651978800
32 bit signed decimal num...	1651978800
64 bit hexadecimal num...	0x28062773230
64 bit octal number	050014235631060
64 bit unsigned decimal ...	2750431048240
64 bit signed decimal num...	2750431048240
Windows time	1601-01-04 04:...
DOS time	2029-03-23 06:1...
Unix time	2022-05-08 03:0...
<b>Big Endian</b>	
UTF8 character	0
UTF16 character	(E)
8 bit hexadecimal number	0x30
8 bit octal number	060
8 bit unsigned decimal num...	48
8 bit signed decimal num...	48
16 bit hexadecimal num...	0x3032
16 bit octal number	050062
16 bit unsigned decimal ...	12338
16 bit signed decimal num...	12338
32 bit hexadecimal num...	0x30327762
32 bit octal number	06014473542
32 bit unsigned decimal ...	808613730
32 bit signed decimal num...	808613730
64 bit hexadecimal num...	0x30327762800...
64 bit octal number	020062356610...
64 bit unsigned decimal ...	3472969527594...
64 bit signed decimal num...	3472969527594...
Windows time	12606-05-28 15:...
DOS time	2004-01-18 14:5...

### Binary view

Offset	Binary data
Sector 6010844 (Parent: SAMSUNG SP0411N TW100-11 Record: 6012892)	
B76FB900:	32 77 62 80 02 00 00 - AF 8C 68 F2 C2 30 E0 50
B76FB910:	00 B0 F9 CB 1D 61 FD EB - 2E 71 68 C5 D9 5B 2B 37
B76FB920:	A2 51 EE 34 39 B7 35 42 - 71 B4 82 92 49 B8 D8 6D
B76FB930:	B6 15 E8 4A 11 11 54 84 - 09 E8 2F 1A D5 A4 E5 11
B76FB940:	10 A4 51 50 77 16 21 0C - 22 71 F9 84 46 11 D0 1B
B76FB950:	88 63 C5 83 80 09 33 09 - CB D3 B8 4E F6 EC FD 2E
B76FB960:	8A 36 6E 66 77 30 CE A3 - 07 5A FE 61 67 3C ED 6E
B76FB970:	DD 2F F5 AA 3F 9B FD - CF FF 9B 3A 1F F8 B5 39
B76FB980:	FE EF F7 6F 30 88 A6 E3 - 72 C7 1B 44 90 A6 48 1D
B76FB990:	B2 1F 2E C9 E0 79 40 34 - 10 95 0D 01 28 8A 59 AE
B76FB9A0:	9C 3E 89 01 6B DE E9 86 - AC 43 0B 48 5A 31 5A 97
B76FB9B0:	7C EF A8 2F B5 CE 15 7E - E7 E4 FF AF E1 76 05 36
B76FB9C0:	1F 3E 92 47 2B 0B 81 8B - FF FB 94 00 CD 80 02 8D
B76FB9D0:	26 4C C9 E9 32 50 58 44 - D9 BD 3D 28 4B 0A 50 7B
B76FB9E0:	31 87 A5 09 6C 8F 66 - 74 F4 A1 21 07 02 76 49
B76FB9F0:	D1 86 DD 24 EA 74 94 45 - CA 5A ED 57 8B D6 C5 29
B76FB900:	94 DC FF A4 06 24 82 46 - 43 E5 D9 74 11 14 03 82
B76FB910:	49 98 68 1C 44 53 5A C2 - 48 7D 01 42 D7 BD D5 92
B76FB920:	B1 B3 F5 C9 EB 4B 18 AF - 56 AE 20 75 6A A5 07 21
B76FB930:	6B A9 4C EF 07 73 5D C1 - B3 97 2F FD 64 3A 6C 58
B76FB940:	A2 09 93 4A 43 4F 02 10 - 8B 96 DA C7 F4 E7 77 A4
B76FB950:	56 D2 89 EA 1E C5 28 A6 - E4 FF A0 05 C1 EE 82 90
B76FB960:	9E 3E 3C C5 A7 0B 00 C4 - E4 23 06 44 81 90 B3 04
B76FB970:	3C 38 D0 A0 94 56 83 92 - 90 15 B2 28 90 93 65 A7
B76FB980:	83 35 15 95 9F 4F 98 59 - 7C B1 E8 80 3A 8D 8F 41
B76FB990:	D4 9F 82 AD 16 A0 2A 39 - 76 A4 A2 D5 15 71 69 3D
B76FB9A0:	AF 60 A9 87 B9 AF 5D CC - CB B5 70 2A D7 C9 24 6D
B76FB9B0:	A0 B8 3D D2 D2 1B 8F 8B - D8 64 F5 81 63 76 2B 8F
B76FB9C0:	A5 82 69 93 87 32 44 78 - C0 F5 6F 2D 81 C0 0F AA
B76FB9D0:	32 71 34 29 A2 8C E9 8C - 72 1E EB F3 4B 3D EC B9
B76FB9E0:	E9 76 92 88 B5 3B 76 D4 - D3 DE A8 18 92 04 D0 70
B76FB9F0:	8B 5C A2 8C 1E 89 9C 91 - 29 E0 4E B6 11 27 1C 4E





You may set which panels and bars to enable/disable.

▣ **To enable/disable:**

ANSI data	Select/Unselect <b>ANSI</b> on the <b>View</b> menu
OEM data	Select/Unselect <b>OEMr</b> on the <b>View</b> menu
UNICODE data	Select/Unselect <b>UNICODE</b> on the <b>View</b> menu
UNICODE+ data	Select/Unselect <b>UNICODE+</b> on the <b>View</b> menu
<b>Toolbar</b>	Select/Unselect <b>Toolbar</b> on the <b>View</b> menu
<b>Properties View</b>	Select/Unselect <b>Properties View</b> on the <b>View</b> menu
<b>Sectors View</b>	Select/Unselect <b>Sectors View</b> on the <b>View</b> menu
<b>Data Interpreter View</b>	Select/Unselect <b>Data Interpreter View</b> on the <b>View</b> menu
<b>Template View</b>	Select/Unselect <b>Template View</b> on the <b>View</b> menu
<b>Bookmarks View</b>	Select/Unselect <b>Bookmarks View</b> on the <b>View</b> menu
<b>Find Results View</b>	Select/Unselect <b>Find Results View</b> on the <b>View</b> menu

## 2 View the information and make necessary changes

Select **Save Changes** on the **Tools** menu if you want to save changes.

▣ **Other ways to save changes**

- Select **Save Changes** on the **File** menu
- or
- Press the **Ctrl+S** keys

### Viewing

There are up to four tabs showing the data in different representations. Actual number of tabs depends on the object and property being viewed/edited.

Std	Exact attribute data. If the attribute is compressed, <b>R-Studio</b> decompresses it prior to showing.
Unlimited	Exact attribute data + <a href="#">free space</a> of last cluster. If the attribute is compressed, <b>R-Studio</b> decompresses it prior to showing.
Direct	Actual data written on the drive. If the attribute is not compressed, it coincides with the Std representation.
Allocation	Resident part of the attribute.

You may view data in 4 various code pages: ANSI/OEM/UNICODE/UNICODE+ by switching on/off the respective code pages in the **Code pages** buttons or select the appropriate code pages on the **View** menu.

You may see which file is written on a particular sector. See [Files and Sectors](#) for details.

### Patterns or Templates

You may select a pattern according to which the data will be parsed and shown in the parsed data pane. The Data Interpreter shows the data selected in the Template pane in various representations.

You may find the next or previous data that matches the pattern signature on the drive. Right-click the right pane of the editor and select either **Find Template Signature Next** or **Find Template Signature Previous** on the shortcut menu. You may also select these items on the **Edit** menu.

You may also [create](#) your own patterns to parse data from various objects.



**Navigating**


**Text/Hexadecimal Editor** gives you various ways to navigate into an object. See the [Navigating through an Object](#) for more details.

**Data Copy**

**Text/Hexadecimal Editor** gives you various ways to copy selected data navigate in an object. See the [Data Copy](#) for more details.

**Filling an area with a pattern**

To fill an area with a pattern, select **Fill** on the **Edit** menu, and specify the pattern and area on the Fill dialog box.

**Fill dialog box****Fill options**

Fill pattern	
HEX	Field for the pattern to fill the area in the hexadecimal representation
ANSI	Field for the pattern to fill the area in the ANSI encoding
OEM	Field for the pattern to fill the area in the OEM encoding
UNICODE	Field for the pattern to fill the area in the UNICODE encoding
Fill range	
From (hex)	Field for the start position of the area to fill with the pattern
To (hex)	Field for the end position of the area to fill with the pattern

**3 Click the Save Changes button to save the changes****Other ways to save the changes made**

- Select **Save Changes** on the **Edit** menu

or

- Press the **F2** key

**> Viewer/Editor will save the changes on the object**

**YOU MUST BE ABSOLUTELY SURE OF WHAT AND WHERE YOU ARE WRITING!**

**Or you may completely lose all your data.**

**Selecting and saving an area in the Viewer/Editor**

You may select an area in the Viewer/Editor panel and save it as a file.

**To select and save an area in the Viewer/Editor panel,**

- 1 Right-click the beginning of the selection and select Select From on the shortcut menu**
- 2 Right-click the end of the selection and select Select To on the shortcut menu**

**Other ways to select an area**


- Select **Select...** on the **Tools** menu and specify an area to select on the Select dialog box,

or

- Click the start point of the area and drag the mouse cursor to its end.

If you need to select an entire object, select **Select All** on the **Tools** menu or click the **Ctrl+A** key

Select **dialog box**




- 3 Select an appropriate item in the **Tools** menu to save the data in a required format and specify its file name

Select:


<b>Save to Binary File...</b>	to save the data in the binary format (default extension is <code>.bin</code> )
<b>Save to Hexadecimal File</b>	to save the data in the binary format (default extension is <code>.hex</code> )

on the **Tools** menu.

If you select an existing file, **R-Studio** will ask you if you want to append or overwrite the file.



If a remote computer is connected for [Data Recovery over Network](#), the Save as... dialog box will appear when you select a place to save the data. You may save it to the local or remote computer.



- > **Viewer/Editor** will save the data in the file


### **Loading data from an external file**

You may load a data from a file and overwrite an area of the object opened in the Viewer/Editor panel.

**To load binary data from a file and overwrite an area of the object opened in the Viewer/Editor panel,**

- 1 Select an area to overwrite and select **Load from File...** on the **Tools** menu

If a remote computer is connected for [Data Recovery over Network](#), the Open as Binary File dialog box will appear when you select a place to open the data file from. You may open it from the local or remote computer.



- 2 Select the necessary file and load the data.

- > The area in the **Viewer/Editor** will be overwritten with the new data.

## 4.2 Navigating through an Object

### **Navigating**

You may quickly move to a particular part of the object. To move to a particular part of the object being viewed/edited, enter the required offset in the **Go to Offset** field between the buttons.


Type an offset to which you want to go. You may select between bytes and sectors. See the [Data Formats and Multipliers](#) topic for more details on data formats.

If a file is opened in **Text/Hexadecimal Editor**, you may select data representation for that file.

Type a sector to go to Sectors DATA: DATA (NR)

You may also use the Go To Offset dialog box to go to a specified place in the object. Click the Offset field on the **Status** bar. You may also use this dialog box to copy the offset.

### Go To Offset dialog box




### Go To Offset options

From:	Jump/offset direction. For example, if you need to find the offset from the object end for a selected byte, switch to the End (backward) option.
HEX/DEC	Switch between the hexadecimal and decimal data representation.
Range	Range of values that can be entered.
dec/hex:	Alternative data representation.
Offset:	Flat data offset (without separation between the sector and offset in the sector).
Sector/offset	Data offset represented as a sector and offset in the sector.
Go!/OK buttons	The Go! button moves the cursor to the specified positions, but the Go To Offset dialog box remains open. The OK button closes the dialog box after moving the cursor.

## Searching

To search for a particular string, click the **Find**, **Find Next**, or **Find Previous** buttons or the same items on the **Edit** menu, and specify the string on the Search dialog box.

### Search dialog box



### ▣ Search options

Not Equal	Search for the place which content is not equal to the string. For example, the first byte not equal to 00 or FF.
<a href="#">Search for</a>	
HEX	Field for the string to search for in the hexadecimal representation
ANSI	Field for the string to search for in the ANSI encoding
OEM	Field for the string to search for in the OEM encoding
UNICODE	Field for the string to search for in the UNICODE encoding
Match case	Select this check box to make the search case-sensitive
<a href="#">Search area</a>	
From current position	Select this check box to start search from the current position
From start position	Select this check box to start search from the beginning of the object
From Address	Select this check box and specify the range in which the search is to be carried out
<a href="#">Search position</a>	
Exhaustive search	Select this check box to search the entire object
Search at offset	Select this check box and specify the sector offset from which the search will start
Reverse	Select this check box to start the search in the reverse direction
Find all	Select this check box to search for all instances of the string to search. Search results will be shown in the Find Results pane.

**Text/Hexadecimal Editor** will show the search progress.

Search results are shown in the Find Results pane. You may easily move to the required found item by clicking the item.

### ▣ Features of the Not Equal option

Suppose we have an object which first 3 consecutive sectors start with:

```
Sector1  FILEAAAAA.....
Sector2  FILEBBBBB.....
Sector3  NOTAFILE.....
```

And the search string is Not Equal FILE.

If the Exhaustive search option is selected, the **Text/Hexadecimal Editor** will stop at the first A character in Sector1.

If the Search at offset=0 option is selected, the **Text/Hexadecimal Editor** will stop at the N character in Sector3.

## Bookmarking


You may create bookmarks to easily move to those places. Right-click the cursor on the place you want to bookmark and select **Toggle Bookmark** on the shortcut menu. The list of bookmarks appears in the Bookmark pane. You may easily move to the required bookmark by clicking it in the list.

You may control bookmarks on the **Edit** menu.

### 4.3 Data Copy

Text/hexadecimal Editor gives you various ways to copy selected data navigate in an object.

#### Data selected in Text/hexadecimal Editor



Depending on what column you have control-clicked, the following commands are available in the shortcut menu:

<p>When right-clicking any column Copy Editor Display</p>	<p><b>Data pasted into a text editor</b></p>
<p>When right-clicking any column Copy as File Signature</p>	<p><b>Data pasted into a text editor</b></p>
<p>When right-clicking the Binary data column Copy as "Binary data"</p>	<p><b>Data pasted into a text editor</b></p>
<p>When right-clicking the ANSI column Copy as "ANSI"</p>	<p><b>Data pasted into a text editor</b></p>
<p>When right-clicking the UNICODE column Copy as "UNICODE"</p>	<p><b>Data pasted into a text editor</b></p>

### 4.4 Files and Sectors

You may see which file is written on a particular sector. To do so:

- 1 Enumerate files on a logical disk in the Drives panel.
  - 2 Go to the tab of that logical disk and select Show Files in HexEditor on the Files menu.
  - 3 Return to the Drives panel and select View/Edit on the shortcut menu.
- > R-Studio will show a file that belongs to a particular section.

### File in a sector

Offset	Binary data
278113E0:	4E 1A 0F 9A 30 DB BB 68 - 72 69 0B 8D 63 48 7C 35 N..8
278113F0:	76 A3 C1 EF AF D2 AD 38 - D4 5A 32 59 90 E0 E6 53 veA1

Sector 1294474 (Parent: WDC WD75A4< File that belongs to this sector

ID: 131399681 Root/Files to wipe/test2.arc

27811400:	CE 0F AD EE 22 B1 09 63 - 31 CF AB 38 B0 60 F9 28 f..1
27811410:	DE BD BC 6F 6D E6 A4 93 - 9D 8E F0 D0 39 24 B4 6B D44c
27811420:	13 9F C3 06 4A AC 85 F4 - FD 73 FD CD 05 2F 46 37 .YA.
27811430:	FC 8D EC B1 FC 0E 15 DF - F9 CD 92 31 F0 AB 45 A9 u.i#
27811440:	9C 74 78 48 8C 79 08 98 - 68 0E C1 03 9C CA 91 34 qe2H
27811450:	01 0F 69 F0 3A D1 72 9E - B7 D2 DA 97 66 8A 9E 73 ..i8
27811460:	5E FD CF 4F EA 14 63 6C - F2 2F EF 67 AB 6E 36 16 ^yIO
27811470:	B5 28 39 80 72 2B FD A5 - 25 32 07 12 27 1B E7 71 u(9.
27811480:	D7 4B 04 45 7C 6C 62 B5 - B0 10 B0 38 C3 02 DC EE *K.E
27811490:	18 79 50 14 06 E7 CE A2 - B5 20 88 47 06 B8 88 70 .yP.
278114A0:	FE BE 90 5D 74 44 F3 96 - 84 90 CC A0 B7 86 AE 63 bK..
278114B0:	03 64 79 09 AA 42 A9 17 - 4B 59 22 1B 42 71 8F 8E .dy.
278114C0:	C0 39 B8 38 D6 9E 9D 92 - 6D BE C6 74 FC 6C BE 58 A9,8
278114D0:	98 58 C4 39 08 8C 9B 16 - 3E 9E D8 E5 55 A1 CA AF .XAg
278114E0:	B3 48 82 72 71 08 A2 C2 - 57 FB D8 64 C6 88 56 FE .H.T
278114F0:	36 0A 68 1C CE B9 52 06 - A9 65 99 7E F3 20 DD 48 6.h.

## 4.5 Creating Custom Patterns

You may create your own patterns yourself.

### [An example of a commented pattern parsing an AVI file.](#)

The syntax of pattern description is similar to that of the XML language. The folder where the files should be placed is specified on the Main tab of the [Settings](#) dialog box.

#### Pattern structure

##### Pattern header

Each pattern starts with a standard header

```
<?xml version="1.0" encoding="utf-8"?>
```

##### Section template

Each pattern starts with a section giving to the pattern a name that will be shown in the parsed data pane.

##### Attributes:

name	Specifies the pattern name shown in the parsed data pane
------	--

##### Example:

```
<template name="AVI File LIST">
.....
</template>
```

##### Section signature

##### Attributes:

align <positive integer>	Specifies if the data structure address is aligned (i.g., by a sector: 512)
--------------------------	---

This section contains elements `field` with hex-codes of the signature. The attribute `offset` specifies their offset from the start of the record. Field length is equal to the number of hex-codes.

##### Example:

```
<signature align="1">
  <field offset="0">46 49</field>
  <field offset="2">4c 45</field>
</signature>
```

##### Section section

Such sections contain all expressions and operations needed for the pattern to parse the data. A section name is shown in the parsed data pane. In fact, sections are virtual objects used to group logically connected `fields`. Sections can be nested.

The main section is not shown in the parsed data pane.

Section contain elements `field` which are actual data objects. `field` names are shown in the parsed data pane with their values.

#### Attributes:

name	Specifies the pattern name shown in the parsed data pane
------	--

#### Example:

```
<section name="JUNK">
  ....
</section>
```

#### List of All Objects in Patterns

#### Data types (in `field`)

- integer

##### Sub-types:

```
int8
int16
int32
int64
uint8
uint16
uint32
uint64
uintX
```

##### Attributes:

endian: (be   le   system)	Optional. Default: <code>system</code> .
base: (decimal   hex   octal)	Optional. Specifies data representation. Default: <code>decimal</code> .
as-offset: <expression>	Optional. Specifies that this field is an offset and its value should be evaluated using the expression. A special variable <code>this</code> returns the value of this field.
purpose: (offset   rsector   sector   cluster   rcluster)	Optional. Specifies the type of the <code>as-offset</code> expression result . If this attribute is present, the attribute is necessary if the offset value should differ from the value of this field (variable <code>this</code> ). <code>rsector</code> and <code>rcluster</code> are offsets relative to the absolute position of the pattern beginning.
assigned- template: <TemplateName>	Specifies the pattern name linked with this field. Ignored if the <code>as-offset</code> or <code>purpose</code> attributes are not specified.
var: <Name>	Optional. Specifies the name under which the value of this field can be accessed in expressions.

- binary

##### Attributes:

display-encoding: (hex   binary)	Optional. Default: hex.
size: <bytes>	Mandatory.

- char

## Attributes:

size: <bytes>	Mandatory.
codepage: (ansi   oem   utf8   utf16)	Optional. Specifies which codepage is used. Default: ansi.

- filetime

Shows time in the Win32 format (64 bits)

- unixtime

Shows time in the Unix format (seconds from 01/01/1970)

- filetime

Shows time in the DOS format (date: hiword, time: loword)

- bits

## Attributes:

size: <bytes>	Mandatory.
pos: <comma separated list of bit positions>	Mandatory. Specifies bit positions in a data block.

## Commands

- goto

Specifies a jump to a specified offset (either absolute or relative one)

## Attributes:

address: <expression>	Specifies an absolute address to jump to.
offset: <expression>	Specifies a relative offset to jump by.

One and only one of the attributes should always be specified.

- if

Evaluates a condition specified in the `test` attribute and, if the condition is true, reads fields specified in this tag.

## Attribute:

test: <expression>	Sets a condition to test against.
--------------------	-----------------------------------

- repeat



Reads the fields specified in the tag until the exit condition is equal to 0 or specified times

Attributes:

count: <expression>	<expression> is evaluated one time upon entering the block. Internal elements are read the specified number of times.
test: <expression>	<expression> is evaluated upon entering the block. Similar to the C++ construction <code>while(...) {}</code> .
test: <expression>	<expression> is evaluated upon exiting the block. Similar to the C++ construction <code>do {} while(...)</code> .

- `setvar`

Sets the value of an internal variable. As an example, this command is convenient to store the current offset. The value of the current offset is stored in a predefined variable `offset`.

Attributes:

var: <string>	Specifies the name of the variable.
expr: <expression>	Specifies an expression which result will be assigned to the variable.

## Expressions

Expressions in the patterns are arithmetic expressions which syntax is similar to that of the C language, including operation preceding.

The following operations are supported:

+ - \* / & | > < <= >= != == || &&

## Predefined variables

- `offset`

An offset in bytes from the pattern beginning data is currently read at.

- `start_position`

An absolute position of the pattern beginning. `offset + start_position = absolute offset`.

- `this`

This variable exists only within the context of the `ass-offset` expression evaluation and is the current value of the data field for which that expression is specified

## 4.6 Pattern Example I

Below is an example of a commented pattern parsing an AVI file.

```
<?xml version="1.0" encoding="utf-8"?>
<!-- A pattern section. The pattern name is AVI File. -->
<template name="AVI File">
  <!-- A template signature section. Alignment is 1. -->
  <signature align="1">
    <!-- A 4-byte signature at offset 0x00. -->
    <field offset="0x00">52 49 46 46</field> <!-- ANSI: RIFF -->
    <!-- A 4-byte signature at offset 0x08. -->
    <field offset="0x08">41 56 49 20</field> <!-- ANSI: LIST -->
```

```
</signature>
```

<!-- A data section. Its name is `AVI File`. This is the main data section. It is not shown in the parsing tree as a section (its name is ignored). -->

```
<section name="AVI File">
```

<!-- The first 4 bytes are read and shown as an ANSI string. -->

```
<field type="char" size="4" name="Signature: RIFF" var="signature"/>
```

<!-- The current position is moved to the beginning of the file. -->

```
<goto offset="-4"/>
```

<!-- The first 4 bytes in the file are read and shown as an unsigned integer. The internal variable `signature` gets the value of the field. -->

```
<field type="uint32" base="hex" name="Signature RIFF as unsigned integer in hex format" var="signature"/>
```

<!-- A test against the condition (`signature == RIFF`) -->

```
<if test="signature == 0x46464952"> <!-- ANSI: RIFF -->
```

<!-- The next 4 bytes are read and shown as an unsigned integer. The internal variable `dataSize` gets the value of the field. -->

```
<field type="uint32" name="Size of the data in file" var="dataSize"/>
```

<!-- A new internal variable `endOfFile` is created and the `expr` field evaluates its value. -->

```
<setvar var="endOfFile" expr="offset + dataSize - 8"/>
```

<!-- The next 4 bytes is read and shown as an ANSI string. -->

```
<field type="char" size="4" name="File type"/>
```

<!-- A new section named `DATA` is created -->

```
<section name="DATA">
```

<!-- A new internal variable `chunksOffset` is created, the `expr` field evaluating its value. This variable gets the absolute value of template offset. -->

```
<setvar var="chunksOffset" expr="start_position"/>
```

<!-- A loop is created. Its condition is set in the test field (while the `endOfFile` variable is greater than the current position.) -->

```
<repeat test="endOfFile > offset">
```

<!-- 4 bytes are read and shown as an ANSI string. -->

```
<field type="char" size="4" name="Signature"/>
```

<!-- The current position is moved backwards by 4 bytes. -->

```
<goto offset="-4"/>
```

<!-- The same 4 bytes are read and shown as an unsigned integer. The internal variable `signature` gets this value. -->

```
<field type="uint32" name="Signature as unsigned integer" var="signature"/>
```

```

<!-- A test against the condition (signature == LIST)-->
<if test="signature == 1414744396"><!-- ANSI: LIST -->
  <!-- The section is shown. Its name is LIST -->
  <section name="LIST">
    <!-- The current position is moved backward by 4 bytes. -->
    <goto offset="-4"/>
    <!-- The 4 bytes are read and shown as an unsigned hexadecimal integer. This field has the
attributes offset and assigned-template. If the user double-clicks this field, the AVI File LIST pattern
will be invoked and the current pattern position will be moved to the address specified in as-offset.-->
    <field type="uint32" base="hex" name="Signature LIST as unsigned
integer in hex format" as-offset="start_position + offset - 4" assigned-
template="AVI File LIST"/>
    <!-- The next 4 bytes are read and shown as an unsigned integer. The listSize variable gets
its value. -->
    <field type="uint32" name="Size of the data in the list"
var="listSize"/>
    <!-- The 4 bytes are read and shown as an ANSI string. -->
    <field type="char" size="4" name="List type"/>
    <!-- The current position is moved backward by 4 bytes. -->
    <goto offset="-4"/>
    <!-- The same 4 bytes are shown as an unsigned hexadecimal integer. The listType variable
gets its value.-->
    <field type="uint32" base="hex" name="List type as unsigned integer in
hex format" var="listType"/>

    <!-- A test against condition (type == movi)-->
    <if test="listType == 0x69766f6d"><!-- ANSI: movi -->
      <!-- The chunksOffset variable gets the value evaluated in the expr attribute. -->
      <setvar var="chunksOffset" expr="start_position + offset - 4"/>
    </if>

    <!-- The current position is moved to the address evaluated in the address attribute. -->
    <goto address="offset + listSize - 4"/>
  </section>
</if>

<!-- A test against condition (signature == JUNK)-->
<if test="signature == 1263424842"><!-- ANSI: JUNK -->
  <!-- The section is shown with the JUNK name. -->
  <section name="JUNK">
    <!-- The next 4 bytes are read and shown as an unsigned integer. The internal variable
junkSize gets its value. -->

```

```

                <field type="uint32" name="Size of the data of the junk"
var="junkSize"/>
        <!-- The current position is moved by junkSize bytes forward. -->
        <goto offset="junkSize"/>
    </section>
</if>

<!-- A test against condition (signature == idx1) -->
<if test="signature == 829973609"> <!-- ANSI: idx1 -->
    <!-- The section is shown with the idx1 name. -->
    <section name="idx1">
        <!-- The next 4 bytes are read and shown as an unsigned integer. The internal variable
idxSize gets its value. -->
                <field type="uint32" name="Size of the data of the idx1"
var="idxSize"/>
        <!-- The section is shown with the First AVIINDEXENTRY name. -->
        <section name="First AVIINDEXENTRY">
            <!-- The 4 bytes are read and shown as an ANSI string. -->
            <field type="char" size="4" name="Chunck id"/>
            <!-- The next 4 bytes are read and shown as an unsigned hexadecimal integer. -->
            <field type="uint32" base="hex" name="Flags"/>
            <!-- The next 4 bytes are read and shown as an unsigned hexadecimal integer. The offset
attribute is evaluated for this field as a sum of the chunksOffset variable and valued of this field. -->
                <field type="uint32" base="hex" name="Chunk offset" as-
offset="chunksOffset + this"/>
            <!-- The next 4 bytes are read and shown as an unsigned integer. -->
            <field type="uint32" name="Chunk size"/>
        </section>
        <!-- The current position is moved by idxSiz bytes forward. -->
        <goto offset="idxSize"/>
    </section>
</if>

<!-- A test against the condition. && is a logical AND (&&) -->
    <if test="signature != 1414744396 && signature != 1263424842
&& signature != 829973609">
        <!-- An empty section is shown. Its name is Unknown signature found -->
        <section name="Unknown signature found">
        </section>
        <!-- The current position is moved to the address set in the endOfFile variable. -->
        <goto address="endOfFile"/>
    </if>

```

```

        </repeat>
    </section>
</if>
</section>
</template>

```

## 4.7 Pattern Example II

```

<?xml version="1.0" encoding="utf-8"?>
<!-- A pattern section. The pattern name is AVI File LIST -->
<template name="AVI File LIST">
    <!-- A template signature section. Alignment is 1. -->
    <signature align="1">
        <!-- A 4-byte signature at offset 0x00. -->
        <field offset="0x00">4C 49 53 54</field> <!-- ANSI: LIST -->
    </signature>

```

<!-- A data section. Its name is AVI File LIST. This is the main data section. It is not shown in the parsing tree as a section (its name is ignored).-->

```

<section name="AVI File LIST">
    <!-- The first 4 bytes are read and shown as an ANSI string. -->
    <field type="char" size="4" name="Signature: LIST"/>
    <!-- The current position is moved to the beginning of the file (4 bytes backward). -->
    <goto offset="-4"/>
    <!-- The first 4 bytes in the file are read and shown as an unsigned integer. The internal variable signature
gets the value of the field. -->
    <field type="uint32" name="Signature LIST as unsigned integer" var="signature"/>

    <!-- A test against the condition (signature == LIST) -->
    <if test="signature == 1414744396"> <!-- ANSI: LIST -->
        <!-- The next 4 bytes are read and shown as an unsigned integer. The internal variable listSize gets its
value. -->
        <field type="uint32" name="Size of the data in the list" var="listSize"/>
        <setvar var="endOfList" expr="offset + listSize"/>

        <field type="char" size="4" name="List type"/>
        <goto offset="-4"/>
        <field type="uint32" base="hex" name="List type as unsigned integer in hex
format" var="listType"/>

    <!-- A test against condition (listType == movi) -->
    <if test="listType == 0x69766f6d"> <!-- ANSI: movi -->
        <!-- This chunk is not to be parsed. The current position is moved to the end of the chunk. -->

```

```

    <goto address="endOfList"/>
</if>

<setvar var="mediaType" expr="0"/>
<repeat test="endOfList > offset - 8">
    <section name="CHUNK">
        <field type="char" size="4" name="Chunk ID"/>
        <goto offset="-4"/>
        <field type="uint32" name="Chunk ID as unsigned integer" var="chunkId"/>
        <if test="chunkId == 1414744396"><!-- ANSI: LIST -->
            <goto offset="-4"/>
            <field type="uint32" base="hex" name="LIST chunk ID as unsigned integer in hex
format" as-offset="start_position + offset - 4" assigned-template="AVI File LIST"/>
            </if>

                <field type="uint32" name="Size of the data in the chunk"
var="chunkSize"/>
            <setvar var="endOfChunk" expr="offset + chunkSize"/>

<!-- Rounding the value of the variable endOfChunk to a number divisible by 2. -->
            <if test="endOfChunk & 1">
                <setvar var="endOfChunk" expr="endOfChunk & 0xFFFFFFFFE"/>
                <setvar var="endOfChunk" expr="endOfChunk + 2"/>
            </if>

<if test="chunkId == 1751742049"><!-- ANSI: avih -->
    <field type="uint32" name="Number of microseconds between frames"/>
    <field type="uint32" name="Approximate maximum data rate of the file"/>
    <field type="uint32" name="Alignment for data, in bytes"/>
        <field type="uint32" name="Bitwise combination of zero or more of the
flags"/>
    <field type="uint32" name="Total number of frames of data in the file"/>
    <field type="uint32" name="Initial frame for interleaved files"/>
    <field type="uint32" name="Number of streams in the file"/>
    <field type="uint32" name="Suggested buffer size for reading the file"/>
    <field type="uint32" name="Width of the AVI file in pixels"/>
    <field type="uint32" name="Height of the AVI file in pixels"/>
    <field type="binary" size="16" name="Reserved"/>
</if>

<if test="chunkId == 1852994675"><!-- ANSI: strn -->

```

```
<field type="char" size="chunkSize" name="Stream name"/>
</if>

<if test="chunkId == 1752331379"> <!-- ANSI: strh -->
  <field type="char" size="4" name="Type"/>
  <goto offset="-4"/>
  <field type="uint32" base="hex" name="Type as unsigned integer in hex
format" var="type"/>
  <setvar var="mediaType" expr="type"/>
  <field type="char" size="4" name="Handler (codec)"/>
  <field type="uint32" base="hex" name="Flags"/>
  <field type="uint32" name="Number of the first block of the stream that
is present in the file"/>
  <field type="uint32" name="Scale"/>
  <field type="uint32" name="Rate"/>
  <field type="uint32" name="Start time of stream"/>
  <field type="uint32" name="Size of stream in units as defined in Rate
and Scale"/>
  <field type="uint32" name="Size of buffer necessary to store blocks of
that stream"/>
  <field type="uint32" name="Quality"/>
  <field type="uint32" name="Sample size (number of bytes of one stream
atom)"/>
</if>

<if test="chunkId == 1718776947"> <!-- ANSI: strf -->
  <if test="mediaType == 0x73646976"> <!-- ANSI: vids -->
    <section name="BITMAPINFOHEADER">
      <field type="uint32" name="Number of bytes required by the
structure"/>
      <field type="int32" name="Width of the bitmap, in pixels"/>
      <field type="int32" name="Height of the bitmap, in pixels"/>
      <field type="uint16" name="Number of planes for the target device"/>
      <field type="uint16" name="Number of bits-per-pixel"/>
      <field type="uint32" name="Type of compression for a compressed
bottom-up bitmap"/>
      <field type="uint32" name="Size, in bytes, of the image"/>
      <field type="int32" name="Horizontal resolution, in pixels-per-
meter, of the target device for the bitmap"/>
      <field type="int32" name="Vertical resolution, in pixels-per-meter,
of the target device for the bitmap"/>
      <field type="uint32" name="Number of color indexes in the color
table that are actually used by the bitmap"/>
    </section>
  </if>
</if>
```

```
        <field type="uint32" name="Number of color indexes that are required
for displaying the bitmap"/>
    </section>
</if>

<if test="mediaType == 0x73647561"><!-- ANSI: auds -->
    <section name="WAVEFORMATEX">
        <field type="uint16" name="Waveform-audio format type"/>
        <field type="uint16" name="Number of channels in the waveform-audio
data"/>
            <field type="uint32" name="Sample rate, in samples per second
(hertz)"/>
                <field type="uint32" name="Required average data-transfer rate, in
bytes per second, for the format tag"/>
                    <field type="uint16" name="Block alignment, in bytes"/>
                        <field type="uint16" name="Bits per sample for the Waveform-audio
format type"/>
                            <field type="uint16" name="Size, in bytes, of extra format
information appended to the end of the WAVEFORMATEX structure"/>
                                </section>
                            </if>
                        </if>
                    </if>

                <goto address="endOfChunk"/>
            </section>
        </repeat>

    </if>

<if test="signature != 1414744396">
    <section name="Invalid LIST signature found">
    </section>
</if>

</section>
</template>
```



## V Technical Information and Troubleshooting

This chapter covers various technical issues and troubleshooting.

- [IntelligentScan technology](#)
- [Data Recovery Issues](#)
- [Extended Information Recovery](#)
- [Data Formats and Multipliers](#)
- [Data Recovery on HFS/HFS+ file system](#)
- [Supported Virtual Disk and Disk Image Formats](#)
- [Bad Sectors](#)
- [Memory Usage](#)
- [R-Studio Switches](#)
- [Properties Tab](#)

### [R-Studio Features](#)

### [Contact Information and Technical Support](#)

### [Data Recovery Using R-Studio](#)

### [Basic File Recovery](#)

### [Advanced Data Recovery](#)

### [Mass File Recovery](#)

### [Volume Sets and RAIDs](#)

### [Data Recovery over Network](#)

### [Text/Hexadecimal Editor](#)

### [R-Studio Emergency](#)

### [R-Studio Agent Emergency](#)

## 5.1 IntelligentScan Technology

**R-Studio** uses a unique *IntelligentScan* technology when it tries to recover the data on the area being scanned.

While scanning the selected area, **R-Studio** reads data directly from the drive, analyzes them, and tries to determine a record to which the data belong. The following record types are possible:

- MBR/GPT records
- NTFS Boot Sector, Folder, and MFT records
- [FAT/exFAT](#) Boot Sector, folder, and file records
- ReFS Boot sector records and ReFS Meta blocks
- HFS/HFS+ Volume headers and BTree+ nodes
- APFS Super blocks, APFS Volume blocks, and APFS nodes
- Ext2/3/4FS SuperBlocks records
- [UFS/FFS](#) SuperBlock records
- Specific file signatures of [Known File types](#) for raw file carving

All these record types have different, but known, structure. Knowing valid values of record fields and relations between them for each record type, **R-Studio** determines a record type for the data. If such record type cannot be unambiguously determined, the data are assigned to the most probable record type. The same data can be assigned to several record types, with a certain probability for each assignment. A list of possible files is generated from these records.

**R-Studio** generates a record list for each record type. This list contains references to records assigned to a record type from the list with their assignment probability. The same data can be included into different record lists. Then **R-Studio** analyzes relations between elements in each list and between different lists, and generates a list of found [partitions](#) with their parameters, such as partition start point and probable size, file system type, cluster size, and existence probability.

Using the file list and partition list, **R-Studio** reconstructs file systems and files on the found partitions. One file can be attributed to several different partitions.

When the entire drive or its part has been scanned, **R-Studio** shows all found partitions. Then the parameters of the found partitions may be manually corrected, if additional information on them is available.

Using the *IntelligentScan* technology, **R-Studio** can recover files not only on new and existing partitions. It also can find and recover data on partitions that have been deleted or [reformatted](#). If, for example, there was an NTFS partition, which later was reformatted as a FAT partition, **R-Studio** will show two partitions on the same place on the drive, one having the FAT file system, the other the NTFS. Then, files found on those partitions can be recovered.

The *IntelligentScan* technology makes **R-Studio** a very powerful data recovery tool, but it is not omnipotent. As it uses probabilistic approach to data reconstruction, it cannot guarantee 100% correct results. Moreover, even if **R-Studio** has reconstructed data structure correctly, it is impossible to guarantee that all found files will be completely and correctly recovered, as new data may be already written over the old files. See the [Data Recovery Issues](#) topic for details.

## 5.2 Data Recovery Issues

**NEVER TRY TO SAVE RECOVERED FILES/FOLDERS TO THE SAME LOGICAL DISK WHERE THEY RESIDE!!!**

**Or you may obtain unpredictable results and lose all of your data.**

**R-Studio** writes directly to a drive only when writing recovered data and from its hex editor, if writing is enabled. In all other actions, **R-Studio** only reads data and analyzes them, and never modifies data on the drives being analyzed.

Most operating systems use lazy-write. So, there is a time lag between file actions and actual changes on data on a drive. **R-Studio** analyzes data on drives only. That is why it does not always detect recent changes in data structure.

Most operating systems constantly write their service information on drives. Such writing is especially intensive during startup and shutdown procedures. When an operating system deletes a file/folder, it treats the space where it has resided as empty and may write something in this place. If this happened, the file/folder and its parameters may be detected correctly, but its data may be lost.

Folder names like **\$\$\$Folder58448** on NTFS [partitions](#) mean that the folder has not been found on the drive but some references to it have been. For example, folders My documents, Work, Photos have been found and all they have one parent folder, whose description has not actually been found on the drive, so its name is unknown and therefore represented as **\$\$\$Folder58448**. It may happen that the description of such folders was outside of the

scan area, so try to enlarge the region or scan the entire drive. If that does not help, most likely that the description of the folder has been overwritten.

Folder names like **\$ROOT58448** on [FAT](#) partitions mean that some folders have been found, but they cannot be included into the folder structure for this FAT partition. Sometimes, such folders may contain other folder structures.



If you recover a file, and it appears that the file contains wrong data, try to do the following:

- **Scan:**
  - the [logical disk](#), if the file has been just deleted.
  - the drive, if the data structure is damaged more seriously.
- **Search for the file** to be restored on all found partitions and try to recover it from all found partitions. Check each recovered file to ensure that it contains correct data. As soon as you found the partition from which the file is recovered correctly, use this partitions to recover all other deleted files.

If there are several deleted files to be restored, you should use a file larger than 2KB to select the required partition.

### **FAT file system:**

#### **Cross-Linked Folders**

Often **R-Studio** finds several FAT folder records that contain the same data. Such folders are called *cross-linked*. **R-Studio** marks such folders with an arrow mark:   Movie

**R-Studio** attributes the content of cross-linked folders to one folder called a *target folder*. When recovering, **R-Studio** places the content to the target folder.

#### **To view the list of cross-linked folders,**

- 1 **Right-click a cross-linked folder and select Cross Linked Folders on the shortcut menu**
- > **A list of cross-linked folders will appear**  
You may go to any folder in this list by clicking it.

#### **To find a target folder,**

- \* **Right-click a cross-linked folder and select Go Target on the shortcut menu, or**  
Select the cross-linked folder and select **Goto Target** on the **File** menu  
If **Go Target** is gray, this folder is already the target folder.

#### **To set the target folder manually,**

- \* **Right-click a cross-linked folder and select Set As Default Target on the shortcut menu, or**  
Select the cross-linked folder and select **Set As Default Target** on the **File** menu.  
If **Set As Default Target** is gray, this folder is already the target folder.

#### **Questionable Folders**

Sometimes, **R-Studio** may find FAT records, which look like folders, but their content is invalid. For example, file names have invalid characters, date, time, and size, or other file attributes may look strange. Please note that **R-Studio** correctly recognizes localized names. **R-Studio** treats such records as folders, but does not analyze their content and structure. You can manually scan such folders, but results may be unpredictable. Usually, such scan reveals garbage.

**R-Studio** marks such folders with a question mark.   ?MP

## To re-scan an object,

- \* Right-click a questionable folder in the **R-Studio's Folders panel** and select **Rescan** on the shortcut menu, OR

Select the questionable folder and select **Rescan** on the **File** menu.


## ReFS, NTFS, APFS, HFS, XFS, and ext fs file systems:

### Symbolic links (symlinks)


[Symbolic links](#) (of symlinks for short) are object that contains references to other files or folders directory in the form of absolute or relative paths and that affect pathname resolution. For example, if a symlink `c:\ProgramData\Documents` points to `D:\Recovered Files\Root\Users\Public\Documents`, entering it will result in entering `D:\Recovered Files\Root\Users\Public\Documents`.

They are present in almost all modern file systems. NTFS, HFS+, APFS, and EXT FS are probably the most popular examples.


**R-Studio** shows such symlinks and their targets in the following way:




### Symlinks can be marked for recovery



Only symlinks on the picture above are marked for recovery. They will be recovered as real files and folders.



Only targets (real folders) on the picture above are marked for recovery. They will be recovered as real files and folders.



Both targets (real folders) and symlinks on the picture above are marked for recovery. They will be recovered as real files and folders and symlinks.

The [R-Studio Settings](#) topic gives more details about symlink recovery.

**Files:**

**Hard links**

[Hard links](#) are file system entries that give file names to files. This term is usually used when files may have several names. **R-Studio** shows hard links using the following icons:

A hard link:  Wipe Test 2.doc

The target file:  Wipe Test 2.doc

You may find a target or [hard link](#) for a file. Right-click the file and select **Links** on the shortcut menu.

**5.3 Extended Information Recovery**

**R-Studio** supports recovery of compressed files, [alternative data streams](#), encrypted files, file security and extended file attributes. If the **R-Studio** host OS and the file system of the disk you are going to save file to support any particular extended information, it will be saved with the file, too. Otherwise, the extended information will be saved as separate files with the same name as the restored file and extension showing the type of the extended information. Below is a quick reference for the host OS and file system of the target drive.

Extended Information	Required host OS	Required target disk FS
Encrypted files	Windows 2000/XP/2003/Vista/? 2008/7/8/8.1/10	NTFS
Alternative data streams	Windows NT/2000/XP/2003/? Vista/2008/7/8/8.1/10	NTFS
File security	Windows NT/2000/XP/2003/? Vista/2008/7/8/8.1/10	NTFS
Extended file attributes	Windows NT/2000/XP/2003/? Vista/2008/7/8/8.1/10	NTFS or FAT/exFAT

**5.4 Data Formats and Multipliers**

You may enter data in all numerical fields either in sectors or in bytes. If there is no letters are after the number, **R-Studio** assumes the numbers are in bytes.


Decimal numbers are entered as they are: 2372354

Hexadecimal numbers are entered as 0x23Fa67 OR 23Fa67 hex.

The following case-insensitive notation is possible:

b	1 byte
kb	1 kb = $2^{10}$ =1024 bytes
mb	1 mb = $2^{20}$ =104857 bytes
gb	1 gb = $2^{30}$ =1073741824 bytes
tb	1 tb = $2^{40}$ =1099511627776 bytes
eb	1 eb = $2^{50}$ =1125899906842624 bytes
hex	A hexadecimal number
sec (sector)	A number is in sectors

You may also select the multipliers in the drop-down boxes.

 Type an offset to which you want to go. You may select between bytes and sectors. See the [Data Formats and Multipliers](#) topic for more details on data formats.

If a file is opened in **Text/Hexadecimal Editor**, you may select data representation for that file.



When the multiplier has been changed, the data value will be changed according to the specific shortcut commands for that field:

Suppose, the initial value is 1 GB, and the sector size of the object is 512 byte. The results will be the following:

**Command: No recalculate**

Change from GB to MB: 1

Change from GB to Sectors: 1

**Command: Always recalculate**

Change from GB to MB: 1024

Change from GB to Sectors: 2097152

**Command: Units type recalculate**

Change from GB to MB: 1

Change from GB to Sectors: 2097152

## 5.5 Data Recovery on HFS/HFS+ File System

When deleting a file, Mac OS X deletes system BTree+ records describing the file. Therefore, it is hard to recover such file directly. Those records may remain in:

1. The swap file (if the deleted file has been deleted recently).
2. In the journal (if the HFS+ journaling is on, and the deleted file has been CREATED recently)

Actually, if a file has been deleted, chances that the records would be found are small. To greatly increase the chances to recover deleted files successfully, you may actively use scanning with enabled [Known Files Types](#).

**Note:** All above is correct for intentionally deleted files. In case of a corrupted file system, HFS/HFS+ can be recovered quite successfully.

When recovering files with HFS+-specific attributes (resource fork, finder info, etc.), **R-Studio** saves it in the so-called [AppleDouble](#) format. When they are copied to an HFS+ disk under Mac OS X, those attributes will be automatically restored.

## 5.6 Supported Virtual Disk and Disk Image Formats

Along with file formats used for purely disk backup and [imaging](#) purposes, there are file formats for virtual disks. Virtual disks are software components that emulates data storage devices in virtual machines. At the same time, virtual disks can be used for disk backup and imaging, too. That is why it's expedient for disk backup and imaging software to support various file formats for virtual disks. This is especially important for system interoperability, when it's necessary to use disk backup/image files on other machines where the disk backup and imaging software isn't installed.

Currently **R-Studio** supports the following virtual disk and disk image formats:

**RDR:** A proprietary disk image format developed by **R-Tools Technology, Inc (R-TT)**. It is the main format in **R-Drive Image**, **R-Studio**, **R-Linux**, and **R-Undelete**. RDR files are interchangeable, that is, any **R-TT** program may load and process, within its capabilities, any rdr file created in another **R-TT** program.

The following image formats can be created only in the **R-Studio Corporate** and **Technician/T80+** versions:

**VHD/VHDX:** A virtual disk file format built into Windows. It's a native virtual hard drive for Hyper-V, the Windows virtual machine. You may read more about these file formats in Wikipedia: [VHD \(file format\)](#). **R-Studio** creates a special file with some metadata for the VHD file format, its extension is vhr. The VHDX file format contains this metadata within its main file.

**VMDK:** A virtual disk file format for the most virtual machines like VMware Workstation, VirtualBox, Parallels Desktop for Mac, etc. You may read more about these file format in our Glossary: [What is a VMDK Virtual Disk](#).

**VDI:** A virtual disk file format for the VirtualBox virtual machine. **R-Studio** creates a special file with some metadata for the VDI file format, its extension is vdr. You may read more about these file format in Wikipedia: [VDI](#).

**R-Studio Standalone** can load these image formats.

The main features of these file formats are presented in the table below:

Features	RDR	VHD/VHDX	VMDK	VDI
<a href="#">Compression</a>	Yes	No	Yes	No
Encryption	Yes	No	No	No
Image Split	Yes	No	Yes	No
Native mounting on Windows	No	Yes	No	No
Mounting on Windows using R-Studio	Yes	Yes	Yes	Yes

### Additional file formats that can be opened "read-only"

Extensions	Description	Licenses
dmg	<a href="#">Apple Disk Image</a>	All
e01/ewf	<a href="#">Expert Witness File Format</a>	<b>Technician/T80+</b>

aff

[Advanced Forensic Format](#)

Technician/T80+

## 5.7 Bad Sectors

Quite often, drives from which the data are to be recovered have [bad sectors](#), or those sectors that are very hard, even impossible, to read, mostly due to hardware problems. **R-Studio** tries to read such sectors several times. The number of tries is specified either on the [Settings/Bad Sectors](#) dialog box, or on the [Properties](#) tab, the Drive Control section, for each drive separately.

When **R-Studio** encounters such bad sectors while performing various tasks and they appear unreadable, it treats them as follows:

### **Object images:**


**R-Studio** fills the space in the [image](#) file where the bad sectors should be with the pattern specified in the Pattern to fill bad blocks field on the [Settings/Bad Sectors](#) dialog box. Please note that **R-Studio** writes the pattern on the image, not on the source drive.

### **Files**

If Skip files with bad sectors on the [Recovery](#) dialog box is cleared, **R-Studio** fills bad sectors in the recovered file with the pattern specified on the the [Settings/Bad Sectors](#) dialog box. Information about such files will appear in the [Log](#).

If Skip files with bad sectors on the [Recovery](#) dialog box is selected, **R-Studio** skips files with bad sectors and displays their list on the Files with bad sectors dialog box when the recovery has been completed. You may select files to immediately recover them or to mark for later recovery. You may also save this list to a text file.

### Files with bad sectors dialog box



### **Files with bad sectors Buttons**

Select All	Click this button to select all files in the list.
Clear All	Click this button to unselect all selected files.
Mark	Click this button to mark all selected files in the list.
Save to File	Click this button to save the list of files with bad sectors to a text file.
Recover	Click this button to immediately recover selected files. The bad sectors in the recovered files will be filled with the pattern specified in the Pattern to fill bad blocks field on the <a href="#">Settings/Bad Sectors</a> dialog box.

### **Objects edited in the Text/Hexadecimal Editor/Viewer**

Bad sectors in the objects viewed/edited in the [Text/Hexadecimal Editor](#) are shown as filled with the pattern specified in the Pattern to fill bad blocks field on the [Settings/Bad Sectors](#) dialog box.



## 5.8 Memory Usage


You may see how much memory **R-Studio** uses while performing a data recovery task. This is especially useful when scanning large drives on a computer with limited resources. You may specify memory control options on the Memory usage tab in the **R-Studio Settings**.

To view memory usage,

1 Select Memory usage on the Tools menu

> **R-Studio** will show the total memory in your computer and how much memory it uses

Memory usage dialog box



### Memory usage

Process Memory	Shows how much memory <b>R-Studio</b> uses. Limit shows how much memory your system can virtually allocate to <b>R-Studio</b> . Actual memory allocation depends also on the RAM and swap file sizes.
System Memory Physical	Shows how much RAM is in your system
System Memory Swap	Shows how much virtual memory is in your system

## 5.9 R-Studio Switches

If there are problems in starting **R-Studio** and while working with it, you may use switches to avoid them.

The following switches are available:

-all_drives	Forces <b>R-Studio</b> to show all <a href="#">logical disks</a> in the system. Normally <b>R-Studio</b> shows only local drives in the system. Some storage devices may pretend that they are not local drives.
-debug	Includes additional debug information. When this switch is used, an additional command <b>Create FS Snapshot</b> on the shortcut menu appears for an object with a file system. An FS Snapshot contains system data for the file system only (file descriptions without file contents). If a problem appears, this snapshot can be sent to <b>R-Studio</b> technical support to identify the problem. This switch greatly slows <b>R-Studio</b> . You may also turn this mode on by selecting <b>Debug Mode</b> on the <a href="#">Settings</a> dialog box.
-flush	Flushes the log file after each write to log operations. This switch is helpful when <b>R-Studio</b> locks and its log file remains in memory cache unwritten to a drive. This switch greatly slows <b>R-Studio</b> .
-log <filename>	Started with this switch, <b>R-Studio</b> writes its log into the specified file. If <b>R-Studio</b> locks and its log file remains in memory cache unwritten to a drive, use the <code>-flush</code> switch.
-mem <size in MB>	Sets memory usage limit in MB for <b>R-Studio</b> to reconstruct the file tree. When it exceeds the limit, a Too many files... message appears. You may temporarily stop file

	listing and browse through found files. Then you can resume file listing. You also may skip this file section and continue file listing. Example: <code>-mem 400</code> - sets the limit to 400 MB.
<code>-no_ide_ext</code>	Turns off the inquiry about extended information on HDDs in Wind9x/ME. This switch may be helpful if <b>R-Studio</b> returns information about HDDs incorrectly (detects HDD geometry incorrectly).
<code>-no_int13</code>	Turns off the disc access through Int13 in Wind9x/ME. This switch may be helpful if the system operates incorrectly (detects HDD geometry incorrectly or lock the system).
<code>-no_ios</code>	Turns off the Wind9x/ME protected-mode I/O system. This switch may be helpful if this system operates incorrectly (detects HDD geometry incorrectly or lock the system).
<code>-reset</code>	<b>R-Studio</b> resets an HDD controller each time it reads a <a href="#">bad sector</a> . This switch may be helpful if the controller locks after it attempts to read a bad sector, or returns incorrect data.
<code>-safe</code>	Disables automatic <a href="#">partition</a> search on a drive, file system recognition on partitions, and other potentially problematic operations. In this mode, it is necessary to use <b>Find partition</b> command from the drive shortcut menu to manually find a partition.

If an unrecognized problem appears, start **R-Studio** with the `-debug` and `-log <filename>` switches, and send the log and screenshot of the **R-Studio** main panel to the **R-Studio** technical support:

[R-Studio Technical Support Team](#) is available 24 hours a day, seven days a week, and has an average response time less than 4 hours.

## 5.10 Properties Tab

### Object size units

You may select the units in which the information on object sizes will be displayed. Some parameters can be edited when the Debug mode is turned on on the [Main](#) dialog box of the **R-Studio** settings.

#### To select the units

- 1 Select Properties on the View menu
- 2 Select the units in which you want to see object sizes.

You may select

Show as Bytes

Show as Sectors

Show as Bytes and Sectors

#### 1. Basic information

This section shows basic information for a drive object.

##### More information...

Drive Type	Device/drive type and subtype. Current <b>R-Studio</b> version supports the following types: Disk, WORM, CDROM, Optical, Changer, Floppy, RAM Disk, LDM Partition, LDM Component, LDM Volume and subtypes:
------------	--

	Device, OS File, Physical Drive, Mount Point, Partition, Volume Set, Mirror, Stripe Set, RAID 4, RAID 5, RAID 6
Name	Device/drive name
Size	Device/drive size
Bus Type	Device/drive bus type. Can be: IDE/ATA, IDE/ATAPI, SCSI, Floppy, USB, 1394, SSA, FibreChannel, RAID, SMART, ABIOS

## 2.Information on drives and logical disks

This section shows available information on drives and [logical disks](#). These properties depend on the drive/disk type and appear only when applicable. Under Windows, an IDE drive/disk may be represented as a SCSI device, that is why the SCSI Address section appears under these OSEs for those drives/disks.

### More information...

OS object	Appears for <a href="#">image</a> files under Windows for drives/disks. An object name used by OS to access the Device/drive.
R-Studio driver	Driver names (both internal and OS) used to access this drive/disk.
Sector Size	Drive/disk sector size
Physical Drive Geometry	This section shows physical geometry for a drive. For a logical disk it shows the physical geometry for a drive where the logical disk resides
Cylinders	
Tracks Per Cylinder	
Sectors Per Track	
Sector Size	
Device Identification	This section shows vendor information for the drive/disk
Vendor	
Product	
Firmware	
Bus	
SCSI Address	This section shows SCSI information for the drive/disk
Port Number	
Path ID	
Target ID	
Lun	

### Windows 9x/ME adds the following properties:

Int13 Drive Number	128 for the first drive accessible through Int13, 129 for the second one, etc. 0...128 for drives and other devices accessible through a Windows 9x/ME protected mode driver, if their Int13 device option is disabled. <b>R-Studio</b> can use Int13 disk access, and for some drive types, like SCSI devices, Int13 access is preferable. You may consider enabling the Int13 device option in the Windows Device Manager for such devices.
Int13 Extension Version	Int13 Extension Version Support for drives. Extended Int13 support is necessary for large drives. If this property is zero, Extended Int13 is not supported, otherwise, it

	shows Extended Int13 standard version, the large, the better.
--	---

### 3.Properties controlling access to drives and logical disks

This section shows properties that control access (read and write) to drives and logical disks. They are set to their optimal values and should be altered only if access problems appear.

#### More information...

Drive Control	
Maximum transfer	Maximum data size that can be read or written during a single access to the drive. If there are problems with drive access, decrease the value of this property
I/O Unit	Data size read or written during a single access to the drive is a multiple value of this property. If there are problems with drive access, decrease the value of this property
Buffer Alignment	Drive data transfer buffer is positioned at an address multiple value of this property. If there are problems with drive access, increase the value of this property.
These three properties are set by OS drivers. If the drivers set incorrect values, problems may appear during data transfer operations. You can alter them until data transfer becomes stable.	
I/O Tries	<p>Number of read/write tries during access to the drive. If there are <a href="#">bad sectors</a> on the drive, increase the value of this property. This may help to successfully read those sectors. Sometimes, if the I/O Tries parameter is set too large and there are some unreadable sectors on the drive, the drive-controller pair may refuse to perform any successive read/write operations with the entire drive when it fails to read/write such sectors. In this case, set this parameter to zero.</p> <p>The default value is specified in the <a href="#">Settings (Bad Sectors)</a> panel.</p> <p><b>R-Studio</b> treats bad sectors in the following way: It reads a certain part of drive (predefined by Windows) and</p> <ul style="list-style-type: none"> <li>• If Default read attempts is set to 0, the entire part with bad sectors will be filled with the specified pattern.</li> <li>• If Default read attempts is set to a non-zero value, <b>R-Studio</b> reads again that part sector by sector, repeating the attempts the specified number of times. If <b>R-Studio</b> still cannot read a bad sector, it fills the sectors with the specified pattern. In this case only the bad sectors will be filled with the pattern, but that extremely slows the drive read process.</li> </ul> <p>For example, if you set Default read attempts to 1, a bad sector will be read 2 times.</p>

### 4.Partition properties

A [partition](#) is a continuous area on a drive, characterized by its offset and size. There are partitions on basic disks, dynamic disks, and recognized volumes and partitions. **R-Studio** treats regions like partitions.

#### More information...

Partition Offset	Initial offset for the partition.
Partition Size	Size of the partition.
Partition Type	File system type for the partition. If the record in the drive partition table is incorrect, this property may differ from the actual file system type for this partition. Still, <b>R-Studio</b> will process this partition correctly, as it does not use this property.
Partition number	Appears under Windows NT/2000/XP/2003/Vista/2008/7/8/8.1/10 only. Shows the number of the partition on the physical drive.

For regions and recognized partitions, Partition Offset and Partition Type properties can be manually corrected.

### 5. Compound volume properties

A *compound volume* is a union of several partitions or other drive objects. Each union type has its own rules, unique for each compound volume type. Among compound volumes are: *Volume Sets* (RAIDs Level 0), *Mirrors* (RAIDs Level 1), *RAIDs4/5/6* (RAIDs Level 4/5/6), both physical and created by the user (*Virtual Volume Sets*, *Virtual Stripe Sets*, *Virtual Mirrors*, *Virtual RAID5*).

**More information...**

Main properties of compound volumes are *parents* (drive objects from which a compound volume is created) and their order. These properties may be viewed in the Parents tab. For user-created compound volumes these properties may be altered.

Raid Block Size	Data block size for compound volumes of RAID (Level 0-5) types
-----------------	--

### 6. LDM disks and volumes (Dynamic Disks)

*LDM disks and volumes* are volumes controlled by Logical Disk Manager (LDM). They are represented on a drive as a LDM database rather than partition tables. Under Windows 2000/XP/2003/Vista/2008/7/8/8.1/10, LDM disks are also called *Dynamic Disks*.

**More information...**

Offset of Logical Disk	Initial offset of a logical disk on a drive. For disks, initially <a href="#">formatted</a> by LDM, this value is often <b>31.5KB</b> , for converted disks, it may be larger.
Supposed Parents Count	Supposed number of parent partitions for compound LDM volumes. If the LDM database is not damaged, the value of this property must be equal to the number of parent objects in the Parents tab for the drive object.
LDM Host GUID	Global Unique Identifier of a computer system where this LDM disk group has been created.
LDM DiskGroup GUID	Global Unique Identifier of the LDM disk group.
LDM Disk GUID	Global Unique Identifier of the drive.
LDM Volume GUID	Global Unique Identifier of the volume.
LDM Disk ID	Local drive Identifier, unique within this LDM disk group.
LDM Partition ID	Local partition Identifier, unique within this LDM disk group.
LDM Component ID	Local component Identifier, unique within this LDM disk group.
LDM Volume ID	Local volume Identifier, unique within this LDM disk group.
LDM Disk AltName	Additional Alternative Name given by LDM to the drive.
LDM Disk DriveHint	Last name of the volume, under which is has been mounted in the system. May be either a letter (C:, D:, etc.), or a mount point under Windows 2000/XP/2003/Vista/? 2008/7/8/8.1/10.

### 7. File System Volume properties

A *File System (FS) volume* is a disk object where a certain, supported by **R-Studio**, file system is present. There are two FS volume types: FS volume on a regular drive object and a recognized volume, found by a scan process. FS volume properties depend on volume's file system and type.

### 7.1. NTFS Volume properties

These properties are present for all NTFS volumes and represent their main properties. For *recognized volumes*, these values can be altered.

#### ▣ More information...

NTFS Information	Regular volumes
Recognized NTFS	Recognized volumes
Cluster Size	Cluster size for the NTFS volume.
MFT record size	Size of one MFT record describing one file on the NTFS volume. This is an important property of any NTFS volume. Its common value is 1KB. If this property has incorrect value, many files may be incorrectly recovered.
Sector Size	Sector size for the physical drive. This property is read from the boot sector of the NTFS volume and does not affect <b>R-Studio</b> operation.
Index Block Size	Index block size for the NTFS volume. This property determines binary trees used to store NTFS folder structure. It does not affect <b>R-Studio</b> operation.
MFT position	MFT offset from the start of the NTFS volume.
MFT Mirror Position	Second MFT copy offset from the start of the NTFS volume.
Volume size	Size of the NTFS volume. This property does not affect <b>R-Studio</b> operation.

### 7.2. FAT Volume properties

These properties are present for all [FAT](#) volumes and represent their main properties. For *recognized volumes*, these values can be altered.

#### ▣ More information...

FAT Information	Regular volumes
Recognized FAT	Recognized volumes
FAT Bits (12,16,32)	FAT type. 12 for the FAT12, 16 for the FAT16, 32 for the FAT32.
Cluster Size	Cluster size for the FAT volume.
First Cluster Offset	Offset of the first cluster from the start of the FAT volume.
Boot Directory Cluster	( <i>For FAT32 only.</i> ) Cluster number where the root directory starts on the FAT volume where the logical disk resides.
Root Directory Offset	( <i>For FAT12 and 16 only.</i> ) Root directory offset from the start of the FAT volume.
Root Directory Length	( <i>For FAT12 and 16 only.</i> ) Root directory length for the FAT volume.
First FAT Offset	Offset for the first FAT table on the volume. Together with the Size of One Fat Table property, is a most important property for a FAT volume. If this property is incorrect, many files (especially fragmented ones) may be incorrectly recovered.
Size of One FAT Table	Size of one FAT table on the volume.
Sector Size	Sector size of the drive. This property is read from the boot sector of the FAT volume and does not affect <b>R-Studio</b> operation.
Number of FAT Copies	Number of FAT copies on the FAT volume.

Active FAT copy	Active FAT table number for the FAT volume. Can be set to Disabled, Auto, 1, or 2. If it is Disabled, <b>R-Studio</b> processes the volume as there is no FAT table present. This may be useful if the volume has been reformatted and thus a new FAT table is created and the old one is deleted. In this case, it is reasonable to recover files from the previous volume without processing the new and irrelevant FAT table. All files will be recovered as continuous byte chains beginning from their start cluster. Unfragmented files will be recovered successfully. If it is 1 or 2, <b>R-Studio</b> uses the first or second FAT table copy, respectively. If it is Auto, <b>R-Studio</b> uses both FAT table copies and decides, which FAT table copy should be used for a particular FAT table sector. This may be useful when both FAT tables are partially damaged.
Major version	FAT version.
Minor version	FAT minor version.
Volume size	Size of the volume.

### 7.3.Ext2/3/4FS Volume properties

These properties are present for all [Ext2/3/4FS](#) volumes and represent their main properties. For *recognized volumes*, these values can be altered.

#### More information...

Ext2FS Information	Regular volumes
Recognized Ext2/3/4FS	Recognized volumes
Block Size	Block size of Ext2FS file system. A block in the Ext2/3/4FS file system is similar to a cluster in the FAT file system.
First SuperBlock Offset	Offset of the first SuperBlock from the start of the Ext2/3/4FS volume.
Blocks Per Volume	Number of blocks in the Ext2/3/4FS volume.
INodes Per Volume	Number of inodes on the Ext2/3/4FS volume. An inode is a record describing file's size, attributes, position on an Ext2F/3/4S volume - all information about a file, except its name, which is stored separately. Therefore, the INodes Per Volume parameter is equal to the maximum number of files on an Ext2/3/4FS volume.
Creator OS	The OS that created this Ext2/3/4FS volume. May be Linux, Hurd, Masix, FreeBSD, Lites.
Major version	Ext2/3/4FS version. Usually 1.
Minor version	Ext2/3/4FS minor version. Usually 0.
Last Mount Time	Last mount time for this Ext2/3/4FS volume.
Last Write Time	Last write time for this Ext2/3/4FS volume.
Last Check Time	Last check time for this Ext2/3/4FS volume.
Volume size	Size of the volume.

### 7.4.Recognized Volume properties

These properties are present for all *recognized volumes*, regardless of their file system type. They estimate how reliable those volumes are recognized. This is useful for fast search for, and selection of, optimally recognized volume to recover.

**More information...**

Parsed File Entries	Number of files proving that this recognized volume existed. May have any non-negative values. The main property characterizing the reliability of volume recognition. The larger it, the higher probability that this recognized volume has file system properties that have been correctly found.
Parsed Boot Records	Number of boot records proving that this recognized volume existed. May be 0 or 1. This is the second important property characterizing the reliability of volume recognition.
Estimated Size	Estimated size of the recognized FS partition/volume. This property shows the most probable size of the recognized FS partition/volume. Alternatively, Size and Partition Size are set to the highest possible values in order to recover the maximum number of files.



## VI R-Studio Emergency

**R-Studio Emergency** is a tool that allows you to startup a computer with a damaged startup disk and recover data stored on its hard drives. Then restored data can either be saved on its disk or transferred to a working computer via a network.

The R-Studio Emergency version is a part of the R-Studio software package.

You may run this R-Studio Emergency version on a computer for which you have bought an R-Studio license, and you may not transfer the licensed software to another computer.

### [R-Studio Emergency](#)

[Contact Information and Technical Support](#)

[Installing R-Studio Emergency Startup Media Creator](#)

[Creating Startup Disks](#)

### [R-Studio Emergency Operation](#)

[Starting a Computer with the R-Studio Emergency Startup Disks](#)

[File Recovery](#)

[Searching for a File](#)

[Disk Scan](#)

[Disk Images](#)

### [Using R-Studio Emergency as Emergency Agent](#)

### [Technical Information](#)

[Network Drives](#)

[Properties and Text/Hexadecimal Viewer](#)

[Log](#)

[Devices to Store Recovered Files](#)

### [Hardware Compatibility List](#)

## 6.1 Contact Informaiton and Technical Support

To obtain the latest version of **R-Studio Emergency**, go to:

Product Site: <http://www.r-tt.com>

Sales Department: [sales@r-tt.com](mailto:sales@r-tt.com)

**R-Studio** Technical Support Team is available 24 hours a day, seven days a week, and has an average response time less than 4 hours.

Tech. Support: [support@r-tt.com](mailto:support@r-tt.com)

Send your support request to: [http://www.r-tt.com/Support\\_request.html](http://www.r-tt.com/Support_request.html)

## 6.2 Creating Startup Disks

- [Installing R-Studio Emergency Startup Media Creator](#)
- [Creating Startup Disks Using R-Studio Emergency Startup Media Creator](#)


- [Creating Startup Disks for Mac and Linux Computers](#)

## 6.2.1 Installing R-Studio Emergency Startup Media Creator

You must have administrative privileges to install R-Studio Emergency Startup Media Creator.

If you are not sure whether you have such privileges, you almost certainly do not have them. Contact your system administrator for assistance.


### 1 Run the setup wizard




### 2 Read the License Agreement and accept its conditions.




### 3 Select the installation location




### 4 Select the Start Menu Folder



## 5 Wait for the program to install



## 6 You may start creating R-Studio Emergency immediately upon install completion.



### 6.2.2 Creating Startup Disks Using R-Studio Emergency Startup Media Creator

You need to create either

- A startup FAT/FAT32 removable device recognized by your system as a bootable one. The total available size of the device should be more than 50 MB. You may use this device to start both UEFI computers (modern Windows/Mac/Linux systems) and old Windows/Mac/Linux machines.

or

- A startup CD/DVD disc. You may create an ISO image, or write the disc directly from **R-Studio** Emergency Startup Media Creator, if there is a CD/DVD recorder in your system. You may use this disc to start both UEFI computers (modern Windows/Mac/Linux systems) and old Windows/Mac/Linux machines.

You may create a [Linux-based](#) or [WinPE](#) based startup disk.


#### 1 Run R-Studio Emergency

## Welcome dialog box



click the **Next** button to see the list of all devices on which startup disks may be created.

## Startup media type selection dialog box




## A Linux-based disk

Check the [Hardware Compatibility List](#).

If you have problems with starting your computer up from the **R-Studio** Emergency startup disks, select **Configure startup media troubleshooting options** on the Startup media type selection dialog box. Then the [Startup Media Troubleshooting Options](#) dialog box will appear. You may configure these options to eliminate those problems.


**3 Select Linux based on the Startup OS selection and click the Next button.**

## Startup OS selection dialog box




- 4 **Read and accept the Activation terms on the R-Studio Emergency GUI Activation dialog box and click the Next button.**

#### R-Studio Emergency GUI Activation dialog box




If you create startup disk for **R-Studio Emergency Technician**, you'll need to enter your license key on the Registration dialog box.

#### Registration dialog box




- 5 **Specify the path and name for the ISO file or verify that you've select the correct USB device and click the Next button.**

#### Insert media dialog box



- > **R-Studio Emergency Startup Media Creator will start creating the startup USB disk showing the progress on the Creating startup media dialog box**

Creating startup media **dialog box**




**R-Studio Emergency Startup Media Creation is Finished message**



### Startup Media Troubleshooting Options

Those options will help you if you have problems with starting you computer up from the **R-Studio** startup disks. Please, contact the [R-Studio Technical Support Team](#) for more information.

**R-Studio** Startup Media Troubleshooting Options **dialog box**




Display kernel startup messages	if this checkbox is enabled, <b>R-Studio</b> Emergency displays all startup messages. That may be useful to locate the source of the problem when your system hangs during <b>R-Studio</b> Emergency startup.
Disables ACPI Disables APIC	Select these checkboxes when your system detects some hardware incorrectly during <b>R-Studio</b> Emergency startup and displays messages like: <code>hda: lost interrupt</code>
Disables USB device support	Select this checkbox if your system experiences problems with USB devices during <b>R-Studio</b> Emergency startup.

Disables SCSI device support	Select this checkbox if your system experiences problems with SCSI devices during <b>R-Studio</b> Emergency startup.
Disables PCMCIA device support	Select this checkbox if your system experiences problems with PCMCIA devices during <b>R-Studio</b> Emergency startup.
Disables DMA for all IDE disk drives	Select this checkbox if your system experiences problems with IDE disks during <b>R-Studio</b> Emergency startup.
IRQ polling mode	Select this checkbox to enable the IRQ polling mode to prevent locking the system because a device generates too much interrupts for the system to handle.
PCI BIOS	Select an appropriate option if your system experiences problems with PCI cards.
BIOS RAIDS	Select an appropriate option if your system experiences problems with RAIDs built in the system board.

## A WindowsPE-based disk


### 3 Select Windows based on the Startup OS selection and click the Next button.

Startup OS selection dialog box



If you select this option for the first time, you'll need to download and install some extra Windows components. Click the Download button and follow the on-screen instructions. When the process is finished, you'll be able to continue creating the startup disk.

Startup OS selection dialog box




If you select this option for the first time, you'll need to download and install some extra Windows components. Click the Download button and follow the on-screen instructions.

You don't have to perform these steps next times.


- 4 Read and accept the Activation terms on the R-Studio Emergency GUI Activation dialog box and click the Next button.

#### R-Studio Emergency GUI Activation dialog box




If you create startup disk for **R-Studio Emergency Technician**, you'll need to enter your license key on the Registration dialog box.

#### Registration dialog box



- 5 Specify the path and name for the ISO file or verify that you've select the correct USB device and click the Next button.


#### Insert media dialog box






- > **R-Studio Emergency Startup Media Creator will start creating the startup USB disk showing the progress on the Creating startup media dialog box**

Creating startup media **dialog box**



**R-Studio Emergency Startup Media Creation is Finished message**



### 6.2.3 Creating Startup Disks on Mac and Linux Computers

To start a Mac or a Linux computer, you may use the following devices:

1. A USB device created using the R-Studio Emergency Startup Media Creator for Windows. See the [Creating Startup Disks Using R-Studio Emergency Startup Media Creator](#) page for more details.
2. A USB device created using a Mac or Linux computer. To create such device, download the ZIP archive of R-Studio Emergency, unzip it, and write files to a FAT32-formatted USB device.

Please note that you cannot use this disk to start non-UEFI computers (old Macs, for example), nor can you just copy those files to a CD/DVD disc to create an R-Studio Emergency startup disc. If you need a CD/DVD disc, burn it using the ISO image.

3. A startup CD/DVD disc. Download the ISO image of that disk and burn it or use the R-Studio Emergency Startup Media Creator for Windows to burn it on a Windows computer.

## 6.3 R-Studio Emergency Operation

[Starting a Computer with the R-Studio Emergency Startup Disks](#)

[File Recovery](#)

[Searching for a File](#)

[Disk Scan](#)

[Disk Images](#)

[Using R-Studio Emergency as Emergency Agent](#)

## [Technical Information](#)

[Properties and Text/Hexadecimal Viewer](#)

[Network Drives](#)

[Log](#)

[Devices to Store Recovered Files](#)

## [Hardware Compatibility List](#)

## [R-Studio Emergency](#)

[Contact Information and Technical Support](#)

[Installing R-Studio Emergency Startup Media Creator](#)

[Creating Startup Disks](#)

### 6.3.1 Starting a Computer with the R-Studio Emergency Startup Disks

We recommended that you print out this help page and have the hardcopy on hand while you are performing this action.

If there is a non-IDE disk controller in your system, or you plan to use network disks or external hardware devices, first check the [Hardware Compatibility List](#).

If you plan to use any external device, turn it on before starting the system.

If the motherboard in your computer supports the Serial ATA (SATA) devices, but IDE disks are also present, only the SATA devices should be set to the Enhanced Mode in BIOS.

**To start the computer with the R-Studio Emergency startup CD/DVD disc or any removable device,**


- 1 Make sure that the first startup device in the system BIOS is the CD/DVD drive or the removable device**  
Disable "Secure boot" in the system BIOS if your computer is certified to run Windows 8. Refer to your system documentation for details.
- 2 Insert the R-Studio Emergency startup CD/DVD disc and start your computer**

**☐ If you have a Mac computer**

To start a Mac computer with the **R-Studio Emergency** startup disk,


1. Insert a CD/DVD disc or connect a USB disk
2. Switch the Mac on.
3. While loading, press the **Option** key on the Mac keyboard (the **Alt** key if you use a non-Apple keyboard).

## The Options key




4. Select the **EFI boot disk** and press **Enter**.

## The R-Studio Emergency startup disk



**R-Studio Emergency** will start loading.

Then a startup screen will appear:



Select the **R-Studio Emergency GUI (Graphic Mode)** to run **R-Studio Emergency** in the graphic mode in which its user interface is similar to the Windows version. If **R-Studio Emergency** cannot run in this mode, restart the system in the Safe VGA mode (only VESA-compliant) which is compatible with most video cards and monitors. If it fails too, select the Text mode in which the **R-Studio Emergency** user interface is shown in the pseudo-graphic mode compatible with all video cards. The help describes this pseudo-graphic mode.

> **R-Studio Emergency** will start and its Device/Disk panel will appear

To start the computer with the **R-Studio Emergency** startup floppy disks,

**1 Make sure that the first startup device in the system BIOS is A (Floppy)**

Refer to your system documentation for details.

**2 Insert the first startup floppy disk and start your computer****> The following text will appear on the screen:**

```
Loading
Uncompressing ... OK, starting the kernel
VFS: Insert the second boot disk and press ENTER
```

**3 Insert the second disk and press ENTER.****> R-Studio Emergency will start and its Device/Disk panel will appear****Secure boot:**

It may be impossible to start a Windows 8 certified computer with the R-Studio Emergency startup disk without some additional actions. This happens because any computer should use a so-called "Secure boot" procedure to comply with Windows 8 hardware certification from Microsoft. In brief, this procedure prevents computer from booting into any operating system that isn't digitally signed with an appropriate digital signature. "Secure boot" is claimed to prevent unauthorized modification of the boot sector by bootkits, viruses, trojans, and other malicious software. To the date, only Windows 8, Windows Server 2012, and selected Linux distributions support this feature. As a side effect, it also prevents most LiveCDs, rescue disks (R-Studio and R-Drive Image included), and other OS from running.

Likely enough, the other requirement of Windows 8 hardware certification is to make it possible for the user to disable the Secure boot procedure. Those settings can be done through the system BIOS under the Boot options. Generally, it's enough to enable Legacy support in those options, but sometimes it may require additional actions. Please, refer to your system documentation to learn more about disabling/enabling Secure boot.


When Secure boot is disabled, it should be possible to start the computer with the R-Studio Emergency startup disk.

Please note that you should enable this feature back after using the startup disks because Windows 8 or Server 2012 may not start properly without the Secure boot feature enabled.

### **6.3.2 File Recovery**


**To recover files,****1 Select a partition on the Device/Disk panel on which the files to recover reside and press the Enter key****> R-Studio will change its panel showing the disk's folders/files structure****2 Select the file to recover on the Files View panel. Use the Tab key to switch between panes**

## Files View panel



- 3 Press the F2 key and specify the output folder on the Recover dialog box

## Recover dialog box



**External USB drives with the NTFS file system:** R-Studio Emergency can save recovered files on such disks if they are properly disconnected in a Windows system using the **Safely Remove Hardware** icon in the system tray or while shutting Windows down.

### [Searching for a File](#)

### [Mapping Network Drives](#)


### [Viewing object properties](#)

## 6.3.3 Searching for a File

To search for a file,

- 1 Select Find on the Tools menu (or press the Alt+F key)
- 2 Specify a file name or mask

## Find dialog box



## Look at dialog box

Deleted files:	If it is selected, <b>R-Studio</b> makes a search among deleted files/folders.
----------------	--

Existing files:	If it is selected, <b>R-Studio</b> makes a search among existing files/folders.
Files:	If it is selected, <b>R-Studio</b> includes files into a search.
Folders:	If it is selected, <b>R-Studio</b> includes folders into a search.

To find the next file corresponding to the specified file mask,


\* Press the Alt+N key

### 6.3.4 Disk Scan

To scan an object

- 1 Select an object on the Device/Disk panel and press the F6 key
- 2 Specify the required parameters on the Scan dialog box and press the Enter key

Scan dialog box




Scan dialog box

Start:	Sets the start point of the area to be scanned.
Size:	Sets the size of the area to be scanned.
Numbers in these fields can be in bytes or sectors. If no letters are after the numbers, <b>R-Studio</b> assumes the numbers in bytes. The following case-ignoring notation is possible:	
<b>b</b>	Bytes
<b>kb</b>	Kilobytes
<b>mb</b>	Megabytes
<b>gb</b>	Gigabytes
<b>tb</b>	Terabytes

- > When an object is scanned, it may be searched for files, and found files may be recovered the same way as for a regular object

### Scan results



### Found objects:

Extra Found Files	Entries of known file types have been found
Recognized1	Records and file entries are found for this partition
Recognized2	Only file entries are found for this partition
Recognized3	Only boot records are found for this partition

### To save scan information

- 1 Select an object with scan information
- 2 Press the Alt+D key and select Save Scan Information on the Drive menu
- 3 Specify the output folder and file name on the Save Scan Information dialog box

### [Mapping Network Drives](#)

### To open scan information

- 1 Select an object to which scan information is to be opened
- 2 Press the Alt+D key and select Open Scan Information on the Drive menu
- 3 Specify the folder and file name with the scan information on the Open Scan Information dialog box

### [Mapping Network Drives](#)

### To delete scan information

- 1 Select an object to which scan information is to be deleted
- 2 Press the Alt+D key and select Delete Scan Information on the Drive menu


## 6.3.5 Disk Images

### To create an image file

- 1 Select an object on the Device/Disk panel

- 2 Press the Alt+D key and select Create Plain Image File or Create Compressed Image File on the Drive menu

Create Image **dialog box**



Plain Image

If this option is selected, **R-Studio** will create a simple exact copy of the object. This image format is compatible with the previous versions of **R-Studio**.

Compressed Image

If this option is selected, **R-Studio** will create an image file compatible with the images created by **R-Drive Image**, but incompatible with the previous versions of **R-Studio**.

- 3 Specify the output folder and file name on the Create Image File **dialog box**

### [Mapping Network Drives](#)

To load an image file

- 1 Press the Alt+D key and select Open Image File on the Drive menu
- 2 Specify the folder and file name with the image on the Open Image File **dialog box**

### [Mapping Network Drives](#)

## 6.4 Using R-Studio Emergency as an Emergency Agent

**R-Studio Emergency Linux version** can be used as an emergency agent for **R-Studio**. Moreover, if you have a Mac computer, this is the only way to start it with **R-Studio Agent Emergency**.

To start the computer with the **R-Studio Emergency/Agent startup CD/DVD disc or any removable device**,

- 1 Make sure that the first startup device in the system BIOS is the CD/DVD drive or the removable device  
Disable "Secure boot" in the system BIOS if your computer is certified to run Windows 8. Refer to your system documentation for details.

- 2 Insert the **R-Studio Emergency startup CD/DVD disc or the removable device and start your computer**


#### **If you have a Mac computer**

To start a Mac computer with the **R-Studio Emergency startup disk**,

1. Insert a CD/DVD disc or connect a USB disk
2. Switch the Mac on.
3. While loading, press the **Option** key on the Mac keyboard (the **Alt** key if you use a non-Apple keyboard).




## The Options key



4. Select the **EFI boot disk** and press **Enter**.


## The R-Studio Emergency startup disk



**R-Studio Emergency** will start loading.

Then a startup screen will appear:

Startup Options



- 2 Select the **R-Studio Agent Emergency** to run **R-Studio Emergency** as an emergency agent.
- > **R-Studio Agent Emergency** will start and its prompt will appear

## R-Studio Emergency as an Emergency Agent

```

Loading rootagt...ok
Loading rconfig.bin...ok
Decompressing Linux... Parsing ELF... No relocation needed... done.
Booting the kernel.
-----
Booting R-Studio Agent Emergency. Please wait...
Waiting 8 seconds for PCMCIA devices to settle...
Booting R-Studio Agent Emergency. Now you may remove boot media.
-----
Querying DHCP to configure network interfaces...
Press ENTER within 10 seconds to configure them manually.
IP Address 192.168.1.14 was assigned for interface eth0 using DHCP protocol
Default gateway is 192.168.1.1 now
* Running R-Studio Agent Emergency 7.6.1116
* This product is licensed to: UNREGISTERED DEMO VERSION
# System: 2 x Intel(R) Core(TM)2 Duo CPU P7350 @ 2.00GHz, 1938 MHz
# OS: Linux 3.10.2 #1 SMP Fri Jan 16 12:46:09 EST 2015
? R-Studio Agent Emergency is not yet registered, 256KB file size recovery limit
  is implied until remotely registered
* R-Studio Agent Emergency started and ready to accept connections...
* R-Studio Agent Emergency is listening on IP(s): 192.168.1.14
* You may press 'E' to view EULA, press 'L' to view Third-Party Copyright Notice
  s and Disclaimers, press ENTER to start connection to remote R-Studio ...

```

### *If your network has a DHCP server*

The computer running R-Studio Agent Emergency will be assigned an IP address automatically

A prompt with a computer address will appear. You need to remember it to access the computer via network.

### *If your network does not have a DHCP server*

You need to configure the interfaces and IP addresses manually.

1. Press Enter to start configuring the settings. A prompt to select an interface will appear. Enter the selected interface name and press **Enter**.
2. A prompt to enter its IP address and optional subnet mask will appear. Enter the IP address and optional subnet mask and press **Enter**.

### Network Setting Configuration

```

Loading rm_pcard.b32...ok
Loading rm_other.b32...ok
Loading rootagt...ok
Loading rconfig.bin...ok
Decompressing Linux... Parsing ELF... No relocation needed... done.
Booting the kernel.
-----
Booting R-Studio Agent Emergency. Please wait...
Waiting 8 seconds for PCMCIA devices to settle...
Booting R-Studio Agent Emergency. Now you may remove boot media.
-----
Querying DHCP to configure network interfaces...
Press ENTER within 10 seconds to configure them manually.
-----
[ List of Interfaces ]
-----
Name      IP Address  NETMASK  Vendor
-----
eth0      Unconfigured  Intel(R) PRO/100+
# Enter interface name, 'gw' for default gateway or just press ENTER to finish
eth0
#># Enter IP Address and optional NETMASK delimited by space
192.168.1.14 255.255.255.0
#>

```

3. A prompt to configure another interface, gateway, or to finish configuring the interfaces will appear. Enter **gw**, enter the IP address of the gateway, and press **Enter**.

### Network Setting Configuration

```

# Enter interface name, 'gw' for default gateway or just press ENTER to finish
eth0
#># Enter IP Address and optional NETMASK delimited by space
192.168.1.14 255.255.255.0
#>
-----
[ List of Interfaces ]
-----
Name      IP Address  NETMASK  Vendor
-----
eth0      192.168.1.14  255.255.255.0  Intel(R) PRO/100+
gw        Unconfigured  Default gateway
# Enter interface name, 'gw' for default gateway or just press ENTER to finish
gw
#># Enter default gateway IP Address
192.168.1.1
#>
-----
[ List of Interfaces ]
-----
Name      IP Address  NETMASK  Vendor
-----
eth0      192.168.1.14  255.255.255.0  Intel(R) PRO/100+
gw        192.168.1.1    Default gateway
# Enter interface name, 'gw' for default gateway or just press ENTER to finish

```

4. Press **Enter** to finish configuring the interfaces, or enter the name of the next interface to configure.

- > **R-Studio Agent Emergency will show a prompt that is ready to accept connections**

### R-Studio Emergency as an Emergency Agent

```
# Enter interface name, 'gw' for default gateway or just press ENTER to finish
gw
#># Enter default gateway IP Address
192.168.1.1
#>
----- [ List of Interfaces ] -----
Name      IP Address  NETMASK  Vendor
-----
eth0      192.168.1.14 255.255.255.0 Intel(R) PRO/100+
gw        192.168.1.1  Default gateway
-----
# Enter interface name, 'gw' for default gateway or just press ENTER to finish

#>* Running R-Studio Agent Emergency 7.6.1116
# This product is licensed to: UNREGISTERED DEMO VERSION
# System: 2 x Intel(R) Core(TM)2 Duo CPU P7350 @ 2.00GHz, 1364 Mhz
# OS: Linux 3.18.2 #1 SMP Fri Jan 16 12:46:09 EST 2015
? R-Studio Agent Emergency is not yet registered, 256KB file size recovery limit
  is implied until remotely registered
# R-Studio Agent Emergency started and ready to accept connections...
# R-Studio Agent Emergency is listening on IP(s): 192.168.1.14
# You may press 'E' to view EULA, press 'L' to view Third-Party Copyright Notices
  and Disclaimers, press ENTER to start connection to remote R-Studio ...
```

Now the computer may be accessed by **R-Studio** via network.

### Secure boot:

It may be impossible to start a Windows 8 certified computer with the R-Studio Emergency startup disk without some additional actions. This happens because any computer should use a so-called "Secure boot" procedure to comply with Windows 8 hardware certification from Microsoft. In brief, this procedure prevents computer from booting into any operating system that isn't digitally signed with an appropriate digital signature. "Secure boot" is claimed to prevent unauthorized modification of the boot sector by bootkits, viruses, trojans, and other malicious software. To the date, only Windows 8, Windows Server 2012, and selected Linux distributions support this feature. As a side effect, it also prevents most LiveCDs, rescue disks (R-Studio and R-Drive Image included), and other OS from running.

Likely enough, the other requirement of Windows 8 hardware certification is to make it possible for the user to disable the Secure boot procedure. Those settings can be done through the system BIOS under the Boot options. Generally, it's enough to enable Legacy support in those options, but sometimes it may require additional actions. Please, refer to your system documentation to learn more about disabling/enabling Secure boot.

When Secure boot is disabled, it should be possible to start the computer with the R-Studio Emergency startup disk.

Please note that you should enable this feature back after using the startup disks because Windows 8 or Server 2012 may not start properly without the Secure boot feature enabled.

### To connect to R-Studio's computer,

- 1 **Press the Enter key and enter the IP address of the computer where R-Studio is running as** IPaddress:port.

The default port is 8080, and you don't have to specify it.

- 2 Enter the password if required, and press the Enter key.
- > When the connection is established successfully, R-Studio Agent Emergency will notify you about this.

### R-Studio Emergency as an Emergency Agent

```
Waiting 8 seconds for PCMCIA devices to settle...
Booting R-Studio Agent Emergency. Now you may remove boot media.
-----
Quering DHCP to configure network interfaces...
Press ENTER within 10 seconds to configure them manually.
IP Address 192.168.1.14 was assigned for interface eth0 using DHCP protocol
Default gateway is 192.168.1.1 now
* Running R-Studio Agent Emergency 7.6.1116
* This product is licensed to: UNREGISTERED DEMO VERSION
# System: 2 x Intel(R) Core(TM)2 Duo CPU P7350 @ 2.00GHz, 1930 MHz
# OS: Linux 3.18.2 #1 SMP Fri Jan 16 12:46:09 EST 2015
? R-Studio Agent Emergency is not yet registered, 256KB file size recovery limit
  is implied until remotely registered
* R-Studio Agent Emergency started and ready to accept connections...
* R-Studio Agent Emergency is listening on IP(s): 192.168.1.14
* You may press 'E' to view EULA, press 'L' to view Third-Party Copyright Notice
  s and Disclaimers, press ENTER to start connection to remote R-Studio ...

# Enter R-Studio IP address or just press ENTER to cancel>192.168.1.10:8080
# Enter password or just press ENTER to connect without one>
Connection with 192.168.1.10:8080 is established successfully.
* R-Studio Agent Emergency is listening on IP(s): 192.168.1.14
* You may press 'E' to view EULA, press 'L' to view Third-Party Copyright Notice
  s and Disclaimers, press ENTER to start connection to remote R-Studio ...
```

## 6.5 R-Studio Emergency Technical Information

[Properties and Text/Hexadecimal Viewer](#)

[Network Drives](#)

[Log](#)

[Devices to Store Recovered Files](#)

[R-Studio Emergency](#)

[R-Studio Emergency](#)

[Contact Information and Technical Support](#)

[Installing R-Studio Emergency Startup Media Creator](#)

[Creating Startup Disks](#)

[R-Studio Emergency Operation](#)

[Starting a Computer with the R-Studio Emergency Startup Disks](#)

[File Recovery](#)

[Searching for a File](#)

[Disk Scan](#)

[Disk Images](#)

[Using R-Studio Emergency as Emergency Agent](#)

[Hardware Compatibility List](#)

### 6.5.1 Properties and Text/Hexadecimal Viewer

To view object properties,

- 1 Select an object
- 2 Press the F7 key

## To view an object

- 1 Select an object
- 2 Press the **F3** key
- 3 Press the **F6** key to view and select file attributes  
Press the **Esc** key to close the viewer.

## 6.5.2 Network Drives


### To map a network drive,

- 1 On a dialog box with Map Network Drive, press the **Alt+M** key
- > The Querying DHCP message will appear

If the network has a DHCP server, the computer will obtain an IP address automatically. A list of adapters and their IP addresses will appear on the Network Adapters dialog box.


If the network does not have a DHCP server, select a network adapter on the Network Adapters dialog box and press the **F4** key. Enter the IP address and network mask and press the **Enter** button.

#### Network Addresses dialog box



- 2 Select a configured network adapter and press the **Enter** key
- 3 Enter the required information on the Map Network Drive message message

#### Map Network dialog box



Server IP Address:	IP address of the computer where the network drive is to reside.
Server Share Name:	Name of the shared folder where the network drive is to reside.
Login:	Username of a user on the computer where the network drive is to reside.
Password:	User's password on the computer where the network drive is to reside.

For the network drive's path //SERVER/Net\_Drive,

**Server IP address:** The IP address of the `SERVER` computer (192.168.1.20)

**Server share name:** `Net_Drive`.

> **The mounted network disk will appear**

**To disconnect a mounted network drive**

- 1 Select a mounted network drive
- 2 Switch to the Disconnect button and press the Enter key

### 6.5.3 Log

**To clear log information**

- \* Select Clear Log on the Tools menu

**To save log information to a file**

- \* Select Save Log To File on the Tools menu

### 6.5.4 Devices to Store Recovered Files

**R-Studio Emergency** can write recovered files to the following devices:

- FAT devices such as USB sticks, memory cards, and other similar devices. Such devices are inexpensive and easily available, they can be fully accessed by all operating systems, but they have one important drawback: they cannot store files larger than 2GB. So, if you plan to recover large video files, this is not your option.
- exFAT devices such as large USB sticks and memory cards, external hard disks, and other similar devices. They are fully accessed by all operating systems. Unlike FAT devices, they don't have the 2GB file size limit.
- NTFS disks (primarily used in Windows computers).

Access without any third-party software:

Windows computers: full.

Mac computers: read.

Linux computers: full.

- HFS/HFS+ disks (used in Mac computers).

Access without any third-party software:

Windows computers: no.

Mac computers: full. Some access problems may appear for files written by **R-Studio Emergency**.

Linux computers: full. Some access problems may appear for files written by **R-Studio Emergency**.

- Ext2/3/4 disks (used in Linux computers).

Access without any third-party software:

Windows computers: no.

Mac computers: no

Linux computers: full.

- XFS disks (used in Linux computers).

Access without any third-party software:

Windows computers: no.

Mac computers: no


Linux computers: full.

- Network disks. Such disks may be on other network computers or NAS devices. See the [Network Drives](#) page for more details

### How to solve file access problems on Macs

Finder in the OSX system shows such inaccessible folders and files in the following way:


#### Inaccessible folders in Finder



To get access to such data, do the following:

1. Under an administrator account, right-click the folder and select **Get Info** on the contextual menu.


#### Info of an inaccessible folder



Click the **Lock** icon in the **Sharing & Permissions** section to unlock the folder properties. The system will ask you for the account password.


2. Click the **Privilege** column and select **Read & Write** on the contextual menu.

### Setting the access rights for the folder



3. If this is a folder with other folders and files, click the **Properties** icon and select **Apply to enclosed items**.

### Setting access rights for enclosed items in the folder



Then click the **Lock** icon to lock the properties back.

## 6.6 R-Studio Emergency Hardware Compatibility List

R-Studio Emergency supports the following hardware devices:

### Data Storage Devices

#### Serial ATA and Parallel ATA drivers

ACPI firmware driver for PATA  
 AHCI SATA  
 ALi PATA  
 AMD/Nvidia PATA  
 ARTOP 6210/6260 PATA  
 ARTOP/Acard ATP867X PATA  
 ATI PATA  
 CMD / Silicon Image 680 PATA  
 CMD640 PCI PATA  
 CMD64x PATA  
 CS5510/5520 PATA  
 CS5530 PATA  
 CS5535 PATA

### Networking Devices

#### Ethernet (10 or 100Mbit)

3c501 `EtherLink`  
 3c503 `EtherLink II`  
 3c505 `EtherLink Plus`  
 3c507 `EtherLink 16`  
 3c509/3c529 (MCA)/3c579 `EtherLink III`  
 3c515 ISA `Fast EtherLink`  
 3c590/3c900 series (592/595/597)  
 `Vortex/Boomerang`  
 3cr990 series `Typhoon`  
 AMD 8111 (new PCI lance)  
 AMD LANCE and PCnet (AT1500 and NE2100)  
 AMD PCnet32 PCI  
 AT1700/1720



CS5536 PATA  
Compaq Triflex PATA  
Cypress CY82C693 PATA  
EFAR SLC90E66  
Generic ATA  
HPT 343/363 PATA  
HPT 366/368 PATA  
HPT 370/370A/371/372/374/302 PATA  
HPT 372N/302N PATA  
IT8211/2 PATA  
IT8213 PATA  
Initio 162x SATA  
Intel ESB, ICH, PIIX3, PIIX4 PATA/SATA  
Intel PATA MPIIX  
Intel PATA old PIIX  
Intel SCH PATA  
JMicron PATA  
Legacy ISA PATA  
Marvell PATA support via legacy mode  
Marvell SATA  
NETCELL Revolution RAID  
NVIDIA SATA  
Nat Semi NS87410 PATA  
Nat Semi NS87415 PATA  
Ninja32/Delkin Cardbus ATA  
OPTI FireStar PATA  
OPTI621/6215 PATA  
Older Promise PATA controller  
PCMCIA PATA  
Pacific Digital ADMA  
Pacific Digital SATA QStor  
Platform AHCI SATA  
Promise PATA 2027x  
Promise SATA SX4  
Promise SATA TX2/TX4  
QDI VLB PATA  
RADISYS 82600 PATA  
RDC PATA  
SC1200 PATA  
SERVERWORKS OSB4/CSB5/CSB6/HT1000  
PATA  
Adaptec Starfire/DuraLAN  
Ansel Communications EISA 3200  
Apricot Xen-II on board Ethernet  
Atheros L2 Fast Ethernet  
Broadcom 440x/47xx ethernet  
CS89x0  
Cabletron E21xx  
DECchip Tulip (dc2114x) PCI  
Dave ethernet support (DNET)  
Davicom DM910x/DM980x  
Early DECchip Tulip (dc2104x) PCI  
EtherExpress 16  
EtherExpressPro support/EtherExpress 10 (i82595)  
Generic DECchip & DIGITAL EtherWORKS  
PCI/EISA  
HP 10/100VG PCLAN (ISA, EISA, PCI)  
HP PCLAN (27245 and other 27xxx series)  
HP PCLAN+ (27247B and 27252A)  
ICL EtherTeam 16i/32  
Intel(R) PRO/100+  
LP486E on board Ethernet  
Myson MTD-8xx PCI Ethernet  
NE2000/NE1000  
NI5010  
NI5210  
NI6510  
National Semiconductor DP8381x series PCI  
Ethernet  
OpenCores 10/100 Mbps Ethernet MAC  
PCI NE2000 and clones support (see help)  
RDC R6040 Fast Ethernet Adapter  
RealTek RTL-8129/8130/8139 PCI Fast Ethernet  
Adapter  
RealTek RTL-8139 C+ PCI Fast Ethernet Adapter  
SEEQ8005  
SMC 9194  
SMC EtherPower II  
SMC Ultra  
SMSC LAN9420 PCI ethernet adapter  
SiS 900/7016 PCI Fast Ethernet Adapter  
Silan SC92031 PCI Fast Ethernet Adapter driver

ServerWorks Frodo / Apple K2 SATA  
 SiS 964/965/966/180 SATA  
 SiS PATA  
 Silicon Image 3124/3132 SATA  
 Silicon Image SATA  
 ULi Electronics SATA  
 VIA PATA  
 VIA SATA  
 VITESSE VSC-7174 / INTEL 31244 SATA  
 Winbond SL82C105 PATA  
 Winbond W83759A VLB PATA

### SCSI low-level drivers

3ware 5/6/7/8xxx ATA-RAID  
 3ware 97xx SAS/SATA-RAID  
 3ware 9xxx SATA-RAID  
 7000FASST SCSI  
 ACARD SCSI  
 ARECA (ARC11xx/12xx/13xx/16xx)  
 SATA/SAS RAID Host Adapter  
 Adaptec AACRAID  
 Adaptec AHA152X/2825  
 Adaptec AHA1542  
 Adaptec AIC79xx U320  
 Adaptec AIC7xxx  
 Adaptec AIC7xxx Fast -> U160  
 Adaptec AIC94xx SAS/SATA  
 Adaptec I2O RAID  
 AdvanSys SCSI  
 Always IN2000 SCSI  
 BusLogic SCSI  
 DMX3191D SCSI  
 DTC3180/3280 SCSI  
 EATA ISA/EISA/PCI (DPT and generic  
 EATA/DMA-compliant boards)  
 Emulex LightPulse Fibre Channel Support  
 Future Domain 16xx SCSI/AHA-2920A  
 Generic NCR5380/53c400 SCSI MMIO  
 Generic NCR5380/53c400 SCSI PIO  
 HP Smart Array SCSI driver  
 HighPoint RocketRAID 3xxx/4xxx Controller

Sun Cassini  
 Sun GEM  
 Sun Happy Meal 10/100baseT  
 Sundance Alta  
 TI ThunderLAN  
 ULi M526x controller  
 VIA Rhine  
 WD80\*3  
 Winbond W89c840 Ethernet  
 Zenith Z-Note  
 nForce Ethernet

### Ethernet (1000 Mbit)

Alteon AceNIC/3Com 3C985/NetGear GA620  
 Gigabit  
 Atheros L1C Gigabit Ethernet  
 Atheros L1E Gigabit Ethernet  
 Atheros/Attansic L1 Gigabit Ethernet  
 Broadcom CNIC  
 Broadcom NetXtremeII  
 Broadcom Tigon3  
 DL2000/TC902x-based Gigabit Ethernet  
 IP1000 Gigabit Ethernet  
 Intel(R) 82575/82576 PCI-Express Gigabit Ethernet  
 Intel(R) 82576 Virtual Function Ethernet  
 Intel(R) PRO/1000 Gigabit Ethernet  
 Intel(R) PRO/1000 PCI-Express Gigabit Ethernet  
 JMicron(R) PCI-Express Gigabit Ethernet  
 National Semiconductor DP83820  
 New SysKonnnect GigaEthernet  
 Packet Engines Hamachi GNIC-II  
 Packet Engines Yellowfin Gigabit-NIC  
 QLogic QLA3XXX Network Driver Support  
 Realtek 8169 gigabit ethernet  
 SiS190/SiS191 gigabit ethernet  
 SysKonnnect Yukon2  
 VIA Velocity

### Ethernet (10000 Mbit)

Broadcom NetXtremeII 10Gb  
 Chelsio 10Gb Ethernet  
 Chelsio Communications T3 10Gb Ethernet

IBM Power Linux RAID adapter  
 IBM ServeRAID  
 Initio 9100U(W)  
 Initio INI-A100U2W  
 Intel/ICP (former GDT SCSI Disk Array) RAID Controller  
 LSI Logic Legacy MegaRAID Driver  
 LSI Logic Management Module  
 LSI Logic MegaRAID Driver  
 LSI Logic MegaRAID SAS RAID Module  
 LSI MPT Fusion SAS 2.0 Device Driver  
 Marvell 88SE64XX/88SE94XX SAS/SATA  
 NCR53c406a SCSI  
 PAS16 SCSI  
 PMC SIERRA Linux MaxRAID adapter  
 PMC-Sierra SPC 8001 SAS/SATA Based Host Adapter driver  
 Promise SuperTrak EX Series  
 QLogic ISP4XXX host adapter family  
 QLogic QLA2XXX Fibre Channel Support  
 Qlogic FAS SCSI  
 Qlogic QLA 1240/1x80/1x160 SCSI  
 SYM53C8XX Version 2 SCSI  
 Symbios 53c416 SCSI  
 Tekram DC390(T) and Am53/79C974 SCSI  
 Tekram DC395(U/UW/F) and DC315(U) SCSI  
 Trantor T128/T128F/T228 SCSI  
 UltraStor 14F/34F  
 UltraStor SCSI  
 VMware PVSCSI driver  
 Workbit NinjaSCSI-32Bi/UDE

### USB support

Cypress C67x00 HCD  
 Datafab Compact Flash Reader  
 Freecom USB/ATAPI Bridge  
 ISD-200 USB/ATA Bridge  
 ISP 1760 HCD  
 ISP116X HCD  
 ISP1362 HCD  
 Lexar Jumpshot Compact Flash Reader

Chelsio Communications T4 Ethernet  
 Cisco VIC Ethernet NIC Support  
 Intel(R) 10GbE PCI Express adapters  
 Intel(R) PRO/10GbE  
 Mellanox Technologies 10Gbit Ethernet  
 Myricom Myri-10G Ethernet  
 NetXen Multi port (1/10) Gigabit Ethernet NIC  
 Neterion X3100 Series 10GbE PCIe Server Adapter  
 QLOGIC QLCNIC 1/10Gb Converged Ethernet NIC Support  
 QLogic QLGE 10Gb Ethernet Driver Support  
 S2IO 10GbE XFrame NIC  
 ServerEngines' 10Gbps NIC - BladeEngine  
 Solarflare Solarstorm SFC4000/SFC9000-family  
 Sun Neptune 10Gbit Ethernet  
 Tehuti Networks 10G Ethernet

### Token Ring driver support

3Com 3C359 Token Link Velocity XL adapter  
 Generic TMS380 PCI  
 Generic TMS380 Token Ring ISA/PCI adapter  
 IBM Lanstreamer chipset PCI adapter  
 IBM Olympic chipset PCI adapter  
 IBM Tropic chipset based adapter  
 Madge Smart 16/4 PCI Mk2  
 Proteon ISA  
 SMC ISA/MCA adapter  
 SysKconnect TR4/16 ISA

### USB Network Adapters

ASIX AX88xxx Based USB 2.0 Ethernet Adapters  
 CDC EEM  
 CDC Ethernet support (smart devices such as cable modems)  
 Davicom DM9601 based USB 1.1 10/100 ethernet devices  
 GeneSys GL620USB-A based cables  
 Host for RNDIS and ActiveSync devices  
 MosChip MCS7830 based Ethernet adapters  
 NetChip 1080 based cables (Laplink, ...)  
 Prolific PL-2301/2302 based cables

OXU210HP HCD  
Olympus MAUSB-10/Fuji DPC-R1  
R8A66597 HCD  
SL811HS HCD  
SanDisk SDDR-09 (and other SmartMedia,  
including DPCM)  
SanDisk SDDR-55 SmartMedia  
USB 2.0  
USB Mass Storage  
USB Monitor  
USBAT/USBAT02-based storage  
xHCI HCD (USB 3.0)

**Block devices**

Compaq SMART2  
Compaq Smart Array 5xxx  
Mylex DAC960/DAC1100 PCI RAID Controller  
Normal floppy disk  
Promise SATA SX8

**IEEE 1394 (FireWire) support**

Legacy alternative FireWire driver stack  
Storage devices (SBP-2 protocol)

**PCMCIA network device support**

3Com 3c574 PCMCIA  
3Com 3c589 PCMCIA  
Asix AX88190 PCMCIA  
COM20020 ARCnet PCMCIA  
Fujitsu FMV-J18x PCMCIA  
NE2000 compatible PCMCIA  
New Media PCMCIA  
SMC 91Cxx PCMCIA  
Xircom 16-bit PCMCIA

**Other devices**

Microsoft Hyper-V Utilities driver  
Microsoft Hyper-V client drivers  
Microsoft Hyper-V virtual block driver  
Microsoft Hyper-V virtual network driver  
Microsoft Hyper-V virtual storage driver

SMSC LAN95XX based USB 2.0 10/100 ethernet  
devices  
Sharp Zaurus (stock ROMs) and compatible  
Simple USB Network Links (CDC Ethernet subset)  
USB CATC NetMate-based Ethernet device  
USB KLSI KL5USB101-based ethernet device  
USB Pegasus/Pegasus-II based ethernet device  
USB RTL8150 based ethernet device

## VII R-Studio Agent Emergency

**R-Studio Agent Emergency** is a tool that allows you to start a network computer with a damaged startup disk and recover data stored on its hard drives. Then restored data can be transferred to a working computer via the network.

It works very simple: Just start the computer with the **R-Studio Agent Emergency** startup disk(s) and, if necessary, manually configure a network interface for **R-Studio Agent Emergency**. When started, the computer and its hard drives can be accessed by **R-Studio** installed on another computer on the network.

### [Contact Information and Technical Support](#)

### [Installing R-Studio Agent Emergency Startup Media Creator](#)

### [Creating Startup Disks](#)

### [Starting a Computer with the R-Studio Agent Emergency Startup Disk](#)

### [Hardware Compatibility List](#)

#### [Disk Controllers](#)

#### [Network Cards](#)

## 7.1 Contact Information and Technical Support

To obtain the latest version of **R-Studio Agent Emergency**, go to:

Product Site: <http://www.r-tt.com>

Sales Department: [sales@r-tt.com](mailto:sales@r-tt.com)

**R-Studio** Technical Support Team is available 24 hours a day, seven days a week, and has an average response time less than 4 hours.

Tech. Support: [support@r-tt.com](mailto:support@r-tt.com)

Send your support request to: [http://www.r-tt.com/Support\\_request.html](http://www.r-tt.com/Support_request.html)

## 7.2 Installing R-Studio Agent Emergency Startup Media Creator

**You must have administrative privileges to install R-Studio Agent Emergency Startup Media Creator.**

If you are not sure whether you have such privileges, you almost certainly do not have them. Contact your system administrator for assistance.

1. Run the setup file.
2. Follow the on-screen instructions.

You may create startup disks even before the installation ends.

## 7.3 Creating Startup Disks

You need to create either

- A startup CD/DVD disc. You may create an ISO image, or write the disc directly from **R-Studio** Emergency Startup Media Creator, if there is a CD/DVD recorder in your system.

or

- A startup FAT/FAT32 removable device recognized by your system as a bootable one. The total available size of the device should be more than 10 MB.

OR

- 4 formatted floppy disks

Check the [Hardware Compatibility List](#).

When **R-Studio Agent Emergency Startup Media Creator** starts, its Welcome dialog box appears:


Welcome to **R-Studio Agent** Emergency Startup Media Creator **dialog box**

Welcome **dialog box**



click the **Next** button to see the list of all devices on which startup disks may be created.

Startup media type selection **dialog box**




To create a startup CD/DVD disc directly on your CD/DVD writer (if present):


- 1 Run **R-Studio Agent Emergency**
- 2 Select the **CD/DVD writer** on the Startup media type selection **dialog box** and click the **Next** button
- 3 Read and accept the **License Agreement** and enter the **R-Studio Agent** registration key on the **R-Studio Agent Emergency Activation dialog box** and click the **Next** button

**Note:** You should enter the registration key of **R-Studio Agent**, not **R-Studio** itself.

## R-Studio Agent Emergency License Agreement dialog box




## R-Studio Agent Emergency Activation dialog box



if you do not enter the registration key, **R-Studio Agent** Emergency will work in the Demo mode. You may enter the key later when **R-Studio Agent** Emergency and **R-Studio** establish a connection


### 4 Insert a blank CD/DVD disk into the CD/DVD recorder and click the Next button

## Insert media disc dialog box



- > **R-Studio Agent Emergency Startup Media Creator** will start creating the startup CD/DVD disc showing the progress on the **Creating startup media dialog box**

Creating startup media **dialog box**



When **R-Studio Agent Emergency Startup Media Creator** finishes creating the startup CD/DVD disc, the **R-Studio Agent Emergency Startup Media Creation is Finished message** will appear

You may either exit **R-Studio Emergency Startup Media Creator** by clicking the **Finish** button or create another startup media by clicking the **Back** button.

**R-Studio Agent Emergency Startup Media Creation is Finished message**



**To create an ISO image of a startup CD/DVD disc**

- 1 **Run R-Studio Agent Emergency**
- 2 **Select ISO Image for a startup CD/DVD on the R-Studio Agent Emergency Startup Media Creator dialog box and click the Next button**
- 3 **Read and accept the License Agreement and enter the R-Studio Agent registration key on the R-Studio Agent Emergency Activation dialog box and click the Next button**

**Note:** You should enter the registration key of **R-Studio Agent**, not **R-Studio** itself.

if you do not enter the registration key, **R-Studio Agent** Emergency will work in the Demo mode. You may enter the key later when **R-Studio Agent** Emergency and **R-Studio** establish a connection.

- 4 **Select a place and file name for the ISO image of the startup CD/DVD and click the Save button**
- > **When R-Studio Bootable Startup Media Creator finishes writing the file with the ISO image, the R-Studio Agent Emergency Startup Media Creation is Finished message will appear**

You may either exit **R-Studio Bootable Startup Media Creator** by clicking the **Finish** button or create another startup media by clicking the **Back** button.



## R-Studio Agent Emergency Startup Media Creation is Finished dialog box




### 5 Create the startup CD/DVD using your favorite CD/DVD creation software

Load the created ISO image into the CD/DVD creation software. Consult documentation for the software for details.

## To create a startup FAT/FAT32 removable device

- 1 Run R-Studio Agent Emergency
- 2 Select the removable device on the Startup media type selection dialog box and click the Next button
- 3 Read and accept the License Agreement and enter the registration key on the R-Studio Agent Emergency Activation dialog box and click the Next button
- 4 Check that the correct FAT/FAT32-formatted device is selected and click the Next button

Confirm device selection dialog box




- > R-Studio Agent Emergency Startup Media Creator will start creating the startup USB disk showing the progress on the Creating startup media dialog box

When R-Studio Agent Emergency Startup Media Creator finishes creating the startup device, the R-Studio Agent Emergency Startup Media Creation is Finished message will appear

You may either exit R-Studio Emergency Startup Media Creator by clicking the Finish button or create another startup media by clicking the Back button.

## R-Studio Agent Emergency Startup Media Creation is Finished dialog box




### To create floppy disks:

You will need 4 formatted floppy disks.


- 1 **Run R-Studio Agent Emergency**
- 2 **Select Floppy Disk for the startup floppy disk on the R-Studio Agent Emergency Startup Media Creator dialog box and click the Next button**
- 3 **Enter the registration information and number on the Registration dialog box and click the Next button**  
If you leave all the field blank, **R-Studio Agent Emergency** will work with the **Demo-version limitations**
- 4 **Insert the floppy disk and click the Next button on the Insert floppy dialog box**

### Insert floppy dialog box




- > **R-Studio Agent Emergency Startup Media Creator will start creating the startup floppy disk showing the progress on the Creating startup media dialog box**

### Creating startup media dialog box




- 5 **Insert the second floppy disk and click the OK button when the Please insert formatted diskette #2 into drive A: message will appear**



Do it with the next 2 floppy disks.

- > **When R-Studio Startup Media Creator finishes creating the startup floppy disk, the R-Studio Agent Emergency Startup Media Creation is Finished message will appear. You may either exit R-Studio Startup Media Creator by clicking the Finish button or create another startup media by clicking the Back button.**

**R-Studio Agent Emergency Startup Media Creation is Finished dialog box**



## 7.4 Starting a Computer with the R-Studio Agent Emergency Startup Disk

We recommended that you print out this help page and have the hardcopy on hand while you are performing this action.

Before you start the computer you should be aware that your network has a DHCP server or you know the computer's IP address and network mask.

If there is a non-IDE disk controller in your system, or you plan to use network disks or external hardware devices, first check the [Hardware Compatibility List](#).

If you plan to use any external device, turn it on before starting the system.

If the motherboard in your computer supports the Serial ATA (SATA) devices, but IDE disks are also present, only the SATA devices should be set to the Enhanced Mode in BIOS.

**To start the computer with the R-Studio Agent Emergency startup disks**

- 1 **Make sure that the first startup device in the system BIOS is the device from which you plan to start your computer (a CD/DVD drive or A (Floppy))**  
Disable "Secure boot" in the system BIOS if your computer is certified to run Windows 8. Refer to your system documentation for details. Refer to your system documentation for details.
- 2 **Insert the R-Studio Agent Emergency startup CD/DVD disc, a removable device, or the first floppy disk and start your computer**
- > **R-Studio Agent Emergency will start and its prompt will appear**  
If you start your computer with floppy disks, you'll see prompts to insert a next floppy disk.

```
-----
Booting R-Studio Emergency. Please wait...
```

```

Waiting 8 seconds for PCMCIA devices to settle
Booting R-Studio Agent Emergency. Now you may remove floppy.
-----
Querying DHCP to configure network interfaces...
Press ENTER within 10 seconds to configure them manually.

```

***If your network has a DHCP server***

**The computer running R-Studio Agent Emergency will be assigned an IP address automatically**

A prompt with a computer address will appear. You need to remember it to access the computer via network.

***If your network does not have a DHCP server***

You need to configure the interfaces and IP addresses manually.

1. A prompt to select an interface will appear. Enter the selected interface name and press **Enter**.
2. A prompt to enter its IP address and optional subnet mask will appear. Enter the IP address and optional subnet mask and press **Enter**.

```

-----[ List of
Interfaces ]-----
Name          IP Address          NETMASK          Vendor
-----
re0           Unconfigured              RealTek
8139C+
-----
# Enter interface name, 'gw' for default gateway or just press
ENTER to finish
#>re0
# Enter IP address and optional NETMASK delimited by space
#>192.168.0.10 255.255.255.0

```

3. A prompt to configure another interface, gateway, or to finish configuring the interfaces will appear. Enter gw, enter the IP address of the gateway, and press **Enter**.

```

-----[ List of
Interfaces ]-----
Name          IP Address          NETMASK          Vendor
-----
re0           Unconfigured              RealTek
8139C+
-----
# Enter interface name, 'gw' for default gateway or just press
ENTER to finish
#>re0
# Enter IP address and optional NETMASK delimited by space
#>192.168.0.10 255.255.255.0

```

```

-----[ List of
Interfaces ]-----
Name          IP Address          NETMASK          Vendor
-----

```

```

re0          192.168.0.10          255.255.255.0          RealTek
8139C+
gw          Unconfigured          Default
gateway
-----
# Enter interface name, 'gw' for default gateway or just press
ENTER to finish
#>gw
# Enter default gateway IP Address
#>192.168.0.1

-----[ List of
Interfaces ]-----
Name          IP Address          NETMASK          Vendor
-----
re0          192.168.0.10          255.255.255.0          RealTek
8139C+
gw          192.168.0.1          Default
gateway
-----
# Enter interface name, 'gw' for default gateway or just press
ENTER to finish
#>

```

4. Press **Enter** to finish configuring the interfaces, or enter the name of the next interface to configure.

> **R-Studio Agent Emergency will show a prompt that is ready to accept connections**

```

* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start to remote R-Studio...

```

Now the computer may be accessed by **R-Studio** via network.

### Secure boot:

It may be impossible to start a Windows 8 certified computer with the R-Studio Agent Emergency startup disk without some additional actions. This happens because any computer should use a so-called "Secure boot" procedure to comply with Windows 8 hardware certification from Microsoft. In brief, this procedure prevents computer from booting into any operating system that isn't digitally signed with an appropriate digital signature. "Secure boot" is claimed to prevent unauthorized modification of the boot sector by bootkits, viruses, trojans, and other malicious software. To the date, only Windows 8, Windows Server 2012, and selected Linux distributions support this feature. As a side effect, it also prevents most LiveCDs, rescue disks (R-Studio and R-Drive Image included), and other OS from running.

Likely enough, the other requirement of Windows 8 hardware certification is to make it possible for the user to disable the Secure boot procedure. Those settings can be done through the system BIOS under the Boot options. Generally, it's enough to enable Legacy support in those options, but sometimes it may require additional actions. Please, refer to your system documentation to learn more about disabling/enabling Secure boot.

When Secure boot is disabled, it should be possible to start the computer with the R-Studio Agent Emergency startup disk.

Please note that you should enable this feature back after using the startup disks because Windows 8 or Server 2012 may not start properly without the Secure boot feature enabled.

### Starting a Connection from R-Studio Agent Emergency

When you need to connect **R-Studio** and **R-Studio Agent Emergency** over the Internet, it may be necessary to start the connection from the computer where **R-Studio Agent Emergency** is running.

To connect to **R-Studio's** computer,

- 1 Press the **Enter** key and enter the IP address of the computer where **R-Studio** is running as IPaddress:port.

```
* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start connection to remote R-Studio...
# Enter R-Studio IP address or just press ENTER to cancel>
192.168.0.25:80
```

The default port is 8080, and you don't have to specify it.

- 2 Enter the password if required, and press the **Enter** key.

```
* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start connection to remote R-Studio...
# Enter R-Studio IP address or just press ENTER to cancel>
192.168.0.25:80
# Enter password or just press ENTER to connect without
one>PaSsWoRd1234
```

- > When the connection is established successfully, **R-Studio Agent Emergency** will notify you about this.

```
* R-Studio Agent started and ready to accept connections...
* You may press ENTER to start connection to remote R-Studio...
# Enter R-Studio IP address or just press ENTER to cancel>
192.168.0.25:80
# Enter password or just press ENTER to connect without
one>PaSsWoRd1234
Connection with 192.168.0.25:80 is established successfully.
```

## 7.5 R-Studio Agent Emergency Hardware Compatibility List

### [Disk Controllers](#)

### [Network Cards](#)

### [R-Studio Agent Emergency](#)

#### [Contact Information and Technical Support](#)

#### [Installing R-Studio Agent Emergency Startup Media Creator](#)

#### [Creating Startup Disks](#)

#### [Starting a Computer with the R-Studio Agent Emergency Startup Disk](#)

### 7.5.1 Disk Controllers

**R-Studio Agent Emergency** is based on the **FreeBSD 5.3** kernel and supports devices from the list published at <http://www.freebsd.org/releases/5.3R/hardware-i386.html>.

\*: Supported in the floppy version

## **Disk controllers**

### **IDE/ATA controllers ( ata driver) \***

The adapters supported by the [aic](#) driver include:

- Adaptec AHA-1505 (ISA)
- Adaptec AHA-1510A, AHA-1510B (ISA)
- Adaptec AHA-1520A, AHA-1520B (ISA)
- Adaptec AHA-1522A, AHA-1522B (ISA)
- Adaptec AHA-1535 (ISA)
- Creative Labs SoundBlaster SCSI host adapter (ISA)
- Adaptec AHA-1460, AHA-1460B, AHA-1460C, AHA-1460D (PC Card)
- Adaptec AHA-1030B, AHA-1030P (PC98)
- NEC PC-9801-100 (PC98)

The [aha](#) driver supports the following SCSI host adapters:

- Adaptec AHA-154xB
- Adaptec AHA-154xC
- Adaptec AHA-154xCF
- Adaptec AHA-154xCP
- Adaptec AHA-1640
- Adaptec AHA-174x in 154x emulation mode
- DTC 3290 SCSI controller in 1542 emulation mode
- Tekram SCSI controllers in 154x emulation mode

The [ahb](#) driver supports the following SCSI host adapters:

- Adaptec AHA-1740
- Adaptec AHA-1742
- Adaptec AHA-1740A
- Adaptec AHA-1742A

The [ahc](#) driver supports the following SCSI host adapter chips and SCSI controller cards:

- Adaptec AIC7770 host adapter chip
- Adaptec AIC7850 host adapter chip
- Adaptec AIC7860 host adapter chip
- Adaptec AIC7870 host adapter chip
- Adaptec AIC7880 host adapter chip
- Adaptec AIC7890 host adapter chip
- Adaptec AIC7891 host adapter chip
- Adaptec AIC7892 host adapter chip
- Adaptec AIC7895 host adapter chip
- Adaptec AIC7896 host adapter chip
- Adaptec AIC7897 host adapter chip
- Adaptec AIC7899 host adapter chip
- Adaptec 274X(W)
- Adaptec 274X(T)
- Adaptec 284X
- Adaptec 2910

Adaptec 2915  
Adaptec 2920  
Adaptec 2930C  
Adaptec 2930U2  
Adaptec 2940  
Adaptec 2940J  
Adaptec 2940N  
Adaptec 2940U  
Adaptec 2940AU  
Adaptec 2940UW  
Adaptec 2940UW Dual  
Adaptec 2940UW Pro  
Adaptec 2940U2W  
Adaptec 2940U2B  
Adaptec 2950U2W  
Adaptec 2950U2B  
Adaptec 19160B  
Adaptec 29160B  
Adaptec 29160N  
Adaptec 3940  
Adaptec 3940U  
Adaptec 3940AU  
Adaptec 3940UW  
Adaptec 3940AUW  
Adaptec 3940U2W  
Adaptec 3950U2  
Adaptec 3960  
Adaptec 39160  
Adaptec 3985  
Adaptec 4944UW  
NEC PC-9821Xt13 (PC-98)  
NEC RvII26 (PC-98)  
NEC PC-9821X-B02L/B09 (PC-98)  
NEC SV-98/2-B03 (PC-98)  
Many motherboards with on-board SCSI support

**The [ahd](#) driver supports the following:**

Adaptec AIC7901 host adapter chip  
Adaptec AIC7901A host adapter chip  
Adaptec AIC7902 host adapter chip  
Adaptec 29320 host adapter  
Adaptec 39320 host adapter  
Many motherboards with on-board SCSI support

**Controllers supported by the [aac](#) driver include:**

Adaptec AAC-364  
Adaptec SCSI RAID 2120S



Adaptec SCSI RAID 2130S  
Adaptec SCSI RAID 2200S  
Adaptec SCSI RAID 2410SA  
Adaptec SCSI RAID 2810SA  
Adaptec SCSI RAID 5400S  
Dell CERC SATA RAID 2  
Dell PERC 2/Si  
Dell PERC 2/QC  
Dell PERC 3/Si  
Dell PERC 3/Di  
Dell PERC 320/DC  
HP NetRAID 4M

The **adv** driver supports the following SCSI controllers:

AdvanSys ABP510/5150  
AdvanSys ABP5140  
AdvanSys ABP5142  
AdvanSys ABP902/3902  
AdvanSys ABP3905  
AdvanSys ABP915  
AdvanSys ABP920  
AdvanSys ABP3922  
AdvanSys ABP3925  
AdvanSys ABP930, ABP930U, ABP930UA  
AdvanSys ABP960, ABP960U  
AdvanSys ABP542  
AdvanSys ABP742  
AdvanSys ABP842  
AdvanSys ABP940  
AdvanSys ABP940UA/3940UA  
AdvanSys ABP940U  
AdvanSys ABP3960UA  
AdvanSys ABP970, ABP970U  
AdvanSys ABP752  
AdvanSys ABP852  
AdvanSys ABP950  
AdvanSys ABP980, ABP980U  
AdvanSys ABP980UA/3980UA  
MELCO IFC-USP (PC-98)  
RATOC REX-PCI30 (PC-98)  
@Nifty FNECHARD IFC-USUP-TX (PC-98)

The **adw** driver supports SCSI controllers including:

AdvanSys ABP940UW/ABP3940UW  
AdvanSys ABP950UW  
AdvanSys ABP970UW  
AdvanSys ABP3940U2W

AdvanSys ABP3950U2W

The **bt** driver supports the following BusLogic MultiMaster ``W'', ``C'', ``S'', and ``A'' series and compatible SCSI host adapters:

BusLogic BT-445C  
BusLogic BT-445S  
BusLogic BT-540CF  
BusLogic BT-542B  
BusLogic BT-542B  
BusLogic BT-542D  
BusLogic BT-545C  
BusLogic BT-545S  
BusLogic/BusTek BT-640  
BusLogic BT-742A  
BusLogic BT-742A  
BusLogic BT-747C  
BusLogic BT-747D  
BusLogic BT-747S  
BusLogic BT-757C  
BusLogic BT-757CD  
BusLogic BT-757D  
BusLogic BT-757S  
BusLogic BT-946C  
BusLogic BT-948  
BusLogic BT-956C  
BusLogic BT-956CD  
BusLogic BT-958  
BusLogic BT-958D

Storage Dimensions SDC3211B / SDC3211F

AMI FastDisk Host Adapters that are true BusLogic MultiMaster clones are also supported by the **bt** driver.

The **dpt** driver provides support for the following RAID adapters:

DPT Smart Cache Plus  
Smart Cache II (PM2?2?, PM2022 [EISA], PM2024/PM2124 [PCI]) (Gen2)  
Smart RAID II (PM3?2?, PM3021, PM3222)  
Smart Cache III (PM2?3?)  
Smart RAID III (PM3?3?, PM3332 [EISA], PM3334UW [PCI]) (Gen3)  
Smart Cache IV (PM2?4?, PM2042 [EISA], PM2044/PM2144 [PCI]) (Gen4)  
Smart RAID IV

The adapters currently supported by the **asr** driver include the following:

Adaptec Zero-Channel SCSI RAID 2000S, 2005S, 2010S, 2015S  
Adaptec SCSI RAID 2100S, 2110S  
Adaptec ATA-100 RAID 2400A  
Adaptec SCSI RAID 3200S, 3210S  
Adaptec SCSI RAID 3400S, 3410S  
Adaptec SmartRAID PM1554  
Adaptec SmartRAID PM1564

Adaptec SmartRAID PM2554  
Adaptec SmartRAID PM2564  
Adaptec SmartRAID PM2664  
Adaptec SmartRAID PM2754  
Adaptec SmartRAID PM2865  
Adaptec SmartRAID PM3754  
Adaptec SmartRAID PM3755U2B / SmartRAID V Millennium  
Adaptec SmartRAID PM3757  
DEC KZPCC-AC (LVD 1-ch, 4MB or 16MB cache), DEC KZPCC-CE (LVD 3-ch, 64MB cache), DEC KZPCC-XC (LVD 1-ch, 16MB cache), DEC KZPCC-XE (LVD 3-ch, 64MB cache) -- rebadged SmartRAID V Millennium

**The [amr](#) driver supports the following:**

AMI MegaRAID 320-1  
AMI MegaRAID 320-2  
AMI MegaRAID 320-4X  
AMI MegaRAID Series 418  
AMI MegaRAID Enterprise 1200 (Series 428)  
AMI MegaRAID Enterprise 1300 (Series 434)  
AMI MegaRAID Enterprise 1400 (Series 438)  
AMI MegaRAID Enterprise 1500 (Series 467)  
AMI MegaRAID Enterprise 1600 (Series 471)  
AMI MegaRAID Elite 1500 (Series 467)  
AMI MegaRAID Elite 1600 (Series 493)  
AMI MegaRAID Elite 1650 (Series 4xx)  
AMI MegaRAID Express 100 (Series 466WS)  
AMI MegaRAID Express 200 (Series 466)  
AMI MegaRAID Express 300 (Series 490)  
AMI MegaRAID Express 500 (Series 475)  
Dell PERC  
Dell PERC 2/SC  
Dell PERC 2/DC  
Dell PERC 3/DCL  
Dell PERC 3/QC  
Dell PERC 4/Di  
HP NetRAID-1/Si  
HP NetRAID-3/Si (D4943A)  
HP Embedded NetRAID

**Note:** Booting from these controllers is supported. EISA adapters are not supported.

**Controllers supported by the [mlx](#) driver include:**

Mylex DAC960P  
Mylex DAC960PD / DEC KZPSC (Fast Wide)  
Mylex DAC960PDU  
Mylex DAC960PL  
Mylex DAC960PJ  
Mylex DAC960PG

Mylex DAC960PU / DEC PZPAC (Ultra Wide)

Mylex AcceleRAID 150 (DAC960PRL)

Mylex AcceleRAID 250 (DAC960PTL1)

Mylex eXtremeRAID 1100 (DAC1164P)

RAIDarray 230 controllers, aka the Ultra-SCSI DEC KZPAC-AA (1-ch, 4MB cache), KZPAC-CA (3-ch, 4MB), KZPAC-CB (3-ch, 8MB cache)

All major firmware revisions (2.x, 3.x, 4.x and 5.x) are supported, however it is always advisable to upgrade to the most recent firmware available for the controller. Compatible Mylex controllers not listed should work, but have not been verified.

**Note:** Booting from these controllers is supported. EISA adapters are not supported.

**Controllers supported by the `mly` driver include:**

Mylex AcceleRAID 160

Mylex AcceleRAID 170

Mylex AcceleRAID 352

Mylex eXtremeRAID 2000

Mylex eXtremeRAID 3000

Compatible Mylex controllers not listed should work, but have not been verified.

**The `twe` driver supports the following ATA RAID controllers:**

AMCC's 3ware 5000 series

AMCC's 3ware 6000 series

AMCC's 3ware 7000-2

AMCC's 3ware 7006-2

AMCC's 3ware 7500-4LP

AMCC's 3ware 7500-8

AMCC's 3ware 7500-12

AMCC's 3ware 7506-4LP

AMCC's 3ware 7506-8

AMCC's 3ware 7506-12

AMCC's 3ware 8006-2LP

AMCC's 3ware 8500-4LP

AMCC's 3ware 8500-8

AMCC's 3ware 8500-12

AMCC's 3ware 8506-4LP

AMCC's 3ware 8506-8

AMCC's 3ware 8506-8MI

AMCC's 3ware 8506-12

AMCC's 3ware 8506-12MI

**The `twa` driver supports the following PATA/SATA RAID controllers:**

AMCC's 3ware 9500S-4LP

AMCC's 3ware 9500S-8

AMCC's 3ware 9500S-8MI

AMCC's 3ware 9500S-12

AMCC's 3ware 9500S-12MI

The **ncr** driver provides support for the following NCR/Symbios SCSI controller chips:

- 53C810
- 53C810A
- 53C815
- 53C820
- 53C825A
- 53C860
- 53C875
- 53C875J
- 53C885
- 53C895
- 53C895A
- 53C896
- 53C1510D

The following add-on boards are known to be supported:

- I-O DATA SC-98/PCI (PC-98)
- I-O DATA SC-PCI (PC-98)

The **sym** driver provides support for the following Symbios/LSI Logic PCI SCSI controllers:

- 53C810
- 53C810A
- 53C815
- 53C825
- 53C825A
- 53C860
- 53C875
- 53C876
- 53C895
- 53C895A
- 53C896
- 53C897
- 53C1000
- 53C1000R
- 53C1010-33
- 53C1010-66
- 53C1510D

The SCSI controllers supported by **sym** can be either embedded on a motherboard, or on one of the following add-on boards:

- ASUS SC-200, SC-896
- Data Technology DTC3130 (all variants)
- DawiControl DC2976UW
- Diamond FirePort (all)
- I-O DATA SC-UPCI (PC-98)
- Logitec LHA-521UA (PC-98)
- NCR cards (all)

Symbios cards (all)

Tekram DC390W, 390U, 390F, 390U2B, 390U2W, 390U3D, and 390U3W

Tyan S1365

**The following devices are currently supported by the `ncv` driver:**

I-O DATA PCSC-DV

KME KXLC002 (TAXAN ICD-400PN, etc.), KXLC004, and UJDCD450

Macnica Miracle SCSI-II mPS110

Media Intelligent MSC-110, MSC-200

NEC PC-9801N-J03R

New Media Corporation BASICS SCSI

Qlogic Fast SCSI

RATOC REX-9530, REX-5572 (SCSI only)

**Controllers supported by the `stg` driver include:**

Adaptec 2920/A

Future Domain SCSI2GO

Future Domain TMC-18XX/3260

IBM SCSI PCMCIA Card

ICM PSC-2401 SCSI

MELCO IFC-SC

RATOC REX-5536, REX-5536AM, REX-5536M, REX-9836A

Note that the Adaptec 2920C is supported by the `ahc` driver.

**Cards supported by the `isp` driver include:**

ISP1000

PTI SBS440

ISP1020

ISP1040

PTI SBS450

Qlogic 1240

Qlogic 1020

Qlogic 1040

Qlogic 1080

Qlogic 1280

Qlogic 12160

Qlogic 2100

Qlogic 2102

Qlogic 2200

Qlogic 2202

Qlogic 2204

Qlogic 2300

Qlogic 2312

PTI SBS470

Antares P-0033

**Controllers supported by the `amd` driver include:**

MELCO IFC-DP (PC-98)

Tekram DC390  
Tekram DC390T

**Controllers supported by the [nsp](#) driver include:**

Alpha-Data AD-PCS201  
I-O DATA CBSC16  
Adaptec AIC-7110 Parallel to SCSI interfaces ( [vpo](#) driver)

**The following controllers are supported by the [ida](#) driver:**

Compaq SMART Array 221  
Compaq Integrated SMART Array Controller  
Compaq SMART Array 4200  
Compaq SMART Array 4250ES  
Compaq SMART 3200 Controller  
Compaq SMART 3100ES Controller  
Compaq SMART-2/DH Controller  
Compaq SMART-2/SL Controller  
Compaq SMART-2/P Controller  
Compaq SMART-2/E Controller  
Compaq SMART Controller

**Controllers supported by the [ciiss](#) driver include:**

Compaq Smart Array 5300  
Compaq Smart Array 532  
Compaq Smart Array 5i  
HP Smart Array 5312  
HP Smart Array 6i  
HP Smart Array 641  
HP Smart Array 642  
HP Smart Array 6400  
HP Smart Array 6400 EM  
HP Smart Array 6422  
HP Smart Array V100  
HP Modular Smart Array 20 (MSA20)  
HP Modular Smart Array 500 (MSA500)

**Controllers supported by the [iir](#) driver include:**

Intel RAID Controller SRCMR  
Intel Server RAID Controller U3-1 (SRCU31a)  
Intel Server RAID Controller U3-1L (SRCU31La)  
Intel Server RAID Controller U3-2 (SRCU32)  
All past and future releases of Intel and ICP RAID Controllers.  
Intel RAID Controller SRCU21 (discontinued)  
Intel RAID Controller SRCU31 (older revision, not compatible)  
Intel RAID Controller SRCU31L (older revision, not compatible)  
The SRCU31 and SRCU31L can be updated via a firmware update available from Intel.  
Promise SuperTrak ATA RAID controllers ([pst](#) driver)

The **hptmv** driver supports the HighPoint RocketRAID 182x SATA controllers.

Controllers supported by the **ips** driver include:

- IBM ServeRAID 3H
- ServeRAID 4L/4M/4H
- ServeRAID Series 5
- ServeRAID 6i/6M

The following controllers are supported by the **mpt** driver:

- LSI Logic 53c1030 (Dual Ultra320 SCSI)
- LSI Logic FC909 (1Gb/s Fibre Channel)
- LSI Logic FC909A (Dual 1Gb/s Fibre Channel)
- LSI Logic FC919 (2Gb/s Fibre Channel)
- LSI Logic FC929 (Dual 2Gb/s Fibre Channel)

The SCSI controller chips supported by the **mpt** driver can be found onboard on many systems including:

- Dell PowerEdge 1750
- IBM eServer xSeries 335

SCSI controllers supported by the **trm** driver include:

- Tekram DC-315 PCI Ultra SCSI adapter without BIOS and internal SCSI connector
- Tekram DC-315U PCI Ultra SCSI adapter without BIOS
- Tekram DC-395F PCI Ultra-Wide SCSI adapter with flash BIOS and 68-pin external SCSI connector
- Tekram DC-395U PCI Ultra SCSI adapter with flash BIOS
- Tekram DC-395UW PCI Ultra-Wide SCSI adapter with flash BIOS
- Tekram DC-395U2W PCI Ultra2-Wide SCSI adapter with flash BIOS

For the Tekram DC-310/U and DC-390F/U/UW/U2B/U2W/U3W PCI SCSI host adapters, use the **sym** driver.

The **wds** driver supports the WD7000 SCSI controller.

## 7.5.2 Network Cards

**R-Studio Agent Emergency** is based on the **FreeBSD 5.3** kernel and supports devices from the list published at <http://www.freebsd.org/releases/5.3R/hardware-i386.html>.

\*: Supported in the floppy version

### **Ethernet NICs**

Adapters supported by the **sf** driver include:

- ANA-62011 64-bit single port 10/100baseTX adapter
- ANA-62022 64-bit dual port 10/100baseTX adapter
- ANA-62044 64-bit quad port 10/100baseTX adapter
- ANA-69011 32-bit single port 10/100baseTX adapter
- ANA-62020 64-bit single port 100baseFX adapter

The **ti** driver supports Gigabit Ethernet adapters based on the Alteon Tigon I and II chips. The **ti** driver has been tested with the following adapters:

- 3Com 3c985-SX Gigabit Ethernet adapter (Tigon 1)
- 3Com 3c985B-SX Gigabit Ethernet adapter (Tigon 2)
- Alteon AceNIC V Gigabit Ethernet adapter (1000baseSX)
- Alteon AceNIC V Gigabit Ethernet adapter (1000baseT)
- Digital EtherWORKS 1000SX PCI Gigabit adapter



Netgear GA620 Gigabit Ethernet adapter (1000baseSX)

Netgear GA620T Gigabit Ethernet adapter (1000baseT)

**The following adapters should also be supported but have not yet been tested:**

Asante GigaNIX1000T Gigabit Ethernet adapter

Asante PCI 1000BASE-SX Gigabit Ethernet adapter

Farallon PN9000SX Gigabit Ethernet adapter

NEC Gigabit Ethernet

Silicon Graphics PCI Gigabit Ethernet adapter

**The `pcn` driver supports adapters and embedded controllers based on the AMD PCnet/FAST, PCnet/FAST+, PCnet/FAST III, PCnet/PRO and PCnet/Home Fast Ethernet chips:**

AMD Am53C974/Am79C970/Am79C974 PCnet-PCI \*

AMD Am79C970A PCnet-PCI II \*

AMD Am79C971 PCnet-FAST \*

AMD Am79C972 PCnet-FAST+ \*

AMD Am79C973/Am79C975 PCnet-FAST III \*

AMD Am79C976 PCnet-PRO \*

AMD PCnet/Home HomePNA

Allied-Telesis LA-PCI

Contec C-NET(98)S (PC-98)

NEC SV-98/2-B05, B06

**The `lnc` driver supports the following adapters:**

Novell NE2100 \*

Novell NE32-VL \*

Isolan AT 4141-0 (16 bit)

Isolan BICC

Isolink 4110 (8 bit)

Diamond HomeFree

Digital DEPCA

Hewlett Packard Vectra 486/66XM

Hewlett Packard Vectra XU

Also supported are adapters working with the `pcn` driver. The `lnc` driver runs these in compatibility mode, thus the `pcn` driver should be preferred.

SMC 83c17x (EPIC)-based Ethernet NICs (`tx` driver)

**The `ed` driver supports the following Ethernet NICs:**

3Com 3c503 Etherlink II

AR-P500 Ethernet

Accton EN1644 (old model), EN1646 (old model), EN2203 (old model) (110pin) (flags 0xd00000)

Accton EN2212/EN2216/UE2216

Allied Telesis CentreCOM LA100-PCM\_V2

Allied Telesis LA-98 (flags 0x000000) (PC-98)

Allied Telesis SIC-98, SIC-98NOTE (110pin), SIU-98 (flags 0x600000) (PC-98)

Allied Telesis SIU-98-D (flags 0x610000) (PC-98)

AmbiCom 10BaseT card

Bay Networks NETGEAR FA410TXC Fast Ethernet

CNet BC40 adapter  
Compex Net-A adapter  
Contec C-NET(98), RT-1007(98), C-NET(9N) (110pin) (flags 0xa00000) (PC-98)  
Contec C-NET(98)E-A, C-NET(98)L-A, C-NET(98)P (flags 0x300000) (PC-98)  
Corega Ether98-T (flags 0x000000) (PC-98)  
Corega Ether PCC-T/EtherII PCC-T/FEther PCC-TXF/PCC-TXD  
CyQ've ELA-010  
DEC EtherWorks DE305  
Danpex EN-6200P2  
D-Link DE-298, DE-298P (flags 0x500000) (PC-98)  
D-Link DE-650/660  
D-Link IC-CARD/IC-CARD+ Ethernet  
ELECOM LD-98P (flags 0x500000) (PC-98)  
ELECOM LD-BDN, LD-NW801G (flags 0x200000) (PC-98)  
ELECOM Lanced LD-CDL/TX, LD-CDF, LD-CDS, LD-10/100CD, LD-CDWA (DP83902A)  
HP PC Lan+ 27247B and 27252A  
IBM Creditcard Ethernet I/II  
ICM AD-ET2-T, DT-ET-25, DT-ET-T5, IF-2766ET, IF-2771ET, NB-ET-T (110pin) (flags 0x500000) (PC-98)  
I-O DATA LA/T-98, LA/T-98SB, LA2/T-98, ET/T-98 (flags 0x900000) (PC-98)  
I-O DATA ET2/T-PCI  
I-O DATA PCLATE  
Kansai KLA-98C/T (flags 0x900000) (PC-98)  
Kingston KNE-PC2, KNE-PCM/x Ethernet  
Linksys EC2T/PCMP100/PCM100, PCMLM56  
Linksys EtherFast 10/100 PC Card, Combo PCMCIA Ethernet Card (PCMP100 V2)  
Logitec LAN-98T (flags 0xb00000) (PC-98)  
MACNICA Ethernet ME1 for JEIDA  
MACNICA ME98 (flags 0x900000) (PC-98)  
MACNICA NE2098 (flags 0x400000) (PC-98)  
MELCO EGY-98 (flags 0x300000) (PC-98)  
MELCO LGH-98, LGY-98, LGY-98-N (110pin), IND-SP, IND-SS (flags 0x400000) (PC-98)  
MELCO LGY-PCI-TR  
MELCO LPC-T/LPC2-T/LPC2-CLT/LPC2-TX/LPC3-TX/LPC3-CLX  
NDC Ethernet Instant-Link  
NEC PC-9801-77, PC-9801-78 (flags 0x910000) (PC-98)  
NEC PC-9801-107, PC-9801-108 (flags 0x800000) (PC-98)  
National Semiconductor InfoMover NE4100  
NetGear FA-410TX  
NetVin 5000  
Network Everywhere Ethernet 10BaseT PC Card  
Networkd 98X3 (flags 0xd00000) (PC-98)  
Networkd EC-98X, EP-98X (flags 0xd10000) (PC-98)  
Novell NE1000/NE2000/NE2100  
PLANEX ENW-8300-T

PLANEX EN-2298-C (flags 0x200000) (PC-98)  
PLANEX EN-2298P-T, EN-2298-T (flags 0x500000) (PC-98)  
PLANEX FNW-3600-T  
RealTek 8029  
SMC Elite 16 WD8013  
SMC Elite Ultra  
SMC EtherEZ98 (flags 0x000000) (PC-98)  
SMC WD8003E/WD8003EBT/WD8003S/WD8003SBT/WD8003W/WD8013EBT/WD8013W and clones  
Socket LP-E  
Surecom EtherPerfect EP-427  
Surecom NE-34  
TDK LAK-CD031, Grey Cell GCS2000 Ethernet Card  
Telecom Device SuperSocket RE450T  
VIA VT86C926  
Winbond W89C940  
C-Bus, ISA, PCI and PC Card devices are supported.

**Adapters supported by the `rl` driver include:**

Accton ``Cheetah" EN1207D (MPX 5030/5038; RealTek 8139 clone)  
Allied Telesyn AT2550  
Allied Telesyn AT2500TX  
Belkin F5D5000  
BUFFALO(Melco INC.) LPC-CB-CLX(CardBus)  
Compaq HNE-300  
CompUSA no-name 10/100 PCI Ethernet NIC  
Corega FEther CB-TXD  
Corega FEtherII CB-TXD  
D-Link DFE-530TX+  
D-Link DFE-538TX (same as 530+?)  
D-Link DFE-690TXD  
Edimax EP-4103DL CardBus  
Encore ENL832-TX 10/100 M PCI  
Farallon NetLINE 10/100 PCI  
Genius GF100TXR,  
GigaFast Ethernet EE100-AXP  
KTX-9130TX 10/100 Fast Ethernet  
LevelOne FPC-0106TX  
Longshine LCS-8038TX-R  
NDC Communications NE100TX-E  
Netronix Inc. EA-1210 NetEther 10/100  
Nortel Networks 10/100BaseTX  
OvisLink LEF-8129TX  
OvisLink LEF-8139TX  
Peppercon AG ROL-F  
Planex FNW-3800-TX

SMC EZ Card 10/100 PCI 1211-TX  
SOHO(PRAGMATIC) UE-1211C

The **wb** driver supports Winbond W89C840F based Fast Ethernet adapters and embedded controllers including:

Trendware TE100-PCIE \*

The **vr** driver supports VIA Technologies Rhine I, Rhine II, and Rhine III based Fast Ethernet adapters including:

D-Link DFE530-TX  
Hawking Technologies PN102TX  
AOpen/Acer ALN-320

The **sis** driver supports Silicon Integrated Systems SiS 900 \* and SiS 7016 \* based Fast Ethernet adapters and embedded controllers, as well as Fast Ethernet adapters based on the National Semiconductor DP83815 (MacPhyter) chip. Supported adapters include:

@Nifty FNECHARD IFC USUP-TX  
MELCO LGY-PCI-TXC  
Netgear FA311-TX (DP83815)  
Netgear FA312-TX (DP83815)  
SiS 630, 635, and 735 motherboard chipsets

The **nge** driver supports National Semiconductor DP83820 \* and DP83821 based Gigabit Ethernet adapters including:

SMC EZ Card 1000 (SMC9462TX)  
D-Link DGE-500T  
Asante FriendlyNet GigaNIX 1000TA and 1000TPC  
Addtron AEG320T  
LinkSys EG1032 (32-bit PCI) and EG1064 (64-bit PCI)  
Surecom Technology EP-320G-TX  
Netgear GA622T  
Netgear GA621  
Ark PC SOHO-GA2500T (32-bit PCI) and SOHO-GA2000T (64-bit PCI)  
Trendware TEG-PCITX (32-bit PCI) and TEG-PCITX2 (64-bit PCI)

The **ste** driver supports Sundance Technologies ST201 based Fast Ethernet adapters and embedded controllers including:

D-Link DFE-530TXS  
D-Link DFE-550TX

Adapters supported by the **sk** driver include:

3COM 3C940 single port, 1000baseT adapter  
Belkin F5D5005 single port, 1000baseT adapter  
Linksys EG1032 single port, 1000baseT adapter  
SK-9521 SK-NET GE-T single port, 1000baseT adapter  
SK-9821 SK-NET GE-T single port, 1000baseT adapter \*  
SK-9822 SK-NET GE-T dual port, 1000baseT adapter \*  
SK-9841 SK-NET GE-LX single port, single mode fiber adapter \*  
SK-9842 SK-NET GE-LX dual port, single mode fiber adapter \*  
SK-9843 SK-NET GE-SX single port, multimode fiber adapter \*  
SK-9844 SK-NET GE-SX dual port, multimode fiber adapter \*

SMC 9452TX single port, 1000baseT adapter

**The `tl` driver supports Texas Instruments ThunderLAN based Ethernet and Fast Ethernet adapters including a large number of Compaq PCI Ethernet adapters. Also supported are:**

Olicom OC-2135/2138 10/100 TX UTP adapter  
Olicom OC-2325/OC-2326 10/100 TX UTP adapter  
Racore 8148 10baseT/100baseTX/100baseFX adapter  
Racore 8165 10/100baseTX adapter

**The `tl` driver also supports the built-in Ethernet adapters of various Compaq Prosignia servers and Compaq Deskpro desktop machines including:**

Compaq Netelligent 10  
Compaq Netelligent 10 T PCI UTP/Coax  
Compaq Netelligent 10/100  
Compaq Netelligent 10/100 Dual-Port  
Compaq Netelligent 10/100 Proliant  
Compaq Netelligent 10/100 TX Embedded UTP  
Compaq Netelligent 10/100 TX UTP  
Compaq NetFlex 3P  
Compaq NetFlex 3P Integrated  
Compaq NetFlex 3P w/BNC

**The `dc` driver provides support for the following chipsets: \***

DEC/Intel 21143  
ADMtek AL981 Comet, AN985 Centaur, ADM9511 Centaur II and ADM9513 Centaur II  
ASIX Electronics AX88140A and AX88141  
Conexant LANfinity RS7112 (miniPCI)  
Davicom DM9009, DM9100, DM9102 and DM9102A  
Lite-On 82c168 and 82c169 PNIC  
Lite-On/Macronix 82c115 PNIC II  
Macronix 98713, 98713A, 98715, 98715A, 98715AEC-C, 98725, 98727 and 98732  
Xircom X3201 (cardbus only)

**The following NICs are known to work with the `dc` driver at this time:**

3Com OfficeConnect 10/100B (ADMtek AN985 Centaur-P)  
Abocom FE2500  
Accton EN1217 (98715A)  
Accton EN2242 MiniPCI  
Adico AE310TX (98715A)  
Alfa Inc GFC2204 (ASIX AX88140A)  
Built in 10Mbps only Ethernet on Compaq Presario 7900 series desktops (21143, non-MII)  
Built in DE500-BA on DEC Alpha workstations (21143, non-MII)  
Built in Sun DMFE 10/100 Mbps Ethernet on Sun Netra X1 and Sun Fire V100 (DM9102A, MII)  
Built in Ethernet on LinkSys EtherFast 10/100 Instant GigaDrive (DM9102, MII)  
CNet Pro110B (ASIX AX88140A)  
CNet Pro120A (98715A or 98713A) and CNet Pro120B (98715)  
Compex RL100-TX (98713 or 98713A)  
D-Link DFE-570TX (21143, MII, quad port)  
Digital DE500-BA 10/100 (21143, non-MII)

ELECOM Lanced LD-CBL/TXA (ADMtek AN985)  
Hawking CB102 CardBus  
IBM EtherJet Cardbus Adapter  
Intel PRO/100 Mobile Cardbus (versions that use the X3201 chipset)  
Jaton XpressNet (Davicom DM9102)  
Kingston KNE100TX (21143, MII)  
Kingston KNE110TX (PNIC 82c169)  
LinkSys LNE100TX (PNIC 82c168, 82c169)  
LinkSys LNE100TX v2.0 (PNIC II 82c115)  
LinkSys LNE100TX v4.0/4.1 (ADMtek AN985 Centaur-P)  
Matrox FastNIC 10/100 (PNIC 82c168, 82c169)  
Melco LGY-PCI-TXL  
Microsoft MN-120 10/100 CardBus (ADMtek Centaur-C)  
Microsoft MN-130 10/100 PCI (ADMtek Centaur-P)  
NDC SOHOware SFA110A (98713A)  
NDC SOHOware SFA110A Rev B4 (98715AEC-C)  
NetGear FA310-TX Rev. D1, D2 or D3 (PNIC 82c169)  
Netgear FA511  
PlaneX FNW-3602-T (ADMtek AN985)  
SMC EZ Card 10/100 1233A-TX (ADMtek AN985)  
SVEC PN102-TX (98713)  
Xircom Cardbus Realport  
Xircom Cardbus Ethernet 10/100  
Xircom Cardbus Ethernet II 10/100

**Adapters supported by the `au` driver include:**

Abocom UFE1000, DSB650TX\_NA  
Accton USB320-EC, SpeedStream  
ADMtek AN986, AN8511  
Billionton USB100, USB100LP, USB100EL, USBE100  
Corega Ether FEther USB-T, FEther USB-TX, FEther USB-TXS  
D-Link DSB-650, DSB-650TX, DSB-650TX-PNA  
Elecom LD-USBL/TX  
Elsa Microlink USB2Ethernet  
HP hn210e  
I-O Data USB ETTX  
Kingston KNU101TX  
LinkSys USB10T adapters that contain the AN986 Pegasus chipset, USB10TA, USB10TX, USB100TX, USB100H1  
MELCO LUA-TX, LUA2-TX  
Planex UE-200TX  
Sandberg USB to Network Link (model number 133-06)  
Siemens Speedstream  
SmartBridges smartNIC  
SMC 2202USB  
SOHOware NUB100

The **cue** driver supports CATC USB-EL1210A based USB Ethernet adapters including:

- Belkin F5U011/F5U111
- CATC Netmate
- CATC Netmate II
- SmartBridges SmartLink

The **kue** driver supports Kawasaki LSI KL5KLUSB101B based USB Ethernet adapters including:

- 3Com 3c19250
- 3Com 3c460 HomeConnect Ethernet USB Adapter
- ADS Technologies USB-10BT
- AOX USB101
- ATen UC10T
- Abocom URE 450
- Corega USB-T
- D-Link DSB-650C
- Entrega NET-USB-E45, NET-HUB-3U1E
- I/O Data USB ETT
- Kawasaki DU-H3E
- LinkSys USB10T
- Netgear EA101
- Peracom USB Ethernet Adapter
- SMC 2102USB, 2104USB

The **axe** driver supports ASIX Electronics AX88172 based USB Ethernet adapters including:

- Buffalo (Melco Inc.) LUA-U2-KTX
- D-Link DUBE100
- LinkSys USB200M
- Netgear FA120
- System TALKS Inc. SGC-X2UL

The **ru**e driver supports RealTek RTL8150 based USB Ethernet adapters including:

- Buffalo (Melco Inc.) LUA-KTX
- Green House GH-USB100B
- LinkSys USB100M
- Billionton 10/100 FastEthernet USBKR2

The **udav** driver supports the following adapters:

- Corega FEther USB-TXC

Adapters supported by the **de** driver include:

- Adaptec ANA-6944/TX
- Cogent EM100FX and EM440TX
- Corega FastEther PCI-TX
- D-Link DFE-500TX
- DEC DE435, DE425, DEC DE450, and DEC DE500
- ELECOM LD-PCI2T, LD-PCITS
- I-O DATA LA2/T-PCI
- SMC Etherpower 8432, 9332 and 9334
- ZNYX ZX3xx

**Controllers and cards supported by the [fe](#) driver include:**

Allied Telesis RE1000, RE1000Plus, ME1500 (110-pin)  
CONTEC C-NET(98)P2, C-NET (9N)E (110-pin), C-NET(9N)C (ExtCard)  
CONTEC C-NET(PC)C PCMCIA Ethernet  
Eiger Labs EPX-10BT  
Fujitsu FMV-J182, FMV-J182A  
Fujitsu MB86960A, MB86965A  
Fujitsu MBH10303, MBH10302 Ethernet PCMCIA  
Fujitsu Towa LA501 Ethernet  
HITACHI HT-4840-11  
NextCom J Link NC5310  
RATOC REX-5588, REX-9822, REX-4886, and REX-R280  
RATOC REX-9880/9881/9882/9883  
TDK LAC-98012, LAC-98013, LAC-98025, LAC-9N011 (110-pin)  
TDK LAK-CD021, LAK-CD021A, LAK-CD021BX  
Ungermann-Bass Access/PC N98C+(PC85152, PC85142), Access/NOTE N98(PC86132) (110-pin)

**Adapters supported by the [fxp](#) driver include:**

Intel EtherExpress PRO/10  
Intel InBusiness 10/100  
Intel PRO/100B / EtherExpressPRO/100 B PCI Adapter \*  
Intel PRO/100+ Management Adapter  
Intel PRO/100 VE Desktop Adapter  
Intel PRO/100 M Desktop Adapter  
Intel PRO/100 S Desktop, Server and Dual-Port Server Adapters  
Contec C-NET(PI)-100TX (PC-98)  
NEC PC-9821Ra20, Rv20, Xv13, Xv20 internal 100Base-TX (PC-98)  
NEC PC-9821X-B06 (PC-98)  
Many on-board network interfaces on Intel motherboards

**The [ex](#) driver supports the following Ethernet adapters:**

Intel EtherExpress Pro/10  
Intel EtherExpress Pro/10+  
The Olicom OC2220

**The [ie](#) driver provides supports the following 8 and 16bit ISA Ethernet cards that are based on the Intel i82586 chip:**

3COM 3C507  
AT&T EN100  
AT&T Starlan 10  
AT&T Starlan Fiber  
Intel EtherExpress 16  
RACAL Interlan NI5210

**The [ep](#) driver supports Ethernet adapters based on the 3Com 3C5x9 Etherlink III Parallel Tasking chipset, including:**

3Com 3C1 CF  
3Com 3C509-TP, 3C509-BNC, 3C509-Combo, 3C509-TPO, 3C509-TPC ISA



3Com 3C509B-TP, 3C509B-BNC, 3C509B-Combo, 3C509B-TPO, 3C509B-TPC ISA  
3Com 3C529, 3C529-TP MCA  
3Com 3C562/3C563 PCMCIA  
3Com 3C569B-J-TPO, 3C569B-J-COMBO CBUS  
3Com 3C574-TX, 3CCFE574BT, 3CXFE574BT, 3C3FE574BT PCMCIA  
3Com 3C579-TP, 3C579-BNC EISA  
3Com 3C589, 3C589B, 3C589C, 3C589D, 3CXE589DT PCMCIA  
3Com 3CCFEM556B, 3CCFEM556BI PCMCIA  
3Com 3CXE589EC, 3CCE589EC, 3CXE589ET, 3CCE589ET PCMCIA  
3Com Megahertz 3CCEM556, 3CXEM556, 3CCEM556B, 3CXEM556B PCMCIA  
3Com OfficeConnect 3CXSH572BT, 3CCSH572BT PCMCIA  
Farallon EtherMac PCMCIA

The [el](#) driver supports the 3Com 3c501 8bit ISA Ethernet card.

The [xl](#) driver supports the following hardware:

3Com 3c900-TPO \*  
3Com 3c900-COMBO \*  
3Com 3c905-TX \*  
3Com 3c905-T4 \*  
3Com 3c900B-TPO \*  
3Com 3c900B-TPC \*  
3Com 3c900B-FL \*  
3Com 3c900B-COMBO \*  
3Com 3c905B-T4 \*  
3Com 3c905B-TX \*  
3Com 3c905B-FX \*  
3Com 3c905B-COMBO \*  
3Com 3c905C-TX \*  
3Com 3c980, 3c980B, and 3c980C server adapters  
3Com 3cSOHO100-TX OfficeConnect adapters  
3Com 3c450 HomeConnect adapters  
3Com 3c555, 3c556 and 3c556B mini-PCI adapters  
3Com 3C3SH573BT, 3C575TX, 3CCFE575BT, 3CXFE575BT, 3CCFE575CT, 3CXFE575CT,  
3CCFEM656, 3CCFEM656B, and 3CCFEM656C, 3CXFEM656, 3CXFEM656B, and 3CXFEM656C  
CardBus adapters  
3Com 3c905-TX, 3c905B-TX 3c905C-TX, and 3c920B-EMB embedded adapters  
Both the 3C656 family of CardBus cards and the 3C556 family of MiniPCI cards have a built-in proprietary modem. Neither the xl driver nor any other driver supports this modem.

The [vx](#) driver supports the following cards:

3Com 3c590 EtherLink III PCI \*  
3Com 3c592 EtherLink III EISA  
3Com 3c595 Fast EtherLink III PCI in 10 Mbps mode \*  
3Com 3c597 Fast EtherLink III EISA in 10 Mbps mode  
Crystal Semiconductor CS89x0-based NICs ([cs](#) driver)

The [sn](#) driver supports SMC9xxx based ISA and PCMCIA cards including:

3Com Megahertz X-Jack Ethernet PC-Card CC-10BT

The [xe](#) driver supports the following cards:

Xircom CreditCard Ethernet (PS-CE2-10)

Xircom CreditCard Ethernet + Modem 28 (PS-CEM-28)

Xircom CreditCard Ethernet + Modem 33 (CEM33)

Xircom CreditCard 10/100 (CE3, CE3B)

Xircom CreditCard Ethernet 10/100 + Modem 56 (CEM56)

Xircom RealPort Ethernet 10 (RE10)

Xircom RealPort Ethernet 10/100 (RE100)

Xircom RealPort Ethernet 10/100 + Modem 56 (REM56, REM56G)

Accton Fast EtherCard-16 (EN2226)

Compaq Netelligent 10/100 PC Card (CPQ-10/100)

Intel EtherExpress Pro/100 PC Card Mobile Adapter 16 (Pro/100 M16A)

Other similar devices using the same hardware may also be supported.

Adapters supported by the [lge](#) driver include:

SMC TigerCard 1000 (SMC9462SX) \*

D-Link DGE-500SX \*

The [txp](#) driver supports the following cards:

3Com 3CR990-TX-95 \*

3Com 3CR990-TX-97 \*

3Com 3cR990B-TXM \*

3Com 3CR990SVR95 \*

3Com 3CR990SVR97 \*

3Com 3cR990B-SRV \*

The [bge](#) driver provides support for various NICs based on the Broadcom BCM570x family of Gigabit Ethernet controller chips, including the following:

3Com 3c996-T (10/100/1000baseTX) \*

Dell PowerEdge 1750 integrated BCM5704C NIC (10/100/1000baseTX) \*

Dell PowerEdge 2550 integrated BCM5700 NIC (10/100/1000baseTX) \*

Dell PowerEdge 2650 integrated BCM5703 NIC (10/100/1000baseTX) \*

IBM x235 server integrated BCM5703x NIC (10/100/1000baseTX) \*

HP ProLiant NC7760 embedded Gigabit NIC (10/100/1000baseTX) \*

HP ProLiant NC7770 PCI-X Gigabit NIC (10/100/1000baseTX) \*

HP ProLiant NC7781 embedded PCI-X Gigabit NIC (10/100/1000baseTX) \*

Netgear GA302T (10/100/1000baseTX) \*

SysKonnect SK-9D21 (10/100/1000baseTX) \*

SysKonnect SK-9D41 (1000baseSX) \*

The [em](#) driver supports Gigabit Ethernet adapters based on the Intel 82540, 82541PI, 82542, 82543, 82544, 82546, 82546EB and 82547 controller chips:

Intel PRO/1000 CT Network Connection (82547)

Intel PRO/1000 F Server Adapter (82543)

Intel PRO/1000 Gigabit Server Adapter (82542)\*

Intel PRO/1000 GT Desktop Adapter (82541PI)

Intel PRO/1000 MF Dual Port Server Adapter (82546)  
Intel PRO/1000 MF Server Adapter (82545)  
Intel PRO/1000 MF Server Adapter (LX) (82545)  
Intel PRO/1000 MT Desktop Adapter (82540)  
Intel PRO/1000 MT Desktop Adapter (82541)  
Intel PRO/1000 MT Dual Port Server Adapter (82546)  
Intel PRO/1000 MT Quad Port Server Adapter (82546EB)  
Intel PRO/1000 MT Server Adapter (82545)  
Intel PRO/1000 T Desktop Adapter (82544)  
Intel PRO/1000 T Server Adapter (82543)  
Intel PRO/1000 XF Server Adapter (82544)  
Intel PRO/1000 XT Server Adapter (82544)

The [gx](#) driver supports Gigabit Ethernet adapters based on the Intel 82542 and 82543 controller chips:

Intel PRO/1000 Gigabit Server Adapter (82542)  
Intel PRO/1000 F Server Adapter (82543)  
Intel PRO/1000 T Server Adapter (82543)

The [hme](#) driver supports the on-board Ethernet interfaces of many Sun UltraSPARC workstation and server models. Cards supported by the [hme](#) driver include:

Sun PCI SunSwift Adapter  
Sun SBus SunSwift Adapter `` ( hme" and ``SUNW,hme")  
Sun PCI Sun100BaseT Adapter 2.0  
Sun SBus Sun100BaseT 2.0  
Sun PCI Quad FastEthernet Controller  
Sun SBus Quad FastEthernet Controller

The [my](#) driver provides support for various NICs based on the Myson chipset. Supported models include:

Myson MTD800 PCI Fast Ethernet chip  
Myson MTD803 PCI Fast Ethernet chip  
Myson MTD89X PCI Gigabit Ethernet chip

**Broadcom BCM4401 based Fast Ethernet adapters ([bfe](#) driver) \***

The [re](#) driver supports RealTek RTL8139C+, RTL8169, RTL8169S and RTL8110S based Fast Ethernet and Gigabit Ethernet adapters including:

Alloy Computer Products EtherGOLD 1439E 10/100 (8139C+) \*  
Compaq Evo N1015v Integrated Ethernet (8139C+) \*  
Corega CG-LAPCIGT Gigabit Ethernet (8169S) \*  
Gigabyte 7N400 Pro2 Integrated Gigabit Ethernet (8110S) \*  
PLANEX COMMUNICATIONS Inc. GN-1200TC (8169S) \*  
Xterasys XN-152 10/100/1000 NIC (8169) \*

The [ixgb](#) driver supports the following cards:

Intel PRO/10GbE LR Server Adapter \*  
Intel PRO/10GbE SR Server Adapter \*

# Index

## - A -

Activation 5  
 Add missing drive 146  
 Add missing drives 149  
 Additional Recovery Options 182  
 Advanced Data Recovery 43  
 Advanced RAID 5 Layouts 106  
 Advanced RAID 6 Layout 106  
 Allocation 298  
 Apple CoreStorage/FileVault/Fusion Drive Volumes 152  
 Apple RAIDs 149  
 Apply changes immediately 96

## - B -

Bad Sectors 326  
 Bad Sectors settings
 

- Default read retries count 12
- Pattern to fill bad blocks 12
- Set default read retries count for all drives 12

 Basic File Recovery 20  
 Binary (byte to byte copy)
 

- Copy range 213
- Copy whole object 213
- Offset 213
- Size 213

 BitLocker Drive Encryption 140  
 BitLocker System Drive Encryption 140  
 BitLocker ToGo 140  
 Block order 96  
 Broken File Name
 

- Prompt: 83
- Rename and change all invalid symbols to: 83
- Skip 83

 Broken File Name options
 

- Change all invalid symbols to 20
- Edit broken symbols only 20
- File name 20
- New name 20

 Button
 

- Clear All 326

Mark 326  
 Recover 326  
 Save to File 326  
 Select All 326

Buttons

- Add 43
- Advanced 43
- Apply 96
- Auto Detect 127
- Choose Variants 127
- Code pages 298
- Connect to Remote 6, 170
- Create Image 6, 73
- Create Region 6, 70
- Create virtual volume sets or RAIDs 6, 96
- Fast Partition Search 6
- File Mask 41
- Go! 304
- Known File Types 43
- Next Pattern 298
- OK 304
- Open Drive Files 6, 20
- Open Image 6, 73
- Open in Hex Editor 43
- Open Local Drives 6, 170
- Preview 34
- Previous Pattern 298
- Recover 20
- Recover Marked 20
- Refresh 6
- Remove 6
- Rename 20
- Rename All 20
- Reset 43
- Save Changes 298
- Scan 6, 43
- Set for all 41
- Set Runtime Image 221
- Skip 20
- Skip All 20
- Stop 6
- Stop Runtime Imaging 221

## - C -

Connect to R-Studio settings
 

- Allow connection from any address 172
- Allow connection from the host 172

- Connect to R-Studio settings
    - Password 172
    - Port 172
    - Server 172
  - Connecting over the Internet 172
  - Connecting to DeepSpar Disk Imager™ manually 234
  - Contact information and technical support 4
  - Create menu
    - Add Empty Space 96
    - Add Missing Drive 96
    - Copy object to... 213
    - Create Exclusive Region 71
    - Create Region 70
    - Create Virtual Block RAID & Autodetect 96
    - Create Virtual Mirror 96
    - Create Virtual Volume Set 96
  - Creating and saving your own RAID configuration 90
  - Creating Custom Patterns 308
  - Creating Startup Disks for Mac and Linux Computers 343
  - Cross-linked folders 320
  - Custom Recovery Lists 188
  - Customizing File Types 60, 62
  - Customizing File Types-II 65
- D -**
- Data Copy in Text/hexadecimal editor 307
  - Data Formats and Multipliers 323
  - Data Recovery Issues 320
  - Data Recovery on HFS/HFS+ File System 324
  - Data recovery over network 165
    - Connect to the remote computer 170
  - Data Recovery Using R-Studio 18
  - DDI Drive Map 234
  - DeepSpar Disk Imager 234
  - DeepSpar RapidSpar 243
  - DeepSpar USB Stabilizer 238
  - Description Files for RAID Configuration 134
  - Devices to Store Recovered Files 356
  - Dialog box
    - Forensic Log Settings 246
  - Dialog boxes
    - Broken File Name 20
    - Connect to Remote Computer 170
    - Connect to R-Studio 167, 169, 172
    - Copy Options 213
    - Create Exclusive Region 71
    - Create Image 73
    - Create Region 70
    - Edit Block RAID Layout Presets 90
    - Edit User's File Types 60
    - Export Recovery List 85
    - File mask 41
    - File Types 43
    - Files with bad sectors 326
    - Fill 298
    - Find/Mark 31
    - Go to 304
    - Go To Offset 304
    - Memory Usage 327
    - Multi-volume image 73
    - Online Activation 5
    - Open Scan Information File 43
    - Please configure R-Studio Agent for Mac 167
    - Please configure R-Studio Agent for Windows 166
    - Please Register 5
    - Preset name 90
    - Raid Parameters Detection 127
    - Recover 20, 81, 170
    - Recover (Advanced) 83
    - R-Studio Agent for Linux Configuration 169
    - Save Scan Information File 43
    - Scan 43
    - Scan Information 43
    - Search 304
    - Settings 12
    - There is not enough space on the disk 20
    - Waiting for remote connection 172
  - Direct 298
  - Disk and Volume Managers 140
  - Disk Image Formats 325
  - Drive menu
    - Connect to DDI 234
    - Connect To Remote 170
    - Create Image 73
    - Open Drive Files 20
    - Open Drive Files Sorted By 82
    - Open Image File 73
    - Open Local Drives 170
    - Open Scan Informaiton 43
    - Real File System Structure 82
    - Recover All Files 81
    - Remove Scan Informaiton 43

Drive menu  
 Save Scan Informaiton 43  
 Scan 43  
 Drive scan 6, 43  
 Drives Copy Wizard 213

## - E -

Edit menu  
 Bookmarks 304  
 Fill 298  
 Find 304  
 Find Next 304  
 Find Previous 304  
 Find Template Signature Next 298  
 Find Template Signature Previous 298  
 Save Changes 298

Editor tabs  
 Allocation 298  
 Direct 298  
 Std 298  
 Unlimited 298

Enable Forensic Mode 246  
 Event log 42  
 Exclusive Region 71  
 Exclusive Region options  
 Exclusive Regions 71  
 Offset: 71  
 Size: 71  
 Start: 71

Export Recovery List 85  
 Extended Information Recovery 323

## - F -

Fast Search for Lost Partitions 59  
 File Already Exists  
 Overwrite 83  
 Overwrite Bigger 83  
 Overwrite Older 83  
 Overwrite Smaller 83  
 Prompt 83  
 Rename 83  
 Skip 83  
 File Information (R-Studio Technician/T80+) 185  
 File Maps 219  
 File mask options

Date 41  
 Deleted files 41  
 Existing files 41  
 Hide symbolic links 41  
 Match case 41  
 Show empty folders 41  
 Size from/up to 41  
 Use advanced options 41

File menu  
 Close All Previews 34  
 Export Recovery List 85  
 Goto Target 320  
 Import Recovery List 85  
 Preview 34  
 Recover 20  
 Recover Marked 20  
 Rescan 320  
 Set As Default Target 320  
 Show Files in HexEditor 307  
 View/Edit 298

File search 6  
 File signature properties 60  
 File Systems settings  
 Default encoding for Ext2/Ext3/Ext4/UFS volumes 12  
 Default encoding for HFS volumes 12  
 Disable any sorting 12  
 Minimize drive access 12  
 Show deleted empty folders 12  
 File Type Signature Specification 62, 65

File Types  
 Clear All 43  
 Reload User's File Types 43  
 Reset to Recommended 43  
 Revert to Default 43  
 Select All 43  
 Set as Default 43

File Types properties 60  
 Files and Sectors 307  
 Find and Mark Multiple Files 82  
 Find options  
 All Files and Folders 31  
 Bad sectors 31  
 Date 31  
 Deleted files 31  
 Existing files 31  
 File Extensions 31  
 File Id 31

Find options  
Files and Folders 31  
Find/Mark mode 31  
Find/mark objects only in real paths, ignore links to folders 31  
Look in 31  
Match case 31  
Recovery chances 31  
Regular Expressions 31  
Runtime image 31  
Size from/up to 31  
Use advanced options 31  
Find/Mark options  
Find all 31  
Find first 31  
Find last 31  
Find next 31  
Find previous 31  
Mark all 31  
Set for all 31  
Unmark all 31  
Finding Previous File Versions 34  
Firewall 172  
Forensic Data Collection Audit Log 246  
Forensic Mode 246  
Found offsets pane 127  
Fusion Drive Component Tab 152

## - H -

Help menu  
Change Language 6  
Hidden Attribute  
Keep 83  
Prompt 83  
Remove 83  
Hidden Devices 183  
Hidden Devices settings 183

## - I -

I/O Monitor 220  
Image 73  
Image options  
Additional output folders 73  
Create scan information file 73  
Estimated size 73

Image name 73  
Image split size 73  
Image type 73  
Password 73  
Pattern to fill bad blocks 73  
Plain image 73  
Post Actions Options 73  
Read retries 73  
Image type:  
Byte by byte image to a file 73  
Byte to byte image to a physical disk 73  
Compressed image (R-Drive Image compatible) 73  
VMDK (VmWare Virtual Machine Disk) 73  
IntelligentScan Technology 319  
Introduction to R-Studio 1

## - K -

Known File Types settings  
Clear All 12  
Edit User's File Types 12  
Reload User's File Types 12  
Reset 12  
Reset to Recommended 12  
Select All 12

## - L -

Linux LVM 161  
Linux mdadm RAID's 159  
Log settings  
Disk 12  
Error 12  
File name 12  
File System 12  
Files 12  
Information 12  
Maximum messages in the Event Log 12  
Network 12  
Partition 12  
Recover 12  
Save log to file 12  
Success 12  
Warning 12

## - M -

- Mac Pro RAID 106
- Main settings
  - Auto-refresh Drive Tree 12
  - Check for update 12
  - Debug Mode 12
  - Enable Write 12, 213, 298
  - File name 12
  - HexView templates path 12
  - Location 12
  - Max changes buffer size 12
  - Reset all hidden notifications 12
  - User's file mask presets 12
  - User's file types 12
  - User's RAID layout 12
- Mass file recovery 81
- Mass File Recovery Options 83
- Memory Usage 327
  - Automatic 12
  - Limit usage of the process memory by 12
  - Process Memory 327
  - System Memory Physical 327
  - System Memory Swap 327
- Messages
  - Cannot connect 166
  - Double-click a logical disk... 20
  - Too many files... 20, 81, 327
- Mirrors 92
- Missing Drive 96
- Mount options
  - Drive letter 163
  - Mount as: 163
- Mounting Virtual Objects in the System 163
- Multi-pass Imaging 226
- Multitasking 179

## - N -

- NAT 172
- Nested and Non-Standard RAID Levels 116

## - O -

- Object Copy 213
- Offset 96

Opening several disks/partitions in one tab 30

## - P -

- Panels
  - Files 20
  - Folders 20
  - Log 20, 42
  - Main 6
- Panes
  - Bookmarks 298
  - Data Interpreter 298
  - Find Results 298
  - Template 298
- Pattern Example I 311
- Pattern Example II 315
- Portable version of R-Studio Technician 177
- Previewing files 34
- Properties tab
  - Active FAT copy 328
  - Block Size 328
  - Blocks Per Volume 328
  - Boot Directory Cluster 328
  - Buffer Alignment 328
  - Bus Type 328
  - Cluster size 328
  - Creator OS 328
  - Device Identification 328
  - Drive Control 328
  - Drive Type 328
  - Estimated Size 328
  - Ext2/3/4FS Information 328
  - Fat Bits (12,16,32) 328
  - FAT Information 328
  - First Cluster Offset 328
  - First FAT Offset 328
  - First SuperBlock Offset 328
  - I/O Tries 328
  - I/O Unit 328
  - Index Block Size 328
  - INodes Per Volume 328
  - Int13 Drive Number 328
  - Int13 Extension Version 328
  - Last Check Time 328
  - Last Mount Time 328
  - Last Write Time 328
  - LDM Component ID 328
  - LDM Disk AltName 328



## Properties tab

LDM Disk DriveHint 328  
 LDM Disk GUID 328  
 LDM Disk ID 328  
 LDM DiskGroup GUID 328  
 LDM Host GUID 328  
 LDM Partition ID 328  
 LDM Volume GUID 328  
 LDM Volume ID 328  
 Major version 328  
 Maximum transfer 328  
 MFT Mirror Position 328  
 MFT position 328  
 MFT record size 328  
 Minor version 328  
 Name 328  
 NTFS Information 328  
 Number of FAT Copies 328  
 Offset of Logical Disk 328  
 OS object 328  
 Parsed Boot Records 328  
 Parsed File Entries 328  
 Partition number 328  
 Partition Offset 328  
 Partition Size 328  
 Partition Type 328  
 Physical Drive Geometry 328  
 Raid Block Size 328  
 Recognized Ext2/3/4FS 328  
 Recognized FAT 328  
 Recognized NTFS 328  
 Root Directory Length 328  
 Root Directory Offset 328  
 R-Studio driver 328  
 SCSI Address 328  
 Sector Size 328  
 Size 328  
 Size of One FAT Table 328  
 Supposed Parents Count 328  
 Volume size 328

**- Q -**

Questionable folders 320

**- R -**

RAID 0 92  
 RAID 1 92  
 RAID 4 96  
 RAID 5 96  
 RAID 5 Operations 96  
 RAID block size 96  
 RAID consistency 129  
 RAID for HP Servers 103  
 RAID Parameter Detection 127  
 RAID with Parity Delays 103  
 RAID10 (1+0) 116  
 RAID1E 118  
 RAID5E 120  
 RAID5EE 122  
 RAID6E 124  
 Recover options
 

- Additional Output Folders 182
- Condense successful restoration events: 20
- Do not recover duplicate files from Extra Found Files 20
- Ignore file mask: 20
- Local computer 170
- Open local folder (folders) when done 20
- Post Actions Options 182
- Recover all marked files 20
- Recover alternative data streams: 20
- Recover extended attributes: 20
- Recover metafiles 20
- Recover real folders structure 20
- Recover security: 20
- Recovered only masked marked files 20
- Remote computer 170
- Restore folder structure: 20
- Restore from root 20

 Recovery Lists 85  
 Region 70  
 Region options
 

- Drive size 70
- Size 70
- Start 70

 Registration 5  
 Regular expressions 42  
 Remote install 166  
 Reverse RAID of a RAID 232  
 Reverse RAID of an Object 231

- Reverse RAIDs 230
  - Rows count 96
  - R-Studio Agent 165
  - R-Studio Agent Emergency 165, 363
    - Contact information and technical support 363
    - Creating Startup Disks 363
    - Disk Controllers 372
    - Hardware Compatibility List 372
    - Installing R-Studio Agent Emergency Startup Media Creator 363
    - Network Cards 382
    - Starting a Computer with the R-Studio Agent Emergency Startup Disk 369
  - R-Studio Agent for Linux 169
  - R-Studio Agent for Mac 167
  - R-Studio Agent for Mac main panel 167
  - R-Studio Agent for Windows 166
  - R-Studio Agent for Windows main panel 166
  - R-Studio Emergency 335
    - Contact Informaiton and Technical Support 335
    - Creating Startup Disks 337
    - Disk Images 349
    - Disk Scan 348
    - Emergency agent 350
    - File Recovery 346
    - Hardware Compatibility List 358
    - Installing R-Studio Emergency Startup Media Creator 336
    - Log 356
    - Network Drives 355
    - Operation 343
    - Properties and Text/Hexadecimal Viewer 354
    - Safely Remove Hardware icon 346
    - Searching for a File 347
    - Starting a Computer with the R-Studio Emergency Startup Disks 344
    - Technical Information 354
  - R-Studio Emergency Startup Media Creator 337, 363
  - R-Studio features 1
  - R-Studio switches 327
  - R-Studio Technician/T80+ 175
  - Runtime Imaging 221
  - Drive size 43
  - File Systems 43
  - Offset 43
  - Post Actions Options 43
  - Save to File 43
  - Scan Areas 43
  - Size 43
  - Start 43
  - Search options
    - ANSI 304
    - Exhaustive search 304
    - From Address 304
    - From current position 304
    - From start position 304
    - HEX 304
    - Match case 304
    - Not Equal 304
    - OEM 304
    - Reverse 304
    - Search at offset 304
    - UNICODE 304
  - Searching for a File 31
  - Sector Map Files 220
  - Settings
    - Bad Sectors 12
    - File Systems 12
    - Known File Types 12
    - Log 12
    - Main 12
    - Memory Usage 12
    - Symbolic Links 12
  - Shortcut menu
    - Add Custom offset 127
    - Add Empty Space 96
    - Add Missing Drive 96
    - Add missing drives 161
    - Add to RAID 96
    - Always recalculate 323
    - Check RAID consistency... 129
    - Clear Log... 42
    - Close drive 30
    - Copy (Column Name) 42
    - Copy as "ANSI" 307
    - Copy as "Binary data" 307
    - Copy as "UNICODE" 307
    - Copy as File Signature 307
    - Copy Editor Display 307
    - Copy Selected Text 42
- S -**
- S.M.A.R.T. Info 6
  - Scan options

## Shortcut menu

- Create Exclusive Region 71
  - Create Image File 73
  - Create Region 70
  - Create Reverse RAID 231, 232
  - Create Virtual Mirror 96
  - Create Virtual RAID5 96
  - Create Virtual Stripe Set 96
  - Create Virtual Volume Set 96
  - Cross Linked Folders 320
  - Edit 70, 71
  - Exclude area 70
  - Export Recovery List 85
  - File mask 41
  - Find Next 31
  - Find Previous 31
  - Find Previous Versions of the File 34
  - Find Template Signature Next 298
  - Find Template Signature Previous 298
  - Find/Mark 31
  - Get Info 20
  - Go Target 320
  - Import Recovery List 85
  - Links 320
  - Log Filter... 42
  - Mark 20, 31
  - Mark All 20
  - Merge Down 43
  - Merge Down All 43
  - Merge Selected 43
  - Mount 73
  - No recalculate 323
  - Open Drive Files 20
  - Open Drive Files Sorted By 82
  - Open Scan Information 43
  - Preview 31, 34
  - Real File System Structure 82
  - Recheck Recovery Chances 20
  - Recover 20, 31
  - Recover All Files 81
  - Recover Marked 20
  - Remove All Scanned Information 43
  - Remove Region 70
  - Save Log to File... 42
  - Save Scan Information 43
  - Scan 43
  - Select From 298
  - Select To 298
  - Set As Default Target 320
  - Set Runtime Image 221
  - Show Files In Tab 30
  - Show password 170
  - Stop Runtime Imaging 221
  - Toggle Bookmark 298
  - Units type recalculate 323
  - Unlock encrypted drive 152
  - Unmark 20
  - Unmark All 20
  - Unmount 73
  - View/Edit 298
  - Smart drive copy
    - Copy all partitions onto original places 213
    - Expand/Shrink partition to whole drive 213
    - Fixed active partition 213
    - One partition after another 213
  - Smart partition copy
    - Copy to: 213
    - Copy without stretching 213
    - Free space before 213
    - Partition size 213
    - Partition type 213
  - Startup Media Troubleshooting Options 337
  - Std 298
  - Storage Pools 146
  - Stripe Sets 92
  - Symbolic links 320
    - Don't show symbolic links by default (Technician version) 186
    - Link conversion (Default) 12, 186
    - Recovery as it is (Technician version) 186
    - Show folder symbolic links as links to their targets, without target content (Technician version) 186
    - Symbolic links display settings 186
    - Symbolic links recovery options 186
  - Symlinks 320
  - Syntax of a Description File for RAID Configurations 129
  - System Requirements 4
- T -
- Tabs
    - Parents 96
    - Properties 328
  - Technical Information and Troubleshooting 319

Text/hexadecimal editor 297  
 ANSI/OEM/UNICODE/UNICODE+ 298  
 Save to Hexadecimal File 298

#### Tools menu

Debug Mode 327  
 File mask 41  
 Find 31  
 Find All 31  
 Find Next 31  
 Find Previous 31  
 Goto 298  
 Mark All 20  
 Save Changes 298  
 Save to Binary File... 298  
 Save to Hexadecimal File 298  
 Select All 298  
 Settings 12  
 Unmark All 20  
 TPM 140

## - U -

Unlimited 298

## - V -

#### View menu

ANSI 298  
 Arrange 20  
 Bookmarks View 298  
 Contents Columns 20  
 Data Interpreter View 298  
 Device View 6  
 Devices 6  
 Event Log 6, 20  
 Files panel 20  
 Folders panel 20  
 Log panel 20  
 OEM 298  
 Parents Tab 6  
 Properties 6, 328  
 Properties Tab 6  
 Properties View 6, 298  
 Scan Information Tab 6  
 Sectors View 298  
 Status bar 6, 20  
 Template View 298

Toolbar 6, 20, 298  
 UNICODE 298  
 UNICODE+ 298

#### Virtual Disk Formats

aff 325  
 dmg 325  
 e01/ewf 325  
 RDR 325  
 VDI 325  
 VHD/VHDX 325  
 VMDK 325

Virtual volume sets and RAIDs 90

Volume sets and RAIDs 90

Volume Sets, Stripe Sets, and Mirrors 92

## - W -

Windows Storage Spaces 146

#### Window

RAID consistency check 129  
 RAID Sequence 106

Windows Dynamic Disks 144

Wiping Objects 80

Working with RAID 6 Presets

Reed-Solomonr 100

Working with RAID6 (Double Xor) Presets 98